

Avaya Context Store Snap-in Reference

Release 3.2 October 2016

Notice

While reasonable efforts have been made to ensure that the information in this document is complete and accurate at the time of printing, Avaya assumes no liability for any errors. Avaya reserves the right to make changes and corrections to the information in this document without the obligation to notify any person or organization of such changes.

Documentation disclaimer

"Documentation" means information published in varying mediums which may include product information, operating instructions and performance specifications that are generally made available to users of products. Documentation does not include marketing materials. Avaya shall not be responsible for any modifications, additions, or deletions to the original published version of Documentation unless such modifications, additions, or deletions were performed by or on the express behalf of Avaya. End User agrees to indemnify and hold harmless Avaya, Avaya's agents, servants and employees against all claims, lawsuits, demands and judgments arising out of, or in connection with, subsequent modifications, additions or deletions to this documentation, to the extent made by End User.

Link disclaimer

Avaya is not responsible for the contents or reliability of any linked websites referenced within this site or Documentation provided by Avaya. Avaya is not responsible for the accuracy of any information, statement or content provided on these sites and does not necessarily endorse the products, services, or information described or offered within them. Avaya does not guarantee that these links will work all the time and has no control over the availability of the linked pages.

Warranty

Avaya provides a limited warranty on Avaya hardware and software. Refer to your sales agreement to establish the terms of the limited warranty. In addition, Avaya's standard warranty language, as well as information regarding support for this product while under warranty is available to Avaya customers and other parties through the Avaya Support website: <u>https://support.avaya.com/helpcenter/</u> <u>getGenericDetails?detailId=C20091120112456651010</u> under the link

getGenericDetails?detailId=C20091120112456651010 under the link "Warranty & Product Lifecycle" or such successor site as designated by Avaya. Please note that if You acquired the product(s) from an authorized Avaya Channel Partner outside of the United States and Canada, the warranty is provided to You by said Avaya Channel Partner and not by Avaya.

"Hosted Service" means an Avaya hosted service subscription that You acquire from either Avaya or an authorized Avaya Channel Partner (as applicable) and which is described further in Hosted SAS or other service description documentation regarding the applicable hosted service. If You purchase a Hosted Service subscription, the foregoing limited warranty may not apply but You may be entitled to support services in connection with the Hosted Service as described further in your service description documents for the applicable Hosted Service. Contact Avaya or Avaya Channel Partner (as applicable) for more information.

Hosted Service

THE FOLLOWING APPLIES ONLY IF YOU PURCHASE AN AVAYA HOSTED SERVICE SUBSCRIPTION FROM AVAYA OR AN AVAYA CHANNEL PARTNER (AS APPLICABLE), THE TERMS OF USE FOR HOSTED SERVICES ARE AVAILABLE ON THE AVAYA WEBSITE, HTTPS://SUPPORT.AVAYA.COM/LICENSEINFO UNDER THE LINK "Avaya Terms of Use for Hosted Services" OR SUCH SUCCESSOR SITE AS DESIGNATED BY AVAYA, AND ARE APPLICABLE TO ANYONE WHO ACCESSES OR USES THE HOSTED SERVICE. BY ACCESSING OR USING THE HOSTED SERVICE, OR AUTHORIZING OTHERS TO DO SO, YOU, ON BEHALF OF YOURSELF AND THE ENTITY FOR WHOM YOU ARE DOING SO (HEREINAFTER REFERRED TO INTERCHANGEABLY AS "YOU" AND "END USER"), AGREE TO THE TERMS OF USE. IF YOU ARE ACCEPTING THE TERMS OF USE ON BEHALF A COMPANY OR OTHER LEGAL ENTITY, YOU REPRESENT THAT YOU HAVE THE AUTHORITY TO BIND SUCH ENTITY TO THESE TERMS OF USE. IF YOU DO NOT HAVE SUCH AUTHORITY, OR IF YOU DO NOT WISH TO ACCEPT THESE TERMS OF USE, YOU MUST NOT ACCESS OR USE THE HOSTED SERVICE OR AUTHORIZE ANYONE TO ACCESS OR USE THE HOSTED SERVICE.

Licenses

THE SOFTWARE LICENSE TERMS AVAILABLE ON THE AVAYA WEBSITE. HTTPS://SUPPORT.AVAYA.COM/LICENSEINFO UNDER THE LINK "AVAYA SOFTWARE LICENSE TERMS (Avaya Products)" OR SUCH SUCCESSOR SITE AS DESIGNATED BY AVAYA, ARE APPLICABLE TO ANYONE WHO DOWNLOADS, USES AND/OR INSTALLS AVAYA SOFTWARE, PURCHASED FROM AVAYA INC., ANY AVAYA AFFILIATE, OR AN AVAYA CHANNEL PARTNER (AS APPLICABLE) UNDER A COMMERCIAL AGREEMENT WITH AVAYA OR AN AVAYA CHANNEL PARTNER. UNLESS OTHERWISE AGREED TO BY AVAYA IN WRITING AVAYA DOES NOT EXTEND THIS LICENSE IF THE SOFTWARE WAS OBTAINED FROM ANYONE OTHER THAN AVAYA, AN AVAYA AFFILIATE OR AN AVAYA CHANNEL PARTNER; AVAYA RESERVES THE RIGHT TO TAKE LEGAL ACTION AGAINST YOU AND ANYONE ELSE USING OR SELLING THE SOFTWARE WITHOUT A LICENSE. BY INSTALLING, DOWNLOADING OR USING THE SOFTWARE, OR AUTHORIZING OTHERS TO DO SO, YOU, ON BEHALF OF YOURSELF AND THE ENTITY FOR WHOM YOU ARE INSTALLING, DOWNLOADING OR USING THE SOFTWARE (HEREINAFTER REFERRED TO INTERCHANGEABLY AS "YOU" AND "END USER"), AGREE TO THESE TERMS AND CONDITIONS AND CREATE A BINDING CONTRACT BETWEEN YOU AND AVAYA INC. OR THE APPLICABLE AVAYA AFFILIATE ("AVAYA").

Avaya grants You a license within the scope of the license types described below, with the exception of Heritage Nortel Software, for which the scope of the license is detailed below. Where the order documentation does not expressly identify a license type, the applicable license will be a Designated System License. The applicable number of licenses and units of capacity for which the license is granted will be one (1), unless a different number of licenses or units of capacity is specified in the documentation or other materials available to You. "Software" means computer programs in object code, provided by Avaya or an Avaya Channel Partner, whether as stand-alone products, pre-installed on hardware products, and any upgrades, updates, patches, bug fixes, or modified versions thereto. "Designated Processor" means a single stand-alone computing device. "Server" means a Designated Processor that hosts a software application to be accessed by multiple users. "Instance" means a single copy of the Software executing at a particular time: (i) on one physical machine; or (ii) on one deployed software virtual machine ("VM") or similar deployment.

License types

Designated System(s) License (DS). End User may install and use each copy or an Instance of the Software only on a number of Designated Processors up to the number indicated in the order. Avaya may require the Designated Processor(s) to be identified in the order by type, serial number, feature key, Instance, location or other specific designation, or to be provided by End User to Avaya through electronic means established by Avaya specifically for this purpose.

Concurrent User License (CU). End User may install and use the Software on multiple Designated Processors or one or more Servers, so long as only the licensed number of Units are accessing and using the Software at any given time. A "Unit" means the unit on which Avaya, at its sole discretion, bases the pricing of its licenses and can be, without limitation, an agent, port or user, an e-mail or voice mail account in the name of a person or corporate function (e.g., webmaster or helpdesk), or a directory entry in the administrative database utilized by the Software that permits one user to interface with the Software. Units may be linked to a specific, identified Server or an Instance of the Software.

Named User License (NU). You may: (i) install and use each copy or Instance of the Software on a single Designated Processor or Server per authorized Named User (defined below); or (ii) install and use each copy or Instance of the Software on a Server so long as only authorized Named Users access and use the Software. "Named User", means a user or device that has been expressly authorized by Avaya to access and use the Software. At Avaya's sole discretion, a "Named User" may be, without limitation, designated by name,

corporate function (e.g., webmaster or helpdesk), an e-mail or voice mail account in the name of a person or corporate function, or a directory entry in the administrative database utilized by the Software that permits one user to interface with the Software.

Heritage Nortel Software

"Heritage Nortel Software" means the software that was acquired by Avaya as part of its purchase of the Nortel Enterprise Solutions Business in December 2009. The Heritage Nortel Software is the software contained within the list of Heritage Nortel Products located at <u>https://support.avaya.com/LicenseInfo</u> under the link "Heritage Nortel Products" or such successor site as designated by Avaya. For Heritage Nortel Software, Avaya grants Customer a license to use Heritage Nortel Software provided hereunder solely to the extent of the authorized activation or authorized usage level, solely for the purpose specified in the Documentation, and solely as embedded in, for execution on, or for communication with Avaya equipment. Charges for Heritage Nortel Software may be based on extent of activation or use authorized as specified in an order or invoice.

Copyright

Except where expressly stated otherwise, no use should be made of materials on this site, the Documentation, Software, Hosted Service, or hardware provided by Avaya. All content on this site, the documentation, Hosted Service, and the product provided by Avaya including the selection, arrangement and design of the content is owned either by Avaya or its licensors and is protected by copyright and other intellectual property laws including the sui generis rights relating to the protection of databases. You may not modify, copy, reproduce, republish, upload, post, transmit or distribute in any way any content, in whole or in part, including any code and software unless expressly authorized by Avaya. Unauthorized reproduction, transmission, dissemination, storage, and or use without the express written consent of Avaya can be a criminal, as well as a civil offense under the applicable law.

Virtualization

The following applies if the product is deployed on a virtual machine. Each product has its own ordering code and license types. Note that each Instance of a product must be separately licensed and ordered. For example, if the end user customer or Avaya Channel Partner would like to install two Instances of the same type of products, then two products of that type must be ordered.

Third Party Components

"Third Party Components" mean certain software programs or portions thereof included in the Software or Hosted Service may contain software (including open source software) distributed under third party agreements ("Third Party Components"), which contain terms regarding the rights to use certain portions of the Software ("Third Party Terms"). As required, information regarding distributed Linux OS source code (for those products that have distributed Linux OS source code) and identifying the copyright holders of the Third Party Components and the Third Party Terms that apply is available in the products, Documentation or on Avaya's website at: https:// support.avaya.com/Copyright or such successor site as designated by Avaya. The open source software license terms provided as Third Party Terms are consistent with the license rights granted in these Software License Terms, and may contain additional rights benefiting You, such as modification and distribution of the open source software. The Third Party Terms shall take precedence over these Software License Terms, solely with respect to the applicable Third Party Components to the extent that these Software License Terms impose greater restrictions on You than the applicable Third Party Terms.

The following applies only if the H.264 (AVC) codec is distributed with the product. THIS PRODUCT IS LICENSED UNDER THE AVC PATENT PORTFOLIO LICENSE FOR THE PERSONAL USE OF A CONSUMER OR OTHER USES IN WHICH IT DOES NOT RECEIVE REMUNERATION TO (i) ENCODE VIDEO IN COMPLIANCE WITH THE AVC STANDARD ("AVC VIDEO") AND/OR (ii) DECODE AVC VIDEO THAT WAS ENCODED BY A CONSUMER ENGAGED IN A PERSONAL ACTIVITY AND/OR WAS OBTAINED FROM A VIDEO PROVIDER LICENSED TO PROVIDE AVC VIDEO. NO LICENSE IS GRANTED OR SHALL BE IMPLIED FOR ANY OTHER USE. ADDITIONAL INFORMATION MAY BE OBTAINED FROM MPEG LA, L.L.C. SEE HTTP://WWW.MPEGLA.COM.

Service Provider

THE FOLLOWING APPLIES TO AVAYA CHANNEL PARTNER'S HOSTING OF AVAYA PRODUCTS OR SERVICES. THE PRODUCT OR HOSTED SERVICE MAY USE THIRD PARTY COMPONENTS SUBJECT TO THIRD PARTY TERMS AND REQUIRE A SERVICE PROVIDER TO BE INDEPENDENTLY LICENSED DIRECTLY FROM THE THIRD PARTY SUPPLIER. AN AVAYA CHANNEL PARTNER'S HOSTING OF AVAYA PRODUCTS MUST BE AUTHORIZED IN WRITING BY AVAYA AND IF THOSE HOSTED PRODUCTS USE OR EMBED CERTAIN THIRD PARTY SOFTWARE, INCLUDING BUT NOT LIMITED TO MICROSOFT SOFTWARE OR CODECS, THE AVAYA CHANNEL PARTNER IS REQUIRED TO INDEPENDENTLY OBTAIN ANY APPLICABLE LICENSE AGREEMENTS, AT THE AVAYA CHANNEL PARTNER'S EXPENSE, DIRECTLY FROM THE APPLICABLE THIRD PARTY SUPPLIER.

WITH RESPECT TO CODECS, IF THE AVAYA CHANNEL PARTNER IS HOSTING ANY PRODUCTS THAT USE OR EMBED THE G.729 CODEC, H.264 CODEC, OR H.265 CODEC, THE AVAYA CHANNEL PARTNER ACKNOWLEDGES AND AGREES THE AVAYA CHANNEL PARTNER IS RESPONSIBLE FOR ANY AND ALL RELATED FEES AND/OR ROYALTIES. THE G.729 CODEC IS LICENSED BY SIPRO LAB TELECOM INC. SEE SIPRO.COM/CONTACT.HTML. THE H.264 (AVC) CODEC IS LICENSED UNDER THE AVC PATENT PORTFOLIO LICENSE FOR THE PERSONAL USE OF A CONSUMER OR OTHER USES IN WHICH IT DOES NOT RECEIVE REMUNERATION TO: (I) ENCODE VIDEO IN COMPLIANCE WITH THE AVC STANDARD ("AVC VIDEO") AND/OR (II) DECODE AVC VIDEO THAT WAS ENCODED BY A CONSUMER ENGAGED IN A PERSONAL ACTIVITY AND/OR WAS OBTAINED FROM A VIDEO PROVIDER LICENSED TO PROVIDE AVC VIDEO. NO LICENSE IS GRANTED OR SHALL BE IMPLIED FOR ANY OTHER USE. ADDITIONAL INFORMATION FOR H.264 (AVC) AND H.265 (HEVC) CODECS MAY BE OBTAINED FROM MPEG LA, L.L.C. SEE HTTP:// WWW.MPEGLA.COM

Compliance with Laws

You acknowledge and agree that it is Your responsibility for complying with any applicable laws and regulations, including, but not limited to laws and regulations related to call recording, data privacy, intellectual property, trade secret, fraud, and music performance rights, in the country or territory where the Avaya product is used.

Preventing Toll Fraud

"Toll Fraud" is the unauthorized use of your telecommunications system by an unauthorized party (for example, a person who is not a corporate employee, agent, subcontractor, or is not working on your company's behalf). Be aware that there can be a risk of Toll Fraud associated with your system and that, if Toll Fraud occurs, it can result in substantial additional charges for your telecommunications services.

Avaya Toll Fraud intervention

If You suspect that You are being victimized by Toll Fraud and You need technical assistance or support, call Technical Service Center Toll Fraud Intervention Hotline at +1-800-643-2353 for the United States and Canada. For additional support telephone numbers, see the Avaya Support website: <u>https://support.avaya.com</u> or such successor site as designated by Avaya.

Security Vulnerabilities

Information about Avaya's security support policies can be found in the Security Policies and Support section of <u>https://</u>support.avaya.com/security.

Suspected Avaya product security vulnerabilities are handled per the Avaya Product Security Support Flow (<u>https://support.avaya.com/css/P8/documents/100161515</u>).

Downloading Documentation

For the most current versions of Documentation, see the Avaya Support website: <u>https://support.avaya.com</u>, or such successor site as designated by Avaya.

Contact Avaya Support

See the Avaya Support website: <u>https://support.avaya.com</u> for product or Hosted Service notices and articles, or to report a problem

with your Avaya product or Hosted Service. For a list of support telephone numbers and contact addresses, go to the Avaya Support website: <u>https://support.avaya.com</u> (or such successor site as designated by Avaya), scroll to the bottom of the page, and select Contact Avaya Support.

Trademarks

The trademarks, logos and service marks ("Marks") displayed in this site, the Documentation, Hosted Service(s), and product(s) provided by Avaya are the registered or unregistered Marks of Avaya, its affiliates, its licensors, its suppliers, or other third parties. Users are not permitted to use such Marks without prior written consent from Avaya or such third party which may own the Mark. Nothing contained in this site, the Documentation, Hosted Service(s) and product(s) should be construed as granting, by implication, estoppel, or otherwise, any license or right in and to the Marks without the express written permission of Avaya or the applicable third party.

Avaya is a registered trademark of Avaya Inc.

All non-Avaya trademarks are the property of their respective owners. Linux $^{\otimes}$ is the registered trademark of Linus Torvalds in the U.S. and other countries.

Contents

Chapter 1: Introduction	
· Purpose	
Prerequisites	
Document changes since last issue	
How to navigate this document	11
Chapter 2: Context Store Snap-in services and features	
Context Store overview	
Data model mapping	
Context lease time	
Sensitive data	13
Context Store architecture overview	
Avaya Breeze [™] overview	15
Topology	
New in this release	17
Context Store services	
Context Store Manager	19
Context Store REST	
Context Store SOAP	
Context Store Query	21
Context Store Screen Pop	
Context Store Notifications	
Context Store Rules	
Context Store Event Streams	
Context Store Java SDK	
Context Store JavaScript SDK	
Context Store features	
Data grid	
External Data Mart	
Context aliasId for additional indexing	
Audit trail	
Upsert method	
Pluggable Data Connector	
Context Store Task Type for Engagement Designer	
Authorization	
Scalability overview	43
Chapter 3: Interoperability	
Avaya product compatibility	
Hardware requirements	
Software requirements	50

Chapter 4: Licensing	51
License requirements	51
Configuring Context Store licenses	51
Chapter 5: Context Store Deployment	53
Certified deployment scenarios	
Key customer configuration information	. 53
Context Store deployment checklist	
Verifying the status of Avaya Breeze [™] servers	57
Loading a snap-in service	58
Configuring a cluster and installing mandatory services	59
Cluster attributes field descriptions	. 61
Installing the optional Context Store services	64
Verifying a successful deployment	
Assigning permissions to an authorization client	66
Geo redundancy and External Data Mart deployment	66
Enabling Geo redundancy in Context Store	67
Enabling External Data Mart	. 68
Enabling External Data Mart provisioning	69
Deploying Context Store PDC on Orchestration Designer	70
Deploying CS Task Type	71
Overview of CS Task Type deployment	
Installing CS Task Types SVAR on Engagement Designer	
Non-OSGi workflows	
Updating non-OSGi workflows	. 73
Context Store Upgrade overview	
Context Store uninstallation and deletion	
Context Store uninstallation overview	
Deleting a Context Store cluster	
Uninstalling an optional snap-in service	
Deleting a snap-in service	
Chapter 6: Administering Context Store	77
Configuring attributes for a service	
CSManager attribute descriptions	
CSRest attribute descriptions	
CSScreenPop attribute descriptions	
CSNotifications attribute descriptions	
CSRules attribute descriptions	
CSQuery attribute descriptions	
CSSoap attribute descriptions	
Chapter 7: High availability	
High availability within a cluster	
Geo redundancy	
Context Store Geo redundancy overview	. 89

Third party load balancer configuration requirement	
Architecture	
Service preservation	
Session preservation	
Notifications in Context Store Geo	93
Failover support	95
Chapter 8: Performance	97
Capacity and scalability specification	. 97
Chapter 9: Security	98
Överview	98
Secure space	98
Configuring space security	99
Certificate-based authentication	99
Port utilization	100
Chapter 10: Troubleshooting	. 101
Troubleshooting overview	
Alarms	
Overview	101
ContextStoreManager_CS_EVT_1	102
CSManager_CS_EVT_2	. 102
ContextStoreManager_CS_EVT_3	103
CSManager_CS_EVT_4	. 104
CSManager_CS_EVT_5	. 104
Events	. 105
Overview	105
CS_AUDIT_5	. 105
CS_AUDIT_7	. 106
CS_AUDIT_8	. 106
CS_AUDIT_10	107
CS_AUDIT_11	107
CS_AUDIT_13	
Logging	
Context Store log files	
Frequently asked questions	
Where do I find documentation for Context Store?	
Where do I get plugins, SDKs, and sample resources for Context Store?	
How do I verify if Context Store is successfully deployed?	
How do I determine the appropriate size for my Context Store deployment?	
How do I verify if Context Store is successfully connected to the External Data Mart?	
How do I determine the appropriate size for my External Data Mart deployment?	112
How do I submit requests to CSRest interface if access through external ReST client is	440
blocked?	
Problems with data grid deployment	. 113

How do I verify if connection between geo-redundant clusters is successfully established?. Why is the CSRest interface returning 503 Service Temporarily Unavailable for all my	114
requests?	114
Why can't I set the state of my cluster to Accept New Service ?	114
What is the maximum lease time permitted for a context?	115
Why can't I access Context Store from a web client?	115
Why is Customer Journey unable to retrieve data?	115
Why is the External Data Mart not working?	115
Chapter 11: Related resources	118
Documentation	118
Finding documents on the Avaya Support website	119
Training	120
Support	120

Chapter 1: Introduction

Purpose

This document describes the Context Store Snap-in characteristics and capabilities, including feature descriptions, interoperability, and performance specifications. The document also provides instructions on deploying, configuring, and troubleshooting the Context Store services.

For information about Avaya Breeze[™], Avaya Aura[®] System Manager, and Avaya Engagement Designer, see the respective product documentation at the Avaya Support website: <u>http://www.avaya.com/support</u>.

This document is intended for anyone who wants to install, configure, and administer Context Store.

Prerequisites

- Users who want to deploy and administer the Context Store services must have a working knowledge of Avaya Breeze[™] and System Manager.
- Users who want to deploy Context Store must have means to access the Avaya PLDS to be able to download the Context Store services.
- Developers who want to use the Context Store services and SDKs must have a working knowledge of the technologies and products referenced in the document.
- Users who want to use Context Store Pluggable Data Connector (PDC) must have access to Avaya Aura[®] Orchestration Designer.
- Users who want to use Context Store Task Type must have access to Avaya Engagement Designer.

Document changes since last issue

Issue	Date	Summary of changes
1	October 2016	Initial issue for Release 3.2 of Context Store.

Table continues...

Issue	Date	Summary of changes
2	December 2016	Second issue for Release 3.2 of Context Store.
		Added the new attribute Use 'Public Machine Provisioning' for Context Store data-grid in the CSManager attribute descriptions page.
		• Added the newly supported databases Microsoft SQL Server and Oracle in the Context Store Query and the Customer journey visualization topics.
		• Added two new questions, Why is Customer Journey unable to retrieve data? and Why is the External Data Mart not working? to the Frequently asked questions topic.
		Added groupId related changes to the appropriate topics.
		• Updated the Customer journey visualization and Viewing customer journey on a standalone Customer Journey application topics with touchpoint and groupId related enhancements.
3	March 2017	Third issue for Release 3.2 of Context Store.
		• Removed references to the temporary attribute Use 'Public Machine Provisioning' added in issue 2 of this document. The references were removed from the CSManager attribute descriptions table and Context Store Event Streams topic.
		• Added the following new entries to the Frequently asked questions section:
		- Problems with data grid deployment
		- What is the maximum lease time permitted for a context?
		 How do I determine the appropriate size for my Context Store deployment?
		 How do I determine the appropriate size for my External Data Mart deployment?
		Added a new request type to the Context Store Query topic.
		Updated the database creation commands in the Creating database tables for External Data Mart topic.
4	May 2017	Fourth issue for Release 3.2 of Context Store
		• Added a new topic, Updating database tables in the External Data Mart section.
		Made minor updates in the Cluster attributes field descriptions topic.
		Updated the Database requirements and planning topic with the supported MS SQL server driver version.

How to navigate this document

You can navigate back and forth within the PDF file using keyboard shortcut keys in Adobe Acrobat Reader. For example, you might click a link to a related topic while following a procedure and might want to go back to the original location or topic on which you clicked the link.

Follow these simple keyboard shortcuts to navigate this document easily:

- To navigate back to the original topic, press Alt and the Left Arrow keys together.
- To go to the previous page, press the Left Arrow key.
- To go to the next page, press the Right Arrow key.
- To go to the first page, press the Home key.
- To go to the last page of the document, press the End key.

Chapter 2: Context Store Snap-in services and features

Context Store overview

Context Store provides a flexible and easy integration among different applications, providing a centralized solution to store context information. Many applications can use the abstract context concepts that Context Store provides.

A context entry in Context Store has the following main elements:

- contextId: A text field that contains a unique identification for the context. You can specify the contextId while adding the context entry in Context Store. If you do not specify a contextId while creating a context, the system generates a unique id.
- Data: The data field in a context entry is an abstract map with multiple key/value pairs. Keys in the data field must be unique. Multiple identical keys in the same request results in the values being overwritten with the last key. To provide a better structure and organization of context data, Context Store also supports inner maps in context data fields.
- groupId: An optional text field that creates a logical group of related context entries. You can specify the groupId while adding the context entry in Context Store or while updating an existing context entry.
- aliasId: An optional field that contains unique identifications for the aliases associated with a Context object. You can specify aliasId/aliasIds while adding the context entry in Context Store or you can update an existing context entry to have aliasIds.
- routingId (rid): A parameter used in a Geo-redundant deployment to route requests by the load balancer. If you specify a value for the rid parameter, Context Store assigns the value to the routingId. The default value is 0. The rid query parameter for a request, if provided, cannot be left blank.

Data model mapping

Context Store maps your data model into the Context Store data model. While mapping your data model into the Context Store abstract model of key/value pairs in Context Store, you must consider the following factors:

- Context size: Context Store uses a high performance in-memory data grid. To take advantage of this environment and to achieve high performance, keep the context size minimal. For more information see, <u>Capacity and scalability specification</u> on page 97.
- Pointers rather than actual data: Use Context Store as a centralized solution to share information and not to store data. For example, use Context Store to store the location and name of a user's picture, not to store the actual picture.
- Structure: Use the inner-map structure of Context Store to structure the data properly.

Context lease time

Context Store preserves a context entry for a specific time defined as the *lease time* of the context. Any Context Store client can renew this lease time, or time-to-live, at any moment. The clients can also define the context lease time while creating a context and specify different lease time values for different scenarios.

A Context Store client can also provide the lease query parameter, but leave the value blank. In this case, Context Store uses the default configured lease for the context object.

To use the Context Store in-memory data grid efficiently, you must evaluate the contexts' lease time requirements before implementing Context Store. This analysis helps to understand the memory requirements and usage, and to provide a Context Store solution that can store all information as long as required.

For details about the average latency of a request, see <u>Capacity and scalability specification</u> on page 97. To store information for a longer duration, you can use an external database.

Important:

• Data can be retrieved through CSRest in order to persist it through a third-party solution using Context Store WebServices API or by using the Context Store database mirror service.

Sensitive data

Context Store supports customer-encrypted data. The keys in the key/values pairs must not be encrypted as character restrictions apply on these identifiers. For more information on character restrictions, see ReST API documentation. While creating a context entry, the Context Store clients can mark context values as sensitive. Context Store does not include the sensitive values in logs, alarms, and reports.

😵 Note:

The ReST API documentation can be accessed by browsing to an instance of the Context Store ReST snap-in by typing http://clusterIP/services/CSRest/. This online documentation is only available through HTTP on either Firefox or Chrome browsers; Internet Explorer is not supported. A copy of the full API documentation is provided in the appendix section of Avaya Context Store Snap-in Developer Guide.

Context Store architecture overview


Avaya Context Store Snap-in provides a centralized data cache to the applications in a contact center. Using a distributed cache, Context Store offers a scalable, reliable, and fault-tolerant system to store context information. Context Store also provides services for making changes to the context information. You must deploy Context Store as a service on Avaya Breeze[™] 3.2. A high availability (HA) deployment requires an Avaya Breeze[™] cluster containing a minimum of 2 Avaya Breeze[™] nodes.

Context Store offers the following functionality:

- A standard RESTful Web Service API to third-party components to set and get context information.
- Storage of context information using multiple key-value data.
- Storage of context information using external identifiers, such as the UCID generated by Session Border Controllers.
- Scalable solution with high availability using a distributed cache.
- Management and monitoring services through the integration of Avaya Breeze[™].
- Security through the integration of Avaya Breeze[™].

Context Store offers the flexibility to be deployed on Avaya Breeze[™] nodes of varying sizes. You can deploy Context Store on a single node or on a cluster of up to five nodes.

The following diagram shows the high-level architecture for the Context Store configuration of a cluster with three instances of Avaya Breeze^M. This is a sample illustration. You can have a single-node cluster or cluster of up to five nodes.



Avaya Breeze[™] overview

Avaya Breeze[™] provides a virtualized and secure application platform where Workflow developers and Java programmers can develop and dynamically deploy advanced collaboration capabilities that extend the power of Avaya Aura[®]. Customers, business partners, and Avaya developers can use the platform as the deployment vehicle for their snap-ins.

Avaya Breeze[™] acts as the platform for many Avaya products such as the Avaya Oceana[™] Solution, Presence Services, Engagement Designer, and Context Store.

Avaya Breeze[™] provides the following benefits:

• Customers, partners, and Avaya organizations can rapidly develop snap-ins and applications that are deployed on Avaya Breeze[™].

- Developers can focus on building the collaboration snap-ins they need, without the need to develop a robust platform on which snap-ins are deployed and invoked.
- A robust Software Development Kit (SDK) with an easy-to-use API. Developers need not understand the details of call processing to develop new capabilities.
- The ability to perform operations such as:
 - Intercepting calls in to and out of the enterprise.
 - Redirecting calls to an alternate destination.
 - Blocking calls and optionally playing an announcement to the caller.
 - Changing the presented caller ID of the calling or called party.
- The ability to place an outbound call for the purpose of playing announcements and collecting digits.
- The ability to invoke web services for added functionality.
- The ability to expose webpages and web services for invocation by remote browsers and applications.
- A Collaboration Bus that allows snap-ins to leverage each others' capabilities through pointto-point and publish/subscribe messaging patterns.
- A Common Data Manager framework that snap-ins use to access common information stored on System Manager.
- Connector snap-ins that provide access to email and Scopia (conferencing) host applications.


Multiple SMS snap-ins are available from Snapp Store.

- The ability to add or replace Trust and Identity Certificates for increased security.
- Tools that log and monitor operations and provide troubleshooting support.
- High availability. For more information on high availability, see the *High Availability* section in *Avaya Breeze*[™] *Overview and Specification*.
- Third party ability to create custom Connectors that provide access to their (external) application or service.

Avaya Breeze[™] is a powerful snap-in delivery platform that provides Unified Communications and Contact Center customers and partners the ability to quickly deliver capabilities using the skill sets of today's enterprise and cloud application developers.

Topology

The following diagram provides a high-level illustration of the components of an Avaya Breeze[™] solution.



New in this release

Release 3.2 of Avaya Context Store Snap-in offers the following new capabilities:

- Customer journey visualization: To allow customers to use the audit trail data to produce a
 visualization of a customer's interactions. With this feature, you can visualize each point in
 the customer journey represented by an interaction with a touchpoint. You can also retrieve
 customer data stored in an external data mart (EDM) using the CSQuery Snap-in. A multi
 session journey can also be visualized. In a multi session journey, a groupId is used to link
 disparate contexts into a single journey.
- Context Store Query (CS Query) Snap-in: To allow customers to retrieve context data that is unavailable in CS data grid from an EDM. The CSQuery snap-in provides a REST interface to collect all associated context data from the external data mart in JSON format. Using this interface, you can generate audit trails or retrieve instances of context data from the historical context data stored in the associated EDM database.
- Authorization Service: To provide authorized access to context data using Avaya Breeze[™] Authorization Service (AS) snap-in. The user-privilege mapping that an administrator creates

for users or applications is stored in the AS snap-in and a bearer token is generated for the users or the applications. This token must be provided with all context store requests.

- Context Store SOAP API: To provide a Simple Object Access Protocol (SOAP)-compliant interface. All the Context Store operations available through the CSRest interface are also available through the SOAP API. Both the CSRest and SOAP interfaces are deployed on the same Avaya Breeze[™] cluster.
- Context Store JavaScript SDK: To provide a client library with which users can write software that will interact with a deployed Context Store system through the CSRest interface. The JavaScript SDK is a .js file within a zip file and is distributed through Avaya DevConnect.

For Release 3.2 of Avaya Context Store Snap-in, the following features are modified:

- Audit trail: To enable retrieval of data from an EDM using the CSQuery Snap-in. You must configure the EDM user name and EDM password to retrieve information from an EDM database.
- Context Store ReST API: .To retrieve aliasIds associated with a contextId and contextIds associated with an aliasId. You can also retrieve metadata of a context entry using contextId or aliasId. Four new ReST URL paths are introduced in Context Store ReST API for this purpose.

Context Store services

Context Store provides the following snap-in services:

- Context Store Manager (CSManager)
- Context Store Rest (CSRest)
- Context Store Screen Pop (CSScreenPop)
- Context Store Notifications (CSNotifications)
- Context Store Rules (CSRules)
- Context Store Event Streams (Streams)
- Context Store SOAP (CSSoap)
- Context Store Query (CSQuery)

You must install these services from the Avaya Breeze[™] **Element Manager** page in System Manager to the Context Store cluster. The system installs the services in all the Avaya Breeze[™] servers that are in the Context Store cluster.

Related links

<u>Context Store Manager</u> on page 19 <u>Context Store REST</u> on page 19 <u>Context Store SOAP</u> on page 20 <u>Context Store Query</u> on page 21 <u>Context Store Notifications</u> on page 23 <u>Context Store Rules</u> on page 24 <u>Context Store Event Streams</u> on page 25 <u>Context Store Java SDK</u> on page 26 Context Store JavaScript SDK on page 27

Context Store Manager

CSManager initializes the configuration of Context Store, External Data Mart, the data grid spaces for Context Store, alarming, Event streaming, and Geo redundancy.

When you install the CSManager snap-in service on Avaya Breeze[™], the system deploys a CSManager service in each Avaya Breeze[™] server in the cluster. The service creates the base for Context Store.

Although the CSManager snap-in service is deployed on every node, only one node is elected to be the Master CSManager, which handles functions such as alarms. If the node elected to be Master CSManager fails, another node is immediately elected.

😵 Note:

Using System Manager, you must create a simple network management protocol (SNMP) target profile and assign the profile to your network monitoring system (NMS).

Related links

<u>Context Store services</u> on page 18 <u>Configuring a cluster and installing mandatory services</u> on page 59

Context Store REST

Context Store implements a RESTful web services interface, the CSRest service, to provide the required services to the clients.

The CSRest service focuses on system resources, including addressing and transferring of resource states. CSRest identifies the resources using HTTP URLs and returns the output to the clients using JavaScript Object Notation (JSON).

Using the contextId, or optionally an aliasId, through the CSRest snap-in service, you can create, read, update and delete context entries and values. You can also group related context entries together by assigning a groupId when the context entry is created or updating an existing context entry with a groupId.

The required fields for Context Store object are as follows:

- contextId: A unique identifier for the context. If you do not specify a contextId while creating a context, the system generates a unique id. A contextId can be of maximum 255 characters.
- data: Represented as key/value pairs.

Basic request example

😵 Note:

On multiple node deployments, CSRest requests must be submitted through the clusterIP, which ensures that the requests are load balanced across all the servers in a cluster. For single node deployments, enter the Avaya Breeze[™] node security IP instead of the cluster IP.

Request name	URL	HTTP request type	Content
Create a new context object	https://clusterIP/ services/CSRest/cs/ contexts/	POST	{"contextId":"sampleContext", data": {"key1":"value1","key2":"value2","ke y3":"value3"}}
Retrieve an existing context object	<pre>https://clusterIP/ services/CSRest/cs/ contexts/sampleContext</pre>	GET	

For more information about CSRest, and the complete API documentation, see Avaya Context Store Snap-in Developer Guide.

Related links

<u>Context Store services</u> on page 18 <u>Configuring a cluster and installing mandatory services</u> on page 59 <u>CSRest attribute descriptions on page 83</u>

Context Store SOAP

Context Store SOAP is an optional snap-in service that provides the required Context Store services to the clients. All the Context Store operations available through the CSRest interface are also available through this Simple Object Access Protocol (SOAP)-compliant interface. A Web Service Definition Language (WSDL) file and schema define the CSSoap interface.

Both the CSRest and SOAP interfaces are deployed on the same Avaya Breeze[™] cluster. Context Store routes the requests received through the SOAP interface to the CSRest interface on the local Avaya Breeze[™] node. The CSSoap snap-in sends the SOAP XML envelopes to the clients as defined by the schema in the snap-in WSDL.

You can download the CSSoap WSDL from http://clusterIP/services/CSSoap/wsdl/cs/Cs.wsdl.

😵 Note:

In a geo-redundant deployment, you cannot download the CSSoap WSDL through the IP address of a customer-provided geo load balancer. You must download the WSDL directly from either of the clusters in the configuration and then update with the IP address of the geo load balancer.

Avaya Aura[®] Contact Center (AACC) uses Context Store SOAP interface as a web interface to send and receive context data. The SOAP interface is compatible with the Database Integration

Wizard (DIW) application of AACC. So the SOAP web service calls can be invoked from the AACC script.

CSSoap snap-in is installed as an SVAR file. For more information, see the Installing the optional Context Store services topic.

For more information about CSSOAP and the complete API documentation, see Avaya Context Store Snap-in Developer Guide.

Related links

<u>Context Store services</u> on page 18 <u>CSSoap attribute descriptions</u> on page 87 <u>Installing the optional Context Store services</u> on page 64 <u>Context Store Rules</u> on page 24 <u>Configuring attributes for a service</u> on page 77 Installing the optional Context Store services on page 64

Context Store Query

Context Store Query (CSQuery) is an optional snap-in service that you can use to retrieve context data that is unavailable in the Context Store data grid from an external data mart (EDM).

The CSQuery snap-in provides a REST interface to collect all associated context data from the EDM in the JSON format. Using the CSQuery REST interface, you can generate audit trails or retrieve instances of context data from the context data stored in the associated EDM database. With this collected data, you can visualize a customer journey represented by an interaction with a touchpoint.

You must configure the **EDM: Database username** and **EDM: Database password** attributes to retrieve information from an EDM.

The CSQuery snap-in is installed as an SVAR file. For more information, see the Installing the optional Context Store services topic.

The supported databases are:

- PostgreSQL
- Microsoft SQL Server
- Oracle

Note:

You must enable the Audit trail feature to use the CSQuery snap-in.

Retrieving customer interaction details with CSQuery snap-in

You can retrieve customer interaction details using a contextId or a groupId. Use contextId to retrieve a single customer journey and use groupId to retrieve multiple customer journeys. You can also retrieve the latest context entry in EDM. When you provide the following URLs with the correct parameters, the CSQuery snap-in displays the requested customer interaction details:

Purpose	URL
Get EDM entry audit data using contextId.	<pre>http(s)://clusterIP/services/CSQuery/edm/contexts/ audit/{contextId}</pre>
Get EDM entry audit data using groupId.	<pre>http(s)://clusterIP/services/CSQuery/edm/contexts/ audit/groups/{groupId}</pre>
Get EDM entry audit data for group using contextId	<pre>http(s)://clusterIP/services/CSQuery/edm/contexts/ audit/groups/context{contextId}</pre>
Get the latest EDM context entry.	<pre>http(s)://clusterIP/services/CSQuery/edm/contexts/ {contextId}</pre>

You can also use additional parameters to refine your search. For example, http:// clusterIP/services/CSQuery/edm/contexts/audit/{contextId}? rid=<rid>&after=<timestamp>&before=<timestamp>&data=true. The following table describes the parameters and the expected results:

Parameter	Displays result	
rid	Context entries with a routingId that matches the parameter.	
before	Context entries with a timestamp later than the timestamp of the before parameter.	
after	Context entries with a timestamp earlier than the timestamp of the after parameter.	
touchpoint	Context entries with a touchpoint that matches the parameter.	
	😵 Note:	
	You can search with multiple touchpoint parameters. Use " " symbol to add multiple touchpoints. For example, touchpoint=EP AGENT Web	
data	The context entry's instance data map.	

Related links

Context Store services on page 18 Customer journey visualization on page 35 Audit trail on page 39 CSQuery attribute descriptions on page 87 Installing the optional Context Store services on page 64 Context Store Rules on page 24

<u>Configuring attributes for a service</u> on page 77 <u>Installing the optional Context Store services</u> on page 64

Context Store Screen Pop

CSScreenPop is an optional service which you can use to either view, add, or update the data stored in Context Store in a format that you prefer. CSScreenPop uses both predefined and user

defined rules to process the available data. The snap-in then returns the processed information to the clients in the specified format. Context Store supports the following formats for returning data: HTML, XML, JSON, URL, REDIRECT, WA, and MAILTO. You can configure these output formats to view the context data in a web browser.

CSScreenPop provides a rules engine with which you can manipulate the view of context data stored in Context Store. To configure the rules, all you must do is add the rule in System Manager, and the rules engine updates the rule set. The rules engine can change the output format, and filter the results based on the keys in the context. For more information about how to create user-configurable rules or make use of the existing predefined rules, see *Avaya Context Store Snap-in Developer Guide*.

The CSScreenPop URLs can easily integrate with other applications, such as Avaya One-X Agent. For information for how to configure CSScreenPop with Avaya one-X[®] Agent, see *Avaya Context Store Snap-in Developer Guide*.

Context Store Notifications

CSNotifications is an optional service in Context Store, using which you can receive notifications for any change in a context entry. Before you install CSNotifications, you must first install the mandatory services CSManager and CSRest. The CSNotifications service uses the CSRest service to send an event trigger to up to five registered subscribers through the REST interface. To use this service, you must:

- Obtain a suitable client that can handle REST messages.
- Create a service on your application server so that the client can handle the REST event messages.
- Subscribe for the CSNotifications service by configuring the CSNotifications attributes in System Manager.

To subscribe for a notification, you must configure the CSNotifications attributes using the System Manager Cluster attributes page and provide:

- The URI of the endpoint that you want to configure for receiving notifications.
- The tenantId of the contexts for which you want to receive notifications.
- The groupId of the contexts for which you want to receive notifications.

You can configure up to five subscriptions. You can enable or disable a subscription by specifying a value of true or false for the attribute *enabled*. You can disable or enable a subscription dynamically. However, to change any other configuration of a subscription, you must first disable the subscription, make the changes, and then enable the subscription again.

Context Store creates the notifications in JSON format and provides the following information:

Field	Description
subscriptionId	The subscription ID for which Context Store generated the notification.

Table continues...

Field	Description
contextId	The ID of the context which change of status has triggered the notification.
tenantId	The tenantId of the context entry for which Context Store has generated this notification.
groupId	The groupId of the context entry for which Context Store has generated this notification.
aliasIds	The aliasIds that are associated with the context entry for which Context Store has generated this notification.
operation	The operation that triggered this notification. The operation can be write, update, or delete.
versionId	The version of the context entry for which Context Store has generated this notification. Context Store increases this value after each update.
	The versionId of a context increases on each interaction, such as Update, Get, Put, and Delete, with a context. However, the versionId does not increase for the requests of Get Audit by ContextId and Get Audit by AliasId.
createTimestamp	The time stamp when the context entry was created.
updateTimestamp	The time stamp when the context entry was last updated.
data	The data that is associated with the contextId.

If Context Store cannot send the notification to the client endpoint for any reason, Context Store retries to send the same notification to the same endpoint up to three times in a 1 minute period. After the third try, if Context Store is still unable to send the notification, Context Store disables the subscription for that endpoint. To enable that subscription again, you must first disable the subscription by setting the CSNotifications attribute *enabled* as *false*. After you verify that the endpoint is available for receiving notifications, you can enable the subscription by setting the value of the *enabled* attribute to *true*.

Related links

<u>Context Store services</u> on page 18 <u>CSNotifications attribute descriptions</u> on page 86 <u>Installing the optional Context Store services</u> on page 64 <u>Context Store Rules</u> on page 24 <u>Configuring attributes for a service</u> on page 77

Context Store Rules

Context Store Rules is an optional service snap-in with which you can integrate Context Store with CRM systems by triggering an Engagement Designer workflow.

Context Store provides a flag to determine if the data must be sent to the rules engine. The rules engine then determines the workflow that must be triggered by raising the Avaya Breeze[™] event that the workflow is listening for.

You can load the CRM integration CSRules snap-in using the standard System Manager SVAR loading mechanism. The CRM Integration CSRules snap-in has:

- User-defined business rules to determine if it must trigger a rule and which Avaya Breeze[™] event it must raise.
- Rules that you can trigger using the following CSRest API calls, if you add the parameter rules=true to the URL:
 - Create Context (POST)
 - Update Context (PUT)

You can define five rules and trigger five independent workflows based on the rules.

To configure the CRM integration snap-in, you must create a unique Avaya Breeze[™] event and an Engagement Designer workflow. You must also configure the Engagement Designer cluster to allow HTTP requests. For more information about CRM integration, see *Avaya Context Store Snap-in Developer Guide*.

Related links

<u>Context Store services</u> on page 18 <u>Configuring attributes for a service</u> on page 77 <u>CSRules attribute descriptions</u> on page 86

Context Store Event Streams

With the Event Streams feature, Context Store provides more fine-grained and personalized event notifications than the CSNotifications feature. Users, such as an agent or agent supervisor, can register for customized event streams. The users can filter the event streams by identifiers of the context, such as contextId, or specific keys or key/value pairs that the context object contains. The users can register for the event streams using a web interface. Context Store delivers the applicable event notifications to the users through the same interface. A sample JavaScript web interface is provided for the Event Streams feature. For more information about the Event Streams feature and the usage of the web interface, see *Avaya Context Store Snap-in Developer Guide*.

To use the Event Streams feature, you must install the Streams SVAR on the Context Store cluster and enable the feature using the **Event Stream: Enable Event Streaming** field on the CSManager page. For more information about installing the SVAR file, see <u>Installing the optional</u> <u>Context Store services</u> on page 64.

The Event Streams feature requires space in the data grid to operate. Hence, while enabling the Event Streams feature, you must reduce the maximum memory allocation in the **ContextStoreSpace DataGrid Settings** field by 6 GB. You must also restart the cluster after reducing the memory allocation.

Feature restrictions

Context Store does not support filtering event notifications by aliasIds. The limitation is because of the inability to filter by complex objects, such as json objects.

The number of users or streams must be limited to five registered streams. You can either have five users with one stream each or fewer users with multiple streams each.

The Event Streams feature is supported only on environments equal to or greater than 64 GB x 3 nodes.

You cannot enable the feature on systems on which traffic is running.

Related links

<u>Context Store services</u> on page 18 <u>CSManager attribute descriptions</u> on page 77 <u>Context Store Rules</u> on page 24 <u>Configuring attributes for a service on page 77</u>

Context Store Java SDK

Context Store provides a Java SDK to facilitate the access to the Context Store services. The Context Store Java SDK provides a client library for users to write software that will interact with a deployed Context Store system.

The Context Store Java SDK is a zip file and is distributed through Avaya DevConnect at http://www.devconnectprogram.com/site/global/products_resources/avaya_breeze/avaya_snap_ins/context_store/overview/index.gsp.

The directory structure of the Context Store Java SDK, ContextStore <version> SDK.zip, is as follows:

```
CS Event Stream Client
 - app
    - assets
   - css
- font
- js
- scripts
 browser components
  boiler plate client.html
 - index.html
 - README.txt
 CS ReST
   - CS ReST Clients
       - cs-rest-csharp-client (rest clients for testing purposes only)
           - packages
- SimpleClient
             - README.txt
            - SimpleClient.sln
 - CS SDK
    - CS SDK API
         conf (logging configuration file)
       - conf (logging configuration file,
- examples (an example integration class using the SDK)

    examples (an example integration class using the SDK)
    lib (the dependencies that are required to use the SDK)

         - cs-sdk-api-<version>-SNAPSHOT.jar
         -cs-sdk-api-3.4-SNAPSHOT-javadoc.jar
         - developer guide.html
     ....- LICENSE.txt
   - CS SDK Docs (the SDK documentation)
        - developer guide.html
```

Access to Context Store through the Java SDK requires client authentication. Authentication is established using certificates. The Java SDK requires users to supply the following system properties at runtime: Keystore location, Keystore password, Truststore location, and Truststore password.

For more information about the guidelines for the Context Store SDK use, see Avaya Context Store Snap-in Developer Guide.

Related links

Context Store services on page 18

Context Store JavaScript SDK

Context Store provides a JavaScript SDK to facilitate access to the Context Store services. The JavaScript SDK provides a client library using which users can write software that interacts with a deployed Context Store system through the CSRest interface.

The SDK provides service interfaces using the created instance of the AvayaDataStoreClient class. With the JavaScript SDK, you can access all Context Store operations that are available through CSRest.

The Context Store JavaScript SDK is a .js file within a zip file and is distributed through Avaya DevConnect at <u>http://www.devconnectprogram.com/site/global/products_resources/avaya_breeze/avaya_snap_ins/context_store/overview/index.gsp</u>.

The zip file contains:

- AvayaDataStoreClient-<version>.min.js: The Context Store JavaScript SDK library
- test_app directory: The directory that contains a sample client for accessing the Context Store JavaScript SDK
- README.txt: Instructions for SDK usage
- License.txt: User license

For more information about JavaScript API operations and guidelines for Context Store JavaScript SDK usage, see *Avaya Context Store Snap-in Developer Guide*.

Related links

Context Store services on page 18

Context Store features

Data grid

Context Store uses an in-memory data grid for storing the context entries for a specific time. Using the CSManager service of Context Store, you can specify for how long you want the context

entries to be present in the data grid. In addition to providing a storage space, the data grid functionality provides the following advantages to Context Store:

- Efficiency by providing an in-memory data cache for a fast and reliable response in any operation on context data
- Scalability by distributing load across all available resources through the built-in scalability features
- · High availability by hot backup for zero downtime
- Consistency by maintaining data integrity with 100% transactional data handling

External Data Mart

External Data Mart overview

External Data Mart is an optional feature of the CSManager snap-in service using which you can connect and persist data from Context Store to an external, customer provided database. To use this feature, you must install any of the Context Store supported databases, create the required tables, and configure the relevant parameters in the CSManager section.

Important:

If you make any configuration changes in External Data Mart after installation, you must restart all servers in the cluster.

Note:

For Release 3.2 of Context Store, ContextStore space fails to deploy if you try to contact an EDM with incorrect login details or if there are connection issues. If ContextStore space fails to deploy, provide the accurate login credentials or solve the connection issues and then restart all the nodes in the Context Store cluster simultaneously.

Context Store provisioning and persistence of data to EDM

While both Context Store provisioning and the persistence of data to EDM features share the same **CSManager** EDM attributes, they operate independently of one another. You can enable either Context Store provisioning or persistence of data to EDM or both on a cluster.

- Provisioning Context Store with data from the database: The Context Store space queries the database on start-up for entries in the database and writes them into its data grid with infinite leases.
- Persistence of data to an external database: The EDM Mirror Service listens to the replication channel of the Context Store data grid and adds entries to database for every operation on a flagged context.

😵 Note:

• The EDM Mirror Service captures any context added to Context Store, including the contexts added using the provisioning feature, and persists the operation table of the EDM database.

• If you have enabled both the EDM persistence and EDM provisioning features, the system writes the provisioned context data into the CS_OPERATION table each time the cluster is restarted. That means that there will be near-identical entries in the CS_OPERATION table, the only differentiation being the time-stamp of the object.

Supported databases

Context Store supports the following three databases for External Data Mart:

- PostgreSQL 9.1 and later
- Oracle 11g and later
- Microsoft SQL Server 2008 and later

When you install CSManager, External Data Mart tries to validate the database tables *CS_OPERATION, CS_PROVISION* and *GENERATED_KEYS* in the external database that you have configured. If the tables are not present or if the tables do not match the required database schema, the installation of the External Data Mart feature fails. If External Data Mart fails to install, Context Store raises an alarm to System Manager.

Database requirements and planning

You must configure the External Data Mart feature while configuring the CSManager service. Consider the following factors before you configure External Data Mart:

- Database: You must install a database server that Context Store supports.
 - Note:

The Context Store database owner requires a minimum of 100 connections to the external database.

- Network:
 - The database must be in the same LAN as the Avaya Breeze[™] host where you have installed Context Store.
- Database user: You must create a user account for Context Store to connect to the database. The user account must have permissions to read and write database entries for Context Store.



- If you are using the Microsoft SQL server: The db user configured for the EDM feature must have database ownership or the system administrator privileges for this connection to be successful. Also, from the security profile of the database user, you must set the Context Store database as the default database.
- The tested and supported MS SQL server driver version for Context Store 3.3 is version 42 (sqljdbc42.jar), which is available in Microsoft JDBC Drivers 6.0.
- Database space: You must plan the space requirements for your database. You cannot
 modify the database and External Data Mart configurations after you install the CSManager
 service. The average size of a context is 2 KB in raw JSON data. However, this size might
 differ significantly depending on your configuration.

- Create database tables: You must create the required database tables before you install External Data Mart. Ensure to create the database tables in the correct database that you intend to use with Context Store.
- Verification: After you create the database tables, perform the following tasks to verify the database and the tables:
 - Test the database connection.
 - Log in to the database and verify if you have created the database tables successfully.
 - Test if the user account that you have created for Context Store has the required permissions.

For the specific instructions on the verification process, see the documentation of your database.

Creating database tables for External Data Mart

About this task

External Data Mart supports PostgreSQL, Oracle, and Microsoft SQL Server. To use the External Data Mart feature, you must use any of these three databases and create the required database tables. For more information about External Data Mart, see <u>External Data Mart overview</u> on page 28.

Context Store provides only the PostgreSQL database by default. However, you can configure Context Store to write to Oracle and Microsoft SQL databases. For more information about configuring the additional databases, see <u>Loading JDBC driver to System Manager</u> on page 35.

😵 Note:

If you are using the Microsoft SQL server: The db user configured for the EDM feature must have database ownership or the system administrator privileges for this connection to be successful. Also, from the security profile of the database user, you must set the Context Store database as the default database.

Procedure

- 1. Log in to the external database that you are using for External Data Mart using the database user account you have created for Context Store.
- 2. Create database tables for External Data Mart.

Depending on the database that you have, enter the relevant commands provided in the following table:

Database	Commands
PostgreSQL	If the tables CS_OPERATION, CS_PROVISION and GENERATED_KEYS exist, drop the tables:
	DROP TABLE IF EXISTS CS_OPERATION CASCADE; DROP TABLE IF EXISTS CS_PROVISION CASCADE; DROP TABLE IF EXISTS GENERATED_KEYS CASCADE;

Database	Commands		
	Create the tables: CREATE TABLE CS_OPERATION (PERSIST_CONTEXT_UID INT8 NOT NULL, CONTEXT_ID VARCHAR(255) NOT NULL, ROUTING_ID VARCHAR(255) NOT NULL, TENANT_ID VARCHAR(255), DATA_JSON TEXT, IDENTIFIER VARCHAR(255), META_JSON TEXT, GROUP_ID VARCHAR(255), OPERATION_TYPE VARCHAR(10), UPDATE_DATE_TIMESTAMP_NOT_NULL, PRIMARY_KEY_(PERSIST_CONTEXT_UID), SCHEMA_JSON_TEXT);		
	<pre>); CREATE TABLE CS_PROVISION (SPACE ID VARCHAR(255) NOT NULL, CONTEXT_ID VARCHAR(255) NOT NULL, ROUTING_ID VARCHAR(255) NOT NULL, TENANT_ID VARCHAR(255), DATA_JSON TEXT, IDENTIFIER VARCHAR(255), META_JSON TEXT, GROUP_ID VARCHAR(255), UPDATE_DATE TIMESTAMP NOT NULL, PRIMARY KEY (SPACE_ID), SCHEMA_JSON TEXT); CREATE INDEX CS OPERATION CONTEXT ID IDX ON CS OPERATION</pre>		
	(CONTEXT_ID); CREATE INDEX CS_OPERATION_GROUP_ID_IDX ON CS_OPERATION (GROUP_ID); CREATE INDEX CS PROVISION CONTEXT ID IDX ON CS PROVISION		
	<pre>(CONTEXT_ID);</pre>		
Oracle	If the tables CS_OPERATION, CS_PROVISION and GENERATED_KEYS exist, drop the tables:		
	DROP TABLE CS_OPERATION CASCADE CONSTRAINTS; DROP TABLE CS_PROVISION CASCADE CONSTRAINTS; DROP TABLE GENERATED_KEYS CASCADE CONSTRAINTS;		
	Create the tables:		
	CREATE TABLE CS_OPERATION (PERSIST_CONTEXT_UID NUMBER(19,0) NOT NULL, CONTEXT_ID VARCHAR2(255 CHAR) NOT NULL, ROUTING_ID VARCHAR2(255 CHAR) NOT NULL, TENANT_ID VARCHAR2(255 CHAR), DATA_JSON CLOB, IDENTIFIER VARCHAR2(255), META_JSON CLOB, GROUP_ID VARCHAR2(255 CHAR), OPERATION_TYPE VARCHAR2(10 CHAR), UPDATE_DATE TIMESTAMP NOT NULL, PRIMARY KEY (PERSIST_CONTEXT_UID), SCHEMA_JSON CLOB		

Database	Commands			
);			
	CREATE TABLE CS_PROVISION (SPACE_ID VARCHAR2(255 CHAR) NOT NULL, CONTEXT_ID VARCHAR2(255 CHAR) NOT NULL, ROUTING_ID VARCHAR2(255 CHAR) NOT NULL, TENANT_ID VARCHAR2(255 CHAR), DATA_JSON CLOB, IDENTIFIER VARCHAR2(255), META_JSON CLOB, GROUP_ID VARCHAR2(255 CHAR), OPERATION_TYPE VARCHAR2(10 CHAR), UPDATE_DATE TIMESTAMP NOT NULL, PRIMARY KEY (SPACE_ID), SCHEMA_JSON CLOB);			
	CREATE INDEX CS_OPERATION_CONTEXT_ID_IDX ON CS_OPERATION (CONTEXT_ID); CREATE INDEX CS_OPERATION_GROUP_ID_IDX ON CS_OPERATION (GROUP_ID);			
	CREATE INDEX CS_PROVISION_CONTEXT_ID_IDX ON CS_PROVISION (CONTEXT_ID); CREATE TABLE GENERATED_KEYS (PK_COLUMN VARCHAR2(255 CHAR), VALUE_COLUMN NUMBER(10,0)) ;			
Microsoft SQL Server	If the tables CS_OPERATION, CS_PROVISION and GENERATED_KEYS exist, drop the tables:			
	DROP TABLE CS_OPERATION; DROP TABLE CS_PROVISION; DROP TABLE GENERATED_KEYS;			
	Create the tables:			
	CREATE TABLE CS_OPERATION (PERSIST_CONTEXT_UID NUMERIC(19,0) NOT NULL, CONTEXT_ID VARCHAR(255) NOT NULL, ROUTING_ID VARCHAR(255) NOT NULL, TENANT_ID VARCHAR(255) NULL, DATA_JSON TEXT NULL, IDENTIFIER VARCHAR(255) NULL, META_JSON TEXT NULL, GROUP_ID VARCHAR(255) NULL, OPERATION_TYPE VARCHAR(10) NULL, UPDATE_DATE DATETIME NOT NULL, PRIMARY KEY (PERSIST_CONTEXT_UID), SCHEMA_JSON TEXT NULL);			
	CREATE TABLE CS_PROVISION (SPACE_ID_VARCHAR(255) NOT_NULL, CONTEXT_ID_VARCHAR(255) NOT_NULL, ROUTING_ID_VARCHAR(255) NOT_NULL, TENANT_ID_VARCHAR(255) NULL, DATA_JSON_TEXT_NULL, IDENTIFIER_VARCHAR(255) NULL, META_JSON_TEXT_NULL, GROUP_ID_VARCHAR(255) NULL, OPERATION_TYPE_VARCHAR(10) NULL, UPDATE_DATE_DATETIME_NOT_NULL, PRIMARY_KEY_(SPACE_ID),			

Database	Commands	
	SCHEMA_JSON TEXT NULL	
);	
	CREATE INDEX CS_OPERATION_CONTEXT_ID_IDX ON CS_OPERATION (CONTEXT ID);	
	CREATE INDEX CS_OPERATION_GROUP_ID_IDX ON CS_OPERATION (GROUP_ID);	
	CREATE INDEX CS_PROVISION_CONTEXT_ID_IDX ON CS_PROVISION (CONTEXT ID);	
	CREATE TABLE GENERATED_KEYS (PK_COLUMN VARCHAR(255), VALUE_COLUMN INT) ;	

Updating database tables

About this task

The database schema has been updated to support Avaya Oceana[™] Solution Core Data Service. If you are upgrading from previous versions of Context Store to Release 3.2.2.1, update the database tables as described in this topic.

Before you begin

Complete all database transactions, such as select, update, and delete operations, before executing the following command.

Procedure

- 1. Log in to the external database that you are using for External Data Mart using the database user account you have created for Context Store.
- 2. update database tables for External Data Mart.

Depending on the database that you have, enter the relevant commands provided in the following table:

Database	Commands
PostgreSQL	Update the tables:
	ALTER TABLE CS_OPERATION (ADD SCHEMA_JSON TEXT;
	ALTER TABLE CS_PROVISION (ADD SCHEMA_JSON TEXT;
Oracle	Update the tables:
	ALTER TABLE CS_OPERATION (ADD SCHEMA_JSON CLOB;
	ALTER TABLE CS_PROVISION (ADD SCHEMA_JSON CLOB;
Microsoft SQL Server	Update the tables:
	ALTER TABLE CS_OPERATION (ADD SCHEMA_JSON TEXT;
	ALTER TABLE CS_PROVISION (

Database	Commands
	ADD SCHEMA_JSON TEXT;

External Data Mart provisioning

With the EDM provisioning feature, you can replicate contexts to an external database and use the replicated contexts to redeploy a pre-populated CS data grid. To facilitate such provisioning, you must create contexts with the "persistTo":"CS_PROVISION" flag set.

Context Store stores the contexts that contain the provisioning flag into the provisioning table of the external data mart. When you reboot Context Store, the contexts that are stored in the CS_PROVISION table are brought back into the data grid from the external data mart.

An operation on a context in the data grid updates the provisioning table in the external data mart with the latest version of the context.

Pump-up operation

When you reboot Context Store, the data grid is empty. If the **EDM: Enable Provisioning from database** field is set to true in the CSManager attributes, Context Store queries the CS_PROVISION table in the EDM database for context entries. Then the system performs a pump-up of the provisioned data to populate the data grid

Context Store supports retrieving 10 contexts from the external data mart per second.

If a configured external data mart is unavailable or the operation times out, Context Store attempts the operation for a fixed number of times. The multiple attempts are to ensure that potential networking difficulties are addressed. For more information about enabling the EDM provisioning feature in Context Store, see the *Enabling External Data Mart* topic. For more information about EDM provisioning, see *Avaya Context Store Snap-in Developer Guide*.

Configuring Additional Databases

Additional databases

Context Store provides only the PostgreSQL database by default. However, you can configure Context Store to write to other databases, if the database has a JDBC-compatible driver. You must load the jar file to System Manager and then configure the drivers in the **CS Manager** page.

You need licence to use some JDBC drivers. You must provide a licensed driver and load it into the Context Store cluster.

For more information about configuring the drivers, see <u>CSManager attribute descriptions</u> on page 77. For more information about enabling External Data Mart, see <u>Enabling External</u> <u>datamart in Context Store</u> on page 68.

Related links

External Data Mart provisioning on page 34

Loading JDBC driver to System Manager

Procedure

- 1. On the System Manager web console, click **Home > Elements > Avaya Breeze > Configuration > JDBC Providers**.
- 2. Click New and enter information in the required fields.
- 3. Click Select the jar file to select the JDBC jar file.

The driver appears on the list of **Available JDBC drivers**.

- 4. On the System Manager web console, click Avaya Breeze > Service Management.
- 5. Select the driver.
- 6. Click Install and select the Context Store cluster.
- 7. Click **Commit** to install the jar file to the cluster.

Related links

External Data Mart provisioning on page 34 JDBC Providers field description on page 35

JDBC Providers field description

Name	Description
Name	The name of your JDBC driver.
Driver Name	The name of the JDBC driver class.
	Oracle:
	- oracle.jdbc.driver.OracleDriver
	Microsoft:
	- com.microsoft.sqlserver.jdbc.SQLServerDriver
Description	The description of the JDBC driver.

Related links

External Data Mart provisioning on page 34

Customer journey visualization

From Release 3.2 of Context Store, call center agents can use the audit trail data to produce a visualization of a customer's interactions. With this feature, you can visualize each point in the customer journey represented by an interaction with a touchpoint. The activity on the touchpoint, if available, is displayed on tooltips and data cards. For example, Touchpoint=Voice, Activity=Assisted service.

Context Store uses the CS Query snap-in to request for customer data stored in an external data mart (EDM). The Context Store Customer Journey application, hosted on the CS Query snap-in, uses the CS Query API to retrieve the data from the EDM and visualize the data by contextId or groupId.

A multi session journey is when a groupld is used to link disparate contexts into a single journey. You can navigate through a multi session journey using interaction cards displayed at the bottom of the visualization. The interaction cards indicate the start and end of an interaction and the number and type of interactions.

The standalone Context Store Customer Journey application provides the option to choose between two data sources:

- The CS Query Snap-in: Data is retrieved from an external database.
- Audit Trail: Audit trail metadata is retrieved from CS data grid.

The CS Query snap-in has access to data at each interaction with a touchpoint. You can click the interaction points to view the data. Audit trail does not have access to the underlying data and shows only the touchpoints and timestamps.

Storing audit trail data in Context Store

To visualize the data stored in Context Store, you must associate a touchpoint with each operation on a context object.

```
For example, Post: http(s)://clusterIP/services/CSRest/cs/contexts/?
touchpoint=web
```

Each interaction has a timestamp associated with it. If you enabled the External Data Mart (EDM) feature and the persistToEDM flag is set to True for a Context Store operation, the data at the time of each update is stored in the EDM database. The CSQuery snap-in can later retrieve the data stored in this manner.

The databases supported to be used with the Customer journey visualization feature are:

- PostgreSQL
- Microsoft SQL Server
- Oracle

Viewing customer interactions

The Customer Journey application provides the following options to view and filter customer data:

- Use the mouse wheel to zoom in and out. Zoom is centered at the mouse point.
- Click and drag the mouse pointer towards left or right to see information on a scrolling window.
- Hover the mouse pointer over an interaction to see a tooltip about the interaction.
- Click an interaction to view data. After a data card is opened, you can also filter the data.
- Click a touchpoint label to filter all associated interactions.
- Hover the mouse pointer over a path segment to see interval and data delta, if exists.
- Search interaction data using the input field.
- Timeline navigation cards are displayed below the timeline to aid navigation of interactions. You can:
 - Click these cards to bring the interactions for this session into view.

- Click a selected card to deselect it and return to the original timeline view.

😵 Note:

- Zooming and panning are not enabled in the drilled-in view.
- The Customer Journey application cannot predict the distribution of interactions. Therefore, some interactions might overlap. The Customer Journey application provides timeline navigation cards and the zoom functionality to address this issue. The application retrieves data as stored in the database; users should use accordingly.

You can select the available date range to view the customer journey. The interactions from the previous 1 to 60 days can be viewed.

Each interaction point in the journey is indicated with a touchpoint icon. You can click a particular icon to view the details of the interaction.

😵 Note:

If the touchpoint is undefined for a specific Context Store operation, you cannot view the interaction details.

The visualization displays icons for the following touchpoints:

- Web
- Email
- Webvoice
- Voice
- Chat
- Social
- Survey
- Chatbot
- CRM
- SMS
- APP

When you use other touchpoints than those listed here, the Context Store Customer Journey application displays the first two letters of the touchpoint string instead of the icons.

Related links

<u>Viewing customer journey on a standalone Customer Journey application</u> on page 37 <u>Audit trail</u> on page 39 <u>Context Store Query</u> on page 21

Viewing customer journey on a standalone Customer Journey application

About this task

In this release, Google Chrome is the only supported browser for viewing customer journey on the standalone Context Store Customer Journey application.

Procedure

- 1. Go to http(S)://clusterIP/services/CSQuery/
- 2. On the top right of the Context Store UI, click the Configuration icon.

The Context Store Customer Journey application displays the Cluster Configuration window.

- 3. In the **Cluster IP** field, enter the IP address of your Context Store cluster.
- 4. Select context Id or group Id.
- 5. In the **Id** field, enter the appropriate Id for the data you want to view customer journey.
- 6. In the **Routing Id** field, enter the routingId of the context entry for which you want to view customer journey.
- 7. In the Select Data Source field, select Audit Trail or CSQuery.

From CSQuery, you can retrieve context data from each interaction point. Audit trail does not have access to the underlying data and shows only the touchpoints and timestamps.

For details on the usage of the Customer Journey application, see the "Viewing customer interactions" section.

8. Click Save.

Related links

Customer journey visualization on page 35

Context aliasId for additional indexing

You can use the Context alias feature to retrieve the same context object using alternative identifiers. Context aliasIds provide more flexibility in retrieving and updating context objects.

A context object can be indexed using the usual contextId and groupId. The object can also be indexed with context aliasIds such as a customer account number, a billing authorization number, and a mobile phone number. A customer object can be retrieved using any of these ids to retrieve the context object.

Context aliasIds are subject to the same restrictions as all other context identifiers such as permissible characters, length, and must be unique in the data grid.

You can add up to three aliasIds for any one context object. In addition to defining aliasIds when a context object is first created, you can add and delete aliasIds post creation. For more information about adding, updating, or deleting an aliasId, see *Avaya Context Store Snap-in Developer Guide*.

😵 Note:

If you add three aliasIds for a context, you must reduce your context data size to 1.5 KB.

Each aliasId for a context must be unique within the context object, and the Context Store data grid. The same aliasId can exist in each cluster in a Geo solution, but the routingId distinguishes

them from one another. Any attempt to duplicate an existing aliasId or retrieve a context using an unknown aliasId results in error messages.

The aliasing capability impacts the performance of Context Store, in particular latency, due to the increased number of lookups and data comparison required to find the correct object in the data grid. For more information, see <u>Capacity and scalability specification</u> on page 97.

Using aliasId as a request parameter

When creating a context, you can specify up to three aliasIds as parameters in the requests. For all other "by aliasId" operations, provide only the aliasId which identifies to the context on which an operation is to be executed.

For more information about the usage of the aliasId feature, see Avaya Context Store Snap-in Developer Guide.

Audit trail

With the Audit trail feature, you can find out a certain configured number of Context Store operations performed on a context during the lifecycle of the context. If you opt for the CSQuery snap-in, you can collect all associated context data from an external data mart (EDM) through CSReST interface. Using this interface, you can generate audit trails or retrieve instances of context data from the historical context data stored in the associated EDM.

Audit trail records all successful interactions with a context and stores the information inside the context object as an extra field. If you enable the Audit trail feature, you can find out which application created or updated the context. You can also track the operation types, such as Create, Read, Update, Delete, and Upsert, that were performed on the context. The audit entry of a context also provides information such as the time at which the operations were performed and the version of the context.

After you enable the Audit trail feature, the CSReST API accepts touchpoint, which is any application that can interact with CSReST APIs, as a parameter for each interaction. The touchpoint parameter is an alphanumeric ID.

If you enabled the Audit trail feature, but did not provide the touchpoint parameter as part of the ReST URL, then the system still records the audit entry with the value undefined.

The versionId of a context increases with each interaction, such as Update, Get, Put, and Delete, with a context.

For more information about the touchpoint parameter, see *Avaya Context Store Snap-in Developer Guide*.

If you want to retrieve audit trail data from an EDM, you must configure the EDM database username and EDM database password in the system.

ReST URL paths

You can retrieve the audit entries of a context using the contextId or aliasId of the context. When you provide the correct parameters, the system displays the audit data. For example, the URL to retrieve audit data using contextId is https://clusterIP/services/CSRest/cs/

contexts/audit/{contextId}/?rid={routingId}. Avaya Context Store Snap-in
Developer Guide has more detailed usage examples.

Setting a limit on audit entries

The number of audit entries for the context objects can reduce the number of contexts that you can store in the Context Store data grid. Therefore, you must set a limit on the number of audit entries that can exist for a context.

By default, the audit entry limit is set to 0. That means that the audit feature is disabled. You can set the number of audit entries for a context by selecting a value ranging between 0 and 50 in the following location in System Manager: **Home > Elements > Avaya Breeze > Configuration > Attributes > Service Clusters > CSManager**. If you set the limit to 10, then Context Store records the 10 most recent interactions as entries for the context. When the number of audit entries reaches the maximum limit, the system removes the oldest audit entry each time a new entry is added.

😵 Note:

If you enable the Audit trail feature in a geo-redundant deployment, the CS Audit: Event limit attribute must be set identically in both clusters.

Audit trail and capacity planning

The number of audit entries configured for a context affects the size of the context object and the number of contexts in the data grid. Therefore, you must consider the size of the audit data trail while planning the Context Store capacity.

For more information about Audit trail and capacity planning, see Avaya Context Store Snap-in Developer Guide.

Related links

<u>Customer journey visualization</u> on page 35 <u>Context Store Query</u> on page 21

Upsert method

With the Upsert method, Context Store either updates an existing context with new data or creates a new context if it does not exist in the data grid. Combining the two operations into a single request reduces the number of API calls.

However, due to the nature of Upsert operations, it is computationally more expensive to complete an Upsert request than to do a single create or update request.

You can perform the Upsert operations using aliasIds. You can also set the lease time of a context with the Upsert method. Context Store applies the lease time that you provide to the context in both Create and Update operations.

Certain fields of the context metadata are immutable by design. You cannot modify the immutable fields of an existing context using the Upsert method. However, if you create a new context with the Upsert method, you can define the properties for the new context.

😒 Note:

There is a performance consideration for Upsert that should be taken into account. A single Upsert operation is more computationally expensive than its corresponding POST or PUT request and can take up to three times longer to complete. Hence, if you are using the Upsert method, the total number of requests per second supported will be reduced as per the number of the Upsert request used per second.

For detailed usage information of Upsert operation, see the Avaya Context Store Snap-in Developer Guide.

Pluggable Data Connector

Context Store provides a Pluggable Data Connector (PDC) to integrate Avaya Aura[®] Experience Portal with the CSRest service. Experience Portal uses call flows created in Avaya Aura[®] Orchestration Designer. When you install the Context Store PDC in Orchestration Designer, a Context Store Connector node is available in Orchestration Designer. You can drag the Context Store Connector node into call flows to integrate Context Store into the flow.

You can also configure the Context Store Connector node to perform actions such as creating, getting, updating, or deleting context information using either contextId or aliasId. For more information on using the pluggable data connector, see *Avaya Context Store Snap-in Developer Guide*.

Context Store Task Type for Engagement Designer

Context Store Task Type is the service in Engagement Designer (ED) that interfaces with Context Store. Engagement Designer is an Avaya Breeze[™] snap-in that business analysts and other non-developers can use to create workflow definitions that describe and execute business processes.

The CS Task Type enables all the Context Store operations to be run from within a workflow in ED. You can perform Add, Update, Retrieve, and Delete operations for both contexts and values using the Context Store Task Type.

😵 Note:

CS Task Type SVAR is compatible only with Release 3.2.0 of Context Store and Release 3.2.0 of Engagement Designer.

For more information about installing Context Store Task Type and performing CS operations using CS Task Type, see *Avaya Context Store Snap-in Developer Guide*.

Authorization

From Release 3.2, Context Store provides authorized access to context data using Avaya Breeze[™] Authorization Service (AS) snap-in.

An administrator authorizes different user groups and applications with specific access levels. This user-privilege mapping is stored in the AS snap-in and a bearer token is generated for the user or application.

When the user or application requires access to Context Store, they must supply the authorization token with the Context Store request. If the user or application is accessing Context Store for the first time, the authorization token must be requested from the AS snap-in. When the Web Filter / Token Validator component of Context Store receives a request, it verifies the existence and validity of the authorization token. If the token exists in the CS data grid, Context Store returns the data requested according to the access level that the user or application is granted

Privilege levels

Context Store supports two features or access levels: Privileged and Standard. For each feature, you can have four values:

Value	Definition
Create	Applies to all CSRest Post requests.
Delete	Applies to all CSRest Delete requests
Read	Applies to all CSRest Get requests
Update	Applies to all CSRest Put requests

Generating bearer tokens

Four Rest methods are available for generating bearer tokens.

Name	Rest method	URL	Headers
Get token	GET	https://clusterIP// services/CSRest/cs/ contexts/token/	
Get token by scope	GET	https://clusterIP// services/CSRest/cs/ contexts/token/scope/	scope
Get token by user	GET	https://clusterIP// services/CSRest/cs/ contexts/token/username/	user namepassword
Get token for user by scope	GET	https://clusterIP// services/CSRest/cs/ contexts/token/username/ scope/	scopeuser namepassword

Related links

Assigning permissions to an authorization client on page 66 CSRest attribute descriptions on page 83

Scalability overview

Context Store provides scalability by supporting varied deployment types to suit all purposes.

The scalability feature facilitates the deployment of Context Store on Avaya Breeze[™] nodes of varying sizes. You can deploy Context Store on a single node or on a cluster of up to five nodes. Deployments with single node or low resources are for non-mission-critical environments, such as customer trials and lab deployments. The scalability options are as follows:

- Scale Out feature: Provides customers the option to deploy Context Store on a single-node cluster or on a cluster containing from two nodes up to a maximum of five nodes.
- Scale Up feature: Supports incremental memory allocations for Avaya Breeze[™] nodes and provides the option to store data in the grid for longer lease duration.

Related links

Addition or removal of nodes overview on page 43 Scale out on page 44 Scaling out Avaya Breeze cluster on page 44 Scale up on page 45 Scaling up Avaya Breeze cluster on page 46

Addition or removal of nodes overview

Context Store provides the option to add or remove Avaya Breeze[™] nodes in the deployed Context Store setup. This feature is only supported in a multi-node cluster. You can add only one node at a time. When you add or remove nodes, ensure that:

- · No traffic runs through the system
- · No Geo replication is in operation

😵 Note:

Context Store does not support scaling out dynamically. After adding or removing a node to the cluster, you must shut down all the nodes and start the nodes simultaneously.

The resources of a node must be identical to the other nodes in the cluster. After adding a node and allocating resources to the node, you must manually update the cluster configuration in System Manager before shutting down the nodes. Updating the configuration ensures that the cluster utilizes the new resources.

😒 Note:

When adding or removing nodes, ensure that all external clients that you create or manage are able to handle the changes to capacity or throughput. The maximum requirements for the external clients and connections do not exceed the requirements in the previous Context Store releases. You must provide adequate bandwidth and performance for the external clients.

Related links

Scalability overview on page 43

Scale out

The Context Store Scale out feature allows you to have a single-node deployment or add additional nodes to an existing multi-node deployment. With an increase in the number of nodes and resources associated with the nodes, you can maintain contexts for longer lease duration or use nodes with smaller footprint to use the capacity.

😵 Note:

Context Store does not support scaling out dynamically. After adding a node to the cluster, you must shut down all the nodes and restart the nodes simultaneously.

By using the Scale out feature, you can:

- Deploy Context Store on one node only. In a single node deployment, load balancing is not enabled and therefore a cluster IP address is not required. Context Store uses the security module IP address of the node for traffic.
- Deploy Context Store on a cluster of two to five nodes. Context Store supports high availability in this configuration.
- Scale the clusters in Geo redundant deployments. Context Store clusters that are connected as part of a Geo deployment must contain the same number of nodes. All the nodes in both the clusters must have the same amount of memory. If a node is added to one cluster, a replica node must be added to the second cluster.

For high availability, Context Store supports a maximum of one failed node regardless of how many nodes are assigned to the cluster. To avoid service interruption, the remaining nodes must be able to support the throughput and capacity of the contribution of the failed node.

Related links

Scalability overview on page 43

Scaling out Avaya Breeze[™] cluster

Before you begin

Identify the cluster configuration that you want to achieve. For example, if your current cluster has three nodes of 64 GB each and, you wish to scale out to five nodes of 64 GB each, configure the following fields as per the requirements of a five-node cluster:

- ContextStore ManagerSpace DataGrid Settings
- ContextStoreSpace DataGrid Settings
- Context Store DataGrid type
- EDM: Mirror Service container size
- GEO: Gateway Service container size

Ensure that all your nodes have identical resources, such as CPU, memory, and hard disk. For more information, see <u>Context Store deployment checklist</u> on page 54.

😵 Note:

You must follow this procedure for one node at a time. You must not add multiple nodes to a cluster at one go.

Procedure

- 1. Deploy a new Avaya Breeze[™] node with the required CPU and memory configuration.
- 2. On the System Manager web console, click **Home** > **Elements** > **Avaya Breeze** > **Cluster Administration**.
- 3. Select the cluster that you want to scale out and select the **Deny New Service** state in the **Cluster State** list.
- 4. Select the cluster again and click Edit.
- 5. On the Cluster Editor window, go to the Servers tab.
- 6. Add the Avaya Breeze[™] node from the **Unassigned Servers** list.
- 7. Click Commit.

The system prompts you to ensure that all Avaya Breeze[™] server restarts are complete before placing the cluster into the **Accept New Service** state.

8. Click OK.

The system starts installing the assigned services to the newly added server.

- 9. Repeat this procedure for all the nodes.
- 10. Shut down all the nodes.
- 11. Power on all the nodes simultaneously.
- 12. On the **Cluster Administration** page, verify that the services are installed for the cluster.
- Click Show on the new cluster to verify if the system has added the servers to the cluster.
 The system displays the Avaya Breeze[™] servers as part of the Context Store cluster.
- 14. Select the check box of the cluster.
- 15. From the Cluster State drop-down menu, select Accept New Service.
- 16. Click Continue in the Accept New Service dialog box.

The system displays the Accepting state in the Servers State column.

Related links

Scalability overview on page 43

Scale up

The Context Store Scale up feature provides the functionality to increase the memory allocations from 8 GB to 128 GB so that contexts can be stored in the data grid for longer lease durations. Ensure that all nodes in your cluster have identical resources, such as memory, CPU, and hard disks.

By using the Scale up feature, you can:

- Deploy Context Store on Avaya Breeze[™] nodes that have memory ranging from 8 GB to 128 GB.
- Support production environments deployed on a cluster of Avaya Breeze[™] nodes that have memory ranging from 16 GB to 128 GB.

😵 Note:

Context Store does not support single-node deployments for production environments as Context Store does not support high availability or Geo redundancy in single-node deployments.

- Support deployments with smaller footprints. You can deploy Context Store on Avaya Breeze[™] nodes that have smaller CPU core allocations for non-mission critical environments.
- Support multiple options for hard disk allocations for the Avaya Breeze[™] nodes in Context Store to facilitate deployments with reduced footprints and requirements. Large hard disks are not required for non-mission-critical environments as maintaining logs for long periods is not required. In addition, the quantity of logs is reduced as the supported throughput is lowered in such a deployment.

For more information about CPU, hard disk and memory allocations see the *Certified Deployments section in Avaya Context Store Snap-in Release Notes*.

Related links

Scalability overview on page 43

Scaling up Avaya Breeze[™] cluster

Procedure

- 1. On the System Manager web console, click **Home** > **Elements** > **Avaya Breeze** > **Cluster Administration**.
- Select the cluster that you want to scale up and click **Deny New Service** in the **Cluster** State list.
- 3. On the System Manager web console, click **Home** > **Elements** > **Avaya Breeze** > **Configuration** > **Attributes** > **Service Clusters** > **CSManager**.
- 4. Change the values in the following fields according to the cluster set up that you want to scale up to:
 - a. Change the values in the ContextStore ManagerSpace DataGrid Settings field.
 - b. Change the values in the ContextStoreSpace DataGrid Settings field.
 - c. Change the values in the Context Store DataGrid type field
 - d. Change the values in the EDM: Mirror Service container size field.
 - e. Change the values in the GEO: Gateway Service container size field.
- 5. Shut down all the Avaya Breeze[™] nodes.

6. Using VSphere Client, increase the memory, hard disk and CPU allocations according the deployment that you want to achieve .

Note:

The CPU, hard disk and memory settings must be the same for all the nodes in the cluster. In a Geo redundant set up, both the clusters must be identical.

- 7. Power on all the nodes simultaneously.
- 8. Select the check box of the cluster.
- 9. From the Cluster State drop-down menu, select Accept New Service.
- 10. Click Continue in the Accept New Service dialog box.

The system displays the **Accepting** state in the **Servers State** column.

Example

Related links

Scalability overview on page 43

Chapter 3: Interoperability

Avaya product compatibility

The Context Store snap-in is compatible with the following Avaya products:

Avaya product	Version
Avaya Aura [®] System Manager	7.0.1
Avaya Breeze [™]	3.2. 0.x
Avaya Aura [®] Experience Portal	7.0.1 (FP) and 7.1
Avaya Aura [®] Orchestration Designer	7.0.1 (FP) and 7.1
Avaya one-X [®] Agent	2.5, 2.5.2, 2.5.4, and 2.5.5
Intelligent Customer Routing	7.0.1
Avaya Engagement Designer	3.2.1

Hardware requirements

This topic provides information about the Context Store hardware requirements. For information about the Avaya Breeze[™] requirements, see the *Interoperability chapter in Avaya Breeze*[™] *Overview and Specification*.

The requirements specified here are not applicable to all deployments options. For more information about the hardware requirements of the certified deployment scenarios, see *Certified Deployments section in Avaya Context Store Snap-in Release Notes*.

ESXi host server

Context Store supports a range of deployment options from a single node cluster to an Avaya Breeze[™] cluster with a maximum of five nodes. As a failover strategy to ensure maximum availability of the solution, Avaya recommends that at least two Avaya Breeze[™] servers be deployed. The servers must be on different VMware ESXi hosts. To guarantee service availability and to ensure high availability of the solution, it is recommended that three servers be used. If you install any or all three Avaya Breeze[™] servers on the same host, then the failure of the host impacts multiple Avaya Breeze[™] servers. The failure of multiple servers prevents Context Store from using a backup server during failover and hence impacts the overall availability of the solution.

😵 Note:

The specifications provided here are for a reference implementation. This is the implementation on which Context Store's capacity and performance figures have been certified. Equivalent performance cannot be guaranteed in environments which do not meet the hardware and network requirements stated here.

• Processor: For the specified best performance, the processor should have at least 8 dedicated, non-hyper-threaded cores, equivalent to a 2.9 GHz Xeon processor.

To ensure that the Context Store solution can support published capacity figures and availability, Avaya recommends that you reserve the processor to achieve maximum traffic rate with low latencies, especially when Context Store is recovering from a failure. Without dedicated cores, Context Store competes with other Virtual Machines on the same VMWare ESXi host for crucial resources at times of maximum throughput or recovery, resulting in poor performance or loss of data.

- Hyper-Threading must not be enabled. Context Store does not support VM features that sub divide the processing power of the core, because it does not expect to have to compete with external processes during max capacity or failover where Context Store requires additional processing overhead to ensure no service interruption.
- vMotion must not be enabled: Neither Context Store nor the Avaya Breeze[™] has certified this feature, and hence it is recommended that this feature not be used during the running of Context Store.
- For best performance, Network should:
 - Support at least Gigabit Ethernet
 - Have a response time of less than 250 milliseconds between hosts.
 - Be able to handle a transfer rate of 48 mb/sec
 - Have all hosts on the same Data Center, on the same subnet and on the same high quality LAN, so no latencies are incurred in the solution.

😒 Note:

Use of VLAN is not recommended, because capacity testing executed on a VLAN environment resulted in poor performance. Frequent connection issues were also seen within the cluster, between geo-redundant clusters, and to an External Data Mart.

- Have a dedicated 1 GB channel with a minimum of 300 MB bandwidth being available for Session Replication between the Context Store clusters, if Context Store's Geo Redundancy feature is used.
- Storage: Must at least be 15000 RPM SATA hard disks.

Guest virtual machines

Note:

The specifications provided here change according to the deployment. For the details about certified deployment scenarios, see *Certified Deployments section in Avaya Context Store Snap-in Release Notes*.

Each guest virtual machine for Context Store must meet the following criteria, which is dependent on the deployment scenario. For details about the Avaya tested hardware requirements based on

the deployment scenarios, see *Certified Deployments section in Avaya Context Store Snap-in Release Notes*.

- Processor: 4 to 8 dedicated cores
 - All Context Store nodes in production environment require 8 dedicated, non-hyperthreaded cores. The CPU resource reservation must be at least 18960 MHz for each node. If Profile 1, 2, or 3 is selected when deploying the Avaya Breeze[™] OVA, the CPU reservation must be increased manually by editing the virtual machine settings after deployment.
- RAM: 8 to 128 GB RAM
- Hard disk: 50 GB to 300 GB

Important:

If you use a SAN, the performance of the SAN must meet the above specifications.

Each guest virtual machine must also be thick provisioned and be on the same subnet.

Software requirements

The Context Store software requirements are based on the Avaya Breeze[™] and System Manager requirements. For information about Avaya Breeze[™] requirements, see the *Interoperability chapter in Avaya Breeze[™] Overview and Specification*. For information about Avaya Aura[®] System Manager requirements, see *Deploying Avaya Aura[®] System Manager in Virtualized Environment*.

Chapter 4: Licensing

License requirements

Use of the Context Store software requires a valid Context Store license file and Avaya Breeze[™] license file.

Context Store uses the snap-in service licensing feature provided by Avaya Breeze[™]. All Context Store SVAR files contain a digital signature which is verified by the Avaya Breeze[™] Element Manager.

Platform and snap-in licenses must be installed on the WebLM server of System Manager, which manages the Platform and snap-in licenses.

A single license, containing information for each licensed feature, applies to all Context Store snap-in services.

Configuring Context Store licenses

Before you begin

- Ensure that you have obtained the Context Store license from Avaya PLDS.
- Ensure that the Avaya Breeze[™] license is installed on System Manager.

In System Manager, click **Elements** > **Avaya Breeze** > **Server Administration** to see the current status of each Avaya Breeze[™] server platform license.

About this task

This task provides information about configuring Context Store license in System Manager.

Procedure

- 1. On the System Manager Home page, select **Services > Licenses**.
- 2. Select Install License.
- 3. Browse to the location of the Context Store license.
- 4. Select the license file and click Install.

The system installs the license file.

In the left navigation pane, the system displays CONTEXT_STORE under Licensed **Products**.

- 5. To verify if the license file is installed successfully:
 - a. Click Elements > Avaya Breeze > Service Management.
 - b. In the **License mode** column, verify that the column displays a check mark for the Context Store node.

The following licensing modes apply to all Avaya Breeze[™] and Context Store licenses

- Normal: Context Store has a valid license file for normal operation of Context Store.
- Error: Context Store is operating in 30 day grace period. All the functionalities of Context Store are still available. However, to get Context Store back to the normal mode, you must install a valid license file before the grace period expires.
- Restricted: Context Store has exceeded its 30 day grace license period and has no access to Avaya Breeze[™].

For more information on licensing modes and licensing for Avaya Breeze[™], see the Avaya Breeze[™] documentation.

Avaya Breeze[™] licensing audit runs every 9 minutes. Any license changes including install or uninstall actions on the WebLM server takes time to reflect on the user interface. The latest license information thus takes a maximum of 9 minutes to reflect in the Avaya Breeze[™] Element Manager.

Chapter 5: Context Store Deployment

Certified deployment scenarios

Avaya provides 13 tested/certified deployment scenarios for Context Store. The hardware requirements, number of nodes, supported features, settings, and capacity specifications differ as per the deployment scenarios.

The support for additional features, such as, AliasIds, CSNotifications, Audit trail, Geo redundancy, External Data Mart, and Event streams, is dependent on the hardware resources allocated to the cluster.

😵 Note:

The additional memory resources required for the Event Streams feature are not included in these figures. If this optional feature is deployed, the ContextStoreSpace DataGrid size must be reduced by 6GB.

This document provides the minimum hardware requirements required for the External Data Mart, Geo Redundancy, and CSNotifications features.

Related links

Capacity and scalability specification on page 97

Key customer configuration information

This topic lists the information that you must have before you install and configure the Context Store snap-in services.

You need the following information to install and configure the Context Store snap-in services. Record the information in this worksheet before beginning the installation.

Requirement	Notes	Your value
The name of the Context Store SVAR files that are available on PLDS.		
The location of the Context Store SVAR files that you have downloaded from PLDS.		

Requirement	Notes	Your value
The instances of Avaya Breeze [™] in System Manager, on which you plan to install Context Store.		
These Avaya Breeze [™] servers must be dedicated for Context Store.		
The IP address of the cluster	The Cluster IP must be on the same subnet as the Security Module IP of the Avaya Breeze [™] instances.	
	Do not specify the IP address of any of the Avaya Breeze [™] servers that you plan to add to the cluster.	
	😵 Note:	
	For single node deployments, you do not require the IP address of the cluster.	
Digital certificates for authentication using mutual TLS	For more information about certificates and authentication, see the <i>Security</i> chapter in this document.	
Identify the configuration attributes for the Context Store services	For more information about configuring attributes, see the chapter <i>Administering Context Store</i> .	

Context Store deployment checklist

😵 Note:

For Release 3.2 of Context Store, ContextStore space fails to deploy if you try to contact an EDM with incorrect login details or there are connection issues. If this happens, you must provide the accurate login credentials or solve the connection issues and then restart all the nodes in the Context Store cluster simultaneously.

Task	Notes	~
 Identify the Avaya Breeze[™] servers to use in the Context Store cluster. 	Verifying the status of Avaya Breeze servers on page 57	
• Ensure that the Avaya Breeze [™] servers are synchronized	For more information about creating and managing SNMP target profiles, see	
• Ensure that the Avaya Breeze [™] servers have passed the Avaya Breeze [™] tests.	Administering Avaya Aura [®] System Manager available at <u>http://support.avaya.com</u> .	
• Ensure that the Avaya Breeze [™] license is installed on System Manager.		

Task	Notes	~
Ensure that the NMS server is configured with System Manager as the target SNMP Profile.		
 Register the fully qualified domain names (FQDNs) of System Manager, Avaya Breeze[™] host names, and security IP address with the domain name system (DNS) server. 		
 Ensure that System Manager can resolve the host name of the Avaya Breeze[™] servers. 		
Download the Context Store snap-in services.	For more information, see Avaya Context Store Snap-in Release Notes.	
Download the Context Store license.	For more information, see Avaya Context Store Snap-in Release Notes.	
Load the required SVAR files in System Manager:	For more information, see <u>Loading a snap-in</u> <u>service</u> on page 58.	
If you plan to use an External Data Mart:	Database requirements and planning on	
• Set up an external database on a separate server. The external database must meet the Context Store requirements.	page 29 <u>Creating database tables for External Data</u> <u>Mart</u> on page 30	
Create the database tables for the External Data Mart feature.		
Define a cluster from the Avaya Breeze [™] > Cluster Administration page in	The system installs the CSManager service when you create a cluster.	
System Manager, and assign the instances of Avaya Breeze [™] to the cluster.	The system also installs the selected optional services, which you add to the cluster deployment.	
	For more information, see <u>Setting up a</u> <u>cluster</u> on page 59.	
Configure the ContextStore	Important:	
ManagerSpace DataGrid Settings, ContextStoreSpace DataGrid Settings and other CSManager and CSRest attributes of the services in the System Manager Service Clusters tab.	If you plan to use External Data Mart, configure the External Data Mart attributes while you configure the CSManager attributes. In CSManager attributes, External Data Mart is referenced as <i>EDM</i> .	

Task	Notes	•
	Important:	
	If you plan to use the external data mart feature, configure	
	If you plan to enable the Geo redundancy feature, see <u>Enabling geo redundancy</u> on page 67.	
	For more information, see <u>CSManager</u> <u>attribute descriptions</u> on page 77.	
Load the Context Store license in System Manager.	Configuring Context Store licenses on page 51	
Optional: Manually install the CSScreenPop services.	CSScreenPop is an optional service. You can manually deploy this service to the cluster after the initial installation of mandatory services.	
	Installing a Context Store service on page 64	
Optional: Configure the CSScreenPop attributes in System Manager.	The Context Store Rest Version attribute must be configured with the version currently installed on the cluster or this service cannot function.	
Optional: Manually install the CSNotifications services.	CSNotifications is an optional service. You can manually deploy this service to the cluster after initial installation of mandatory services.	
	Installing a Context Store service on page 64	
Optional: Configure the CSNotifications attributes in System Manager.		
Optional: Manually install the Streams services.	Event streams is an optional service. You can manually deploy this service to the cluster after the initial installation of mandatory services.	
	Installing a Context Store service on page 64	
Optional: Configure the Streams attributes in System Manager.	CSManager attribute descriptions on page 77	
Optional: Manually install the CSRules services.	CSRules is an optional service. You can manually deploy this service to the cluster after the initial installation of mandatory services.	

Task	Notes	~
	Installing a Context Store service on page 64	
Optional: Configure the CSRules attributes in System Manager.	CSRules page field descriptions on page 86	
Optional: Deploy PDC on Orchestration Designer.	PDC Plug-in deployment overview on page 70	
Optional: Manually install the CSSoap snap-in.	CSSoap is an optional service. You can manually deploy this service to the cluster after the initial installation of mandatory services.	
	Installing a Context Store service on page 64	
Optional: Configure the CSSoap attributes in System Manager.	The Context Store Rest Version attribute must be configured with the version currently installed on the cluster or this service cannot function.	
Optional: Manually install the CSQuery snap-in.	CSQuery is an optional service. You can manually deploy this service to the cluster after the initial installation of mandatory services.	
	Installing a Context Store service on page 64	
Optional: Configure the CSQuery attributes in System Manager.		
Verify the installation.	Verifying a successful deployment on page 65.	
Optional: Verify the installation of optional services.	Verifying a successful deployment on page 65.	

Verifying the status of Avaya Breeze[™] servers

Before you begin

Identify the Avaya Breeze[™] servers on which you plan to install the snap-in services.

About this task

This topic provides the basic procedures for verifying the status of the Avaya Breeze[™] servers. For detailed procedures, see *Deploying Avaya Breeze*[™].

Procedure

- 1. Ensure that the Avaya Breeze[™] servers are in the synchronized state:
 - a. On the System Manager web console, navigate to **Home > Services > Replication**.
 - b. Locate the Avaya Breeze[™] node in the **Replica Group** list.
 - c. In the **Synchronization Status** column, verify that the Avaya Breeze[™] status is **Synchronized**.

If the status is not **Synchronized**, for more information, see *Maintaining and Troubleshooting Avaya Breeze*.

- 2. Ensure that the Avaya Breeze[™] servers are passing the tests:
 - a. On the System Manager web console, click **Elements** > **Avaya Breeze** > **System Tools** > **Maintenance Tests**.
 - b. Select the Avaya Breeze[™] servers and perform all tests.
 - c. Ensure that all tests are successful.
- 3. On the System Manager web console, click **Elements** > **Avaya Breeze** > **Server Administration**.

Ensure that:

- For the Avaya Breeze[™] servers the **System State** column displays the **Denying** state.
- The License Mode column displays a green check mark.

Loading a snap-in service

Procedure

- 1. On the System Manager web console, click **Home > Elements > Avaya Breeze > Service Management**.
- 2. Click Load.
- 3. On the Load Service window, click Choose File.
- 4. Select the snap-in service svar file that you want to load.
- 5. Click Load.

The system displays the Accept End User License Agreement window.

6. Click Accept.

Configuring a cluster and installing mandatory services

Before you begin

- Identify the Avaya Breeze[™] servers on which you plan to install Context Store. These servers must be dedicated to Context Store only.
- Add the Avaya Breeze[™] servers to System Manager. For more information, see *Deploying Avaya Breeze*[™].
- Verify the status of the Avaya Breeze[™] servers.
- Ensure that System Manager can resolve the host name of the Avaya Breeze[™] servers. Register the fully qualified domain names (FQDNs) of System Manager, Avaya Breeze[™] host names, and security IP address with the domain name system (DNS) server.
- Download the following Context Store SVAR files from PLDS:
 - CSManager
 - CSRest
 - Note:

For more information about downloading the software from PLDS, see *Deploying Avaya Breeze*[™].

About this task

This topic provides information about setting up an Avaya Breeze[™] cluster for Context Store and installing the CSManager and CSRest services. CSRest is not a mandatory service, but is required if you need to interact with the data grid that CSManager deploys.

The cluster provides high availability and scaling by distributing the services across multiple Avaya Breeze[™] servers. With this distribution of services, the system achieves throughput and avoids interruption if a failure occurs. The clients access the services through a cluster IP address that supports high availability. For more information about clustering, see *Deploying Avaya Breeze*[™].

Procedure

- 1. On the System Manager web console, click Elements > Avaya Breeze.
- 2. In the left navigation pane, click Service Management.
- 3. On the **Service Management** page, load the mandatory service CSManager. For more information about loading a service, see *Administering Avaya Breeze*[™].
- 4. On the System Manager web console, click **Elements** > **Avaya Breeze** > **Cluster Administration**.
- 5. On the **Cluster Administration** page, click **New**.
- 6. Enter the following details for the cluster in the **General** tab of the **Cluster Editor** page:
 - Cluster Profile: Select Context Store from the drop-down menu.
 - **Cluster Name**: Enter a unique cluster name. The name can be any string such as ContextStore.

Important:

Ensure that no spaces are included in string.

• Cluster IP: The Cluster IP must be on the same subnet as the Security Module IP of the Avaya Breeze[™] servers. Ensure that you do not specify the IP address of any of the Avaya Breeze[™] servers that you plan to add to the cluster.

😵 Note:

For single node deployments, do not enter the IP address of the cluster. Requests must instead be submitted directly to the Security Module IP address of the node.

- **Description**: Enter a description for the cluster.
- 7. In the **Cluster Attributes** section, specify the attributes for the cluster that you are creating.

For more information about the cluster attributes, see the topic *Cluster attributes field descriptions*.

8. On the **Cluster Editor** page, select the **Servers** tab.

The system displays all Avaya Breeze[™] servers in the **Unassigned Servers** section.

9. Add the three identified Context Store nodes to the Context Store cluster.

Click the plus sign (+) on the node to add the node to the cluster.

The system adds the Avaya Breeze[™] servers to the **Assigned Servers** section.

10. On the Cluster Editor page, select the Services tab.

The system displays the Context Store services that you have loaded and configured through the **Service Management** page.

By default, the system automatically adds the mandatory service, CSManager, to the **Assigned Services** list. The **Available Services** list displays the optional services that are available for you to add to the Context Store cluster. Ensure that you configure the optional services and then attempt to install the optional services.

- 11. Click **the plus sign (+)** on any node in the **Available Services** list to add the service to the cluster.
- 12. Click Commit.

The system prompts you to ensure that all Avaya Breeze[™] server restarts are complete before placing the cluster into the **Accept New Service** state.

- 13. Click Ok.
 - The system starts installing the assigned services to the cluster servers.
 - The system displays the **Cluster Administration** page.
- 14. On the Cluster Administration page, verify that the services are installed for the cluster.
- 15. Click **Show** on the new cluster to verify if the system has added the servers to the cluster.

The system displays the Avaya Breeze[™] servers as part of the Context Store cluster.

😵 Note:

You must shut down all Avaya Breeze[™] nodes in the cluster and start them again using ESXi instead of the reboot and shutdown option in System Manager.

- 16. Select the check box of the new cluster.
- 17. From the Cluster State drop-down menu, select Accept New Service.
- 18. Click Continue in the Accept New Service dialog box.

The system displays the Accepting state in the Servers State column.

19. Configure the attributes of the CSManager service.

For more information about configuring attributes, see the chapter *Administering Context Store*.

Next steps

Enable geo redundancy in Context Store if required.

Enable the External Data Mart feature in Context Store if required.

Related links

Cluster attributes field descriptions on page 61

Cluster attributes field descriptions

For more information about setting cluster attributes, see the Administering Avaya Breeze[™].

Basic Attributes

Name	Description	Default value	Change to
Cluster Profile	Type of profile for the	Not selected	Context Store
	cluster.		Important:
		Ensure that you set this value to Context Store.	
Cluster Name	Name of the cluster	None	Any name describing the cluster.
			Important:
			Ensure that no spaces are included in string.
			This field is mandatory.

Name	Description	Default value	Change to
Cluster IP	IP address for the cluster	None	The designated cluster IP for this Context Store cluster.
			This field is mandatory for the Load Balancing feature.
			😿 Note:
			This field is not applicable for a single-node deployment.
Enable Cluster Database	This check box is disabled by default. Not applicable to Context Store.	Not set	You must not select this check box.
Enable Database Auto Switchover	This check box is selected by default. Not applicable to Context Store.	Set	Do not update.
Description		None	Any text describing the cluster.
			This field is optional.

Cluster Attributes

Name	Description	Default value	Change to
Authorization Service Address		None	Do not update
Cluster Activity Status			
Default SMS Connector Service			
Grid password	Specify a password for grid security.	None	
Use secure grid?	If selected, grid security is enabled.	Not set	
HTTP or HTTPS limit on connections	Number of http/https connections.	3000	Do not update
HTTP or HTTPS traffic rate limit in bytes/sec	Http/https traffic rate in bytes per second.	4000000	Do not update
HTTP Load Balancer backend server max failure response		15	Do not update

Name	Description	Default value	Change to
timeout period (seconds)			
Max number of failure responses from HTTP Load Balancer backend server		2	Do not update
Network connection timeout to HTTP Load Balancer backend server (seconds)		10	Do not update
Only allow secure web communications		Enabled	The administrator or user can decide whether to disable this attribute or leave it as enabled.
Is Load Balancer enabled?	Select this check box to enable load balancing for the cluster. If you do not select this check box, load	Not set	Select check box to enable the load balancer. You must enable the check box.
	balancing will not be available on the cluster.		 Note: This field is not applicable for a single-node deployment.
Is session affinity enabled?	Not applicable to Context Store.		Do not update
Trusted addresses for converting to use X- Real-IP for session affinity	Not applicable to Context Store.		Do not update
The maximum number of Avaya Breeze servers allowed in a Cluster	Max number of Avaya Breeze servers allowed in an a cluster. This field is not editable.	5	
Default identity for special make call cases			
Media server shuffle out timer (seconds)			
Limit on the memory (GB) to allocate for base processes			

Name	Description	Default value	Change to
Percent of memory to allocate base processes			
Percent of memory to allocate for WAS			
Limit on the memory (GB) to allocate for WAS			
Minimum TLS Version for Non-SIP Traffic			
Minimum TLS Version for SIP Call Traffic			
List of required snap- ins including minimum version	Lists snap-ins required for a Context Store cluster.	"CSManager-1.0.0.0.0",	
	This field is not editable.		
Default SIP Domain	Not applicable to Context Store.		Do not update
Use secure signaling for platform initiated SIP calls	Not applicable to Context Store.		
Preferred Minimum Session Refresh Interval (secs)	Not applicable to Context Store.		Do not update
Use early pre-answer media?	Not applicable to Context Store.		Do not enable
Use short replication interval?	Not applicable to Context Store.		Do not enable

Related links

Configuring a cluster and installing mandatory services on page 59

Installing the optional Context Store services

Before you begin

Download the optional services that you want to install from PLDS.

Record the information mentioned in the Key customer configuration information on page 53.

About this task

Two approaches to installing optional services are as follows:

- Deploy the optional services manually after creating a cluster.
- · Deploy the optional services as part of creating a cluster.

This task provides basic details about manually installing the optional Context Store snap-in services. For detailed procedures about installing snap-in services, see *Deploying Avaya Breeze*[™].

😵 Note:

The mandatory snap-in service, CSManager, is installed when you create a cluster.

Procedure

- 1. On the System Manager web console, click Elements > Avaya Breeze.
- 2. In the left navigation pane, click Service Management.
- 3. On the **Service Management** page, select and load the optional Context Store services. For more information about loading a service, see *Administering Avaya Breeze*[™].
- 4. Configure the attributes of the Context Store services as described in <u>Configuring</u> <u>attributes for a service</u> on page 77.
- 5. On the **Service Management** page, select and install the Context Store service.

For more information about installing a service, see Administering Avaya Breeze[™].

Verifying a successful deployment

Procedure

Open your web browser and type the following URL:

```
https://clusterIP/services/<Service name>/
```

Where:

- clusterIP is the IP address of the Context Store cluster where the service that you want to verify is running
- <Service name> is the service that you want to verify: For example, CSManager.

Note:

You must enter the service names as they are displayed in the **Name** column on the Service Management page.

Ensure that you have configured certificate authentication on the browser. For more information, see <u>Certificate-based authentication</u> on page 99.

The web browser displays a confirmation message if the service that you are trying to verify is successfully installed in the specified cluster. If you are verifying CSRest service, Context Store

displays the CSRest documentation and the CSRest client. CSRest Client is not supported when using HTTPS.

Assigning permissions to an authorization client

Before you begin

- · Configure LDAP user and synchronize it with System Manager
- Import LDAP server certificate.

For more information about configuring LDAP user, synchronizing the user with System Manager, and importing LDAP server certificate, see *Deploying Avaya Oceana[™] Solution*.

Procedure

1. On the System Manager web console, click **Home > Elements > Avaya Breeze > Configuration > Authorization**.

The system displays the Clients tab.

- 2. Select the CS cluster name and click Edit Grants.
- 3. Click New.

The system displays the Create Grants for Authorization Client: <client name> screen.

- 4. Select the resource from the Resource Name drop-down list.
- 5. Select the version of the resource cluster from the Resource Cluster drop-down list.
- 6. Select the feature that the resource cluster wants to advertise from the **Feature** drop-down list.
- 7. Click the **Select** check box corresponding to the value you want to select.
- 8. Click **Commit**.

Related links

<u>Authorization</u> on page 41 CSRest attribute descriptions on page 83

Geo redundancy and External Data Mart deployment

The Geo redundancy and External Data Mart features have no dependencies or restrictions on each other; either or both of these optional features can be enabled on a Context Store cluster.

To use the Geo redundancy feature, you must:

1. Manage the Context Store clusters from the same System Manager.

- 2. Individually enable Geo redundancy for each cluster in the Context Store set up.
- 3. Allocate identical resources to the clusters in a geo-redundant deployment.
- 4. Restart the Context Store cluster after enabling or reconfiguring Geo redundancy.

For more information, see Enabling Geo redundancy in Context Store on page 67.

To use the External Data Mart feature, you must:

- 1. Identify and configure the external database to which context data is saved.
- 2. Individually enable the External Data Mart for each cluster in the Context Store set up.
- 3. Restart the Context Store cluster after enabling or reconfiguring the External Data Mart.

For more information, see Enabling External datamart in Context Store on page 68.

To use Context Store without Geo redundancy and External Data Mart, follow the procedure mentioned in <u>Configuring a cluster and installing mandatory services</u> on page 59.

Related links

Enabling Geo redundancy in Context Store on page 67 Enabling External Data Mart on page 68 Enabling External Data Mart provisioning on page 69

Enabling Geo redundancy in Context Store

Before you begin

- Ensure you have configured two Context Store clusters.
- Create and download the keystore, from the **Security** > **Certificate** > **Authority** page in the System Manager web console. For more information about certificates, see *Avaya Context* Store Snap-in Developer Guide.

About this task

This topic provides information about enabling session preservation and thereby achieve Geo redundancy in Context Store.

You cannot enable the Geo redundancy feature at runtime. You must restart the cluster to redeploy the data grid with the updated configuration.

You must perform this procedure on each Avaya Breeze[™] node in both the Context Store clusters.

Procedure

1. To configure security for the data grid, navigate to /opt/Avaya/dcm/gigaspace/ security/ and put the keystore certificate in each Avaya Breeze[™] node in the cluster:

The certificate enforces SSL encryption on the replication channel. For more information about the certificate based authentication and creation of the keystore certificate, see *Avaya Context Store Snap-in Developer Guide*.

😵 Note:

The replication does not work without the SSL encryption.

If an Avaya Breeze[™] node is upgraded or redeployed, the configuration steps for Geo redundancy security must be repeated.

- 2. Enable the Geo redundancy feature and configure attributes:
 - a. On the System Manager web console, click **Elements > Avaya Breeze > Configuration > Attributes**.
 - b. Select **Service Clusters** and select the cluster and the service **CSManager** from the drop-down list of services.
 - c. Enter true in the Cluster Deny Service on 2 node outage field.
 - d. Enter true in the GEO: Enable session preservation field.
 - e. Configure the other GEO attributes. All attributes related to Geo-Redundancy configuration are prefixed with **GEO**:.
- 3. Configure the CSManager service data grid:
 - a. Set the applicable values for **DataGrid Settings** and **Gateway Service container** size for the deployment size

See the *Certified Deployments* section in *Avaya Context Store Snap-in Release Notes* for applicable values.

- b. Click Commit.
- 4. Restart all the Avaya Breeze[™] servers in the Context Store cluster.
- 5. Repeat these steps on the second cluster.

Next steps

After you configure and restart the second Context Store cluster, confirm that replication is active between both the Context Store spaces by creating a context object in one cluster and retrieving the context object from the other cluster.

Configure the load balancer for geo redundancy.

Related links

<u>Geo redundancy and External Data Mart deployment</u> on page 66 <u>Third party load balancer configuration requirement</u> on page 90

Enabling External Data Mart

Before you begin

Ensure that you create the database table(s) before enabling the External Data Mart feature. For more information about creating database tables, see <u>Creating database tables for External Data</u> <u>Mart</u> on page 30

About this task

You cannot enable the External Data Mart feature at runtime. You must restart the cluster to redeploy the data grid with the updated configuration.

Procedure

- 1. On the System Manager web console, click **Elements** > **Avaya Breeze** > **Configuration** > **Attributes**.
- 2. Click the Service Clusters tab.

Note:

To use only one EDM in the geo solution, you must disable EDM from the other cluster in the **Service Cluster** tab.

- 3. From the Service drop-down menu, select CSManager
- 4. Enter true in the EDM: Enable Persistence to database field.
- 5. Configure the other EDM attributes. All attributes related to External Data Mart configuration are prefixed with **EDM**:.
- 6. Configure the CSManager service data grid:
 - a. Set the applicable values for **DataGrid Settings** and **Mirror Service container size** for the deployment size

See the *Certified Deployments* section in *Avaya Context Store Snap-in Release Notes* for applicable values.

- b. Click Commit.
- 7. Restart all the Avaya Breeze[™] servers in the Context Store cluster.

Next steps

Confirm that the external data mart is active by creating a context object in the cluster and verifying that it has been written to the database.

Related links

Geo redundancy and External Data Mart deployment on page 66

Enabling External Data Mart provisioning

Before you begin

Ensure that you create the database table(s) before enabling the External Data Mart provisioning feature. For more information about creating database tables, see <u>Creating database tables for</u> <u>External Data Mart</u> on page 30

About this task

You cannot enable the EDM provisioning feature at runtime. You must restart the cluster to redeploy the data grid with the updated configuration.

Procedure

- 1. On the System Manager web console, click **Elements** > **Avaya Breeze** > **Configuration** > **Attributes**.
- 2. Click the **Service Clusters** tab.
- 3. From the Service drop-down menu, select CSManager
- 4. Enter true in the EDM: Enable Provisioning from database field
- 5. Configure the other EDM attributes. All attributes related to External Data Mart configuration are prefixed with **EDM**:.

😵 Note:

Enabling the **EDM: Space supports EDM database connection** attribute is not required to facilitate data provisioning, but must be enabled if you also wish to persist data to either table in the database.

- 6. Configure the CSManager service data grid:
 - a. Set the applicable values for **DataGrid Settings** and **Mirror Service container size** for the deployment size

See the *Certified Deployments* section in *Avaya Context Store Snap-in Release Notes* for applicable values.

- b. Click Commit.
- 7. Restart all the Avaya Breeze[™] servers in the Context Store cluster.

Example

Next steps

Confirm that the provisioning was successful by querying a context object in the cluster that existed in the database.

Related links

Geo redundancy and External Data Mart deployment on page 66

Deploying Context Store PDC on Orchestration Designer

Before you start deploying PDC on Orchestration Designer, ensure that you have:

- Installed Orchestration Designer 6.0 or later in the system where you want to deploy Context Store PDC. The Orchestration Designer software is available on <u>http://www.avaya.com/</u> <u>devconnect</u>.
- The latest Context Store PDC. The Context Store PDC is available on Avaya DevConnect Program at <u>http://www.devconnectprogram.com/site/global/products_resources/</u> <u>avaya_breeze/avaya_snap_ins/context_store/overview/index.gsp.</u>

• The sample application that uses the Context Store PDC. The sample application is available on Avaya DevConnect Program at http://www.devconnectprogram.com/site/global/ products_resources/avaya_breeze/avaya_snap_ins/context_store/overview/index.gsp.

You must also ensure that the machine where you plan to install Context Store PDC can resolve the cluster IP address. If DNS is not set up in the machine, you must add the cluster IP address in the *hosts* file.

For more information about Orchestration Designer, see *Avaya Aura*[®] Orchestration Designer *Developer's Guide*.

For more information about installing and using the PDC, see *Avaya Context Store Snap-in Developer Guide* available on <u>http://www.avaya.com/devconnect</u>.

Avaya Context Store Snap-in Developer Guide provides detailed information about the following tasks:

- Configuring Orchestration Designer to use Tomcat.
- Configuring certificates for the Context Store PDC.
- Running the Test project.
- Configuring the Context Store PDC.
- Using the Context Store connector in the workflow.
- Creating the variables and getting the output variables.

Deploying CS Task Type

Overview of CS Task Type deployment

Before you install Context Store Task Type for Engagement Designer, ensure that you have:

- Release 3.2.0 of Context Store.
- Release 3.2.0 of Engagement Designer.

😵 Note:

The Engagement Designer cluster and the Context Store cluster must be managed by the same System Manager.

Install Engagement Designer into the General Purpose cluster. For more information about installing Engagement Designer, see *Avaya Engagement Designer snap-in Reference*.

😵 Note:

If the Engagement Designer cluster has multiple nodes, you must select the **Is session affinity enabled?** check box for the Engagement Designer cluster while creating the cluster.

For Release 3.2 of Engagement Designer, Context Store Task Type is an SVAR file. When the Engagement Designer cluster has reached the Installed state, restart all nodes in the Engagement Designer cluster. After the cluster reaches a stable state after the restart, upload the CS Task Type Bundle through the Engagement Designer Administration console.

For more information about accessing the Engagement Designer Administration or Design consoles, see *Getting Started with Avaya Engagement Designer*.

Related links

Context Store deployment checklist on page 54

Installing CS Task Types SVAR on Engagement Designer

Before you begin

Deploy Engagement Designer.

Procedure

- 1. Download the CS Task Types SVAR file from PLDS.
- 2. Open the following URL in a web browser.

https://Applicable-ED-IP-ADDRESS/services/EngagementDesigner/
admin.html

For more information on accessing the Engagement Designer Admin console, see *Getting Started with Avaya Engagement Designer*.

- 3. Click the Bundles tab.
- 4. Click Upload Bundle.
- 5. Click Choose File.
- 6. Browse and select the CS Task Types SVAR file.
- 7. Click Upload.

The system uploads the file.

8. Click the check box corresponding to the CS Task Types SVAR file and click **Deploy Bundle**.

You should now be able to see the Context Store bundle in the Engagement Designer Design console.

Non-OSGi workflows

From version 3.1, CS Task Type has extra parameters to provide the following new functionality of Context Store:

· Geo-redundancy

- AliasIds
- Audit trail

Therefore, you must create the flows from the outset. If you need to use a previous non-OSGi flow, import the flow into Engagement Designer and remap the missing mapping links.

For more information about CS Task Type, see Avaya Context Store Snap-in Developer Guide.

Updating non-OSGi workflows

Procedure

- 1. Copy the workflows that you want to upgrade to a temporary directory in Engagement Designer.
- 2. Run the portFlowToOSGi.sh script on each workflow.

The system generates new xml files.

3. Copy all the new xml files to your computer, and rename them by removing the appended OSGi string.

For example, MyFlowFileName.xml

The action produces a new xml file that is compatible with the new OSGi-based CS Task Type.

- 4. Import the xml files into Engagement Designer.
- 5. Click Save.
- 6. Open each CS Task.
- 7. Remap the missing mapping links.

Context Store Upgrade overview

To upgrade a Context Store snap-in service in Avaya Breeze[™] you must install a new version of the snap-in service. For detailed procedure and information about upgrading various Context Store snap-in services, see *Avaya Context Store Snap-in Release Notes*.

Context Store uninstallation and deletion

Context Store uninstallation overview

The options are:

- Delete a Context Store cluster: To uninstall the mandatory Context Store services, you must delete the Context Store cluster.
- Uninstall a snap-in service: For optional snap-in services, you can uninstall a service snap-in: When you uninstall a service, the system does not remove the attributes from the Avaya Breeze[™] PostgreSQL database.
- Delete a snap-in service: When you delete a service, the system removes the attributes from the Avaya Breeze[™] PostgreSQL database.

😵 Note:

To completely uninstall Context Store and the data grid, you must delete the services so that the configuration information is removed from the Avaya Breeze[™] server database.

Deleting a Context Store cluster

Procedure

- 1. On the System Manager web console, click **Elements** > **Avaya Breeze** > **Cluster Administration**.
- 2. Select the Context Store clusters that you want to delete.
- 3. On the Cluster State list, select Deny New Service, if the clusters are in Accepting state.
- 4. On the Warning box, click Continue.

The states of the selected clusters change to **Denying**.

- 5. Click Delete.
- 6. On the Warning box, click **Continue**.

Next steps

Verify that the Context Store cluster was deleted successfully:

- 1. On the **Cluster Administration** page of System Manager web console, verify that the clusters that you deleted in the above procedure have been removed from the list.
- 2. On the **Service Management** page of System Manager web console, verify that the status of the Context Store services have been changed from **Installed** to **Loaded**.

Uninstalling an optional snap-in service

About this task

This task provides information about uninstalling an optional service snap-in.

😵 Note:

- When you uninstall a service, the system does not remove the attributes from the Avaya Breeze[™] Postgres database.
- The system preserves the DataGrid and the entries written to spaces until the lease times expire.

Procedure

- 1. On the System Manager web console, click **Elements > Avaya Breeze**.
- 2. In the left navigation pane, click **Cluster Administration**.
- 3. On the Cluster Administration page, select the check box for the cluster and then click **Edit**.
- 4. On the Cluster Editor page, perform the following steps:
 - a. Click the **Services** tab.

The system displays the list of services installed in the cluster.

- b. Click the X icon for the service that you want to uninstall.
- c. Click Commit.

Next steps

To verify that the service is uninstalled, click **Elements** > **Avaya Breeze** and perform the following steps:

1. On the Server Administration page, verify that the **Service Install Status** for the service is **Uninstalling**.

😒 Note:

After the service is uninstalled, the State of the service is Loaded.

- 2. On the Service Management page, verify that the State of the service is Loaded.
- 3. On the Cluster Administration page, perform the following steps:
 - a. Click Show.
 - b. Click the required server and verify that the Service Status page does not display the uninstalled service.

Deleting a snap-in service

Before you begin

Before deleting a service snap-in, you must ensure that the service snap-in is uninstalled.

For more information, see Uninstalling a service snap-in on page 75.

About this task

This task provides information about deleting a service snap-in. When you delete a service, the system removes the attributes from the Avaya Breeze[™] Postgres database.

😵 Note:

Delete all the previous version of Context Store services. Also, note down the existing attributes configurations, so that you can refer to it during the new installation.

Procedure

- 1. On the System Manager web console, click **Elements** > **Avaya Breeze**.
- 2. In the left navigation pane, click Service Management.
- 3. On the Service Management page, perform the following steps:
 - a. Verify that the State of the service is Loaded.
 - b. Select the service that you want to delete and then click **Delete**.
 - c. In the dialog box, select the **Please Confirm** check box to confirm the deletion.
 - d. Click **Delete**.

Next steps

To verify that the service is deleted, click **Elements** > **Avaya Breeze** and perform the following steps:

- 1. Click Service Management.
- 2. Verify that the Service Management page does not display the deleted service.

Chapter 6: Administering Context Store

Configuring attributes for a service

About this task

Use this procedure to configure values for a Context Store service. The configuration is a one-time activity that you must perform after installing a service.

Important:

If you plan to use External Data Mart, configure the External Data Mart attributes while you configure the CSManager attributes. In CSManager attributes, External Data Mart is referenced as *EDM*.

Procedure

- 1. On the System Manager web console, click **Elements** > **Avaya Breeze**[™].
- 2. In the navigation pane, click Configuration > Attributes.
- 3. Click the Service Clusters tab
- 4. From the **Service** drop-down menu, select the service that contains the service attributes you want to configure.

The table displays all the attributes that you can configure for the service, including a description of each attribute.

- 5. For the attribute you want to change:
 - a. Click Override Default.
 - b. Enter the new value or string in the Effective Value field.
- 6. Click **Commit** to save your changes.

CSManager attribute descriptions

After configuring the following CSManager attributes which control the data grid, EDM, or Geo Redundancy, you must restart all servers in the cluster:

- ContextStore DataGrid type
- ContextStore ManagerSpace DataGrid Settings

- ContextStoreSpace DataGrid Settings
- · Event Stream: Enable Event Streaming

If you enable the Event Streams feature, ContextStoreSpace DataGrid must be reduced by 6GB, and therefore cluster will require restart to deploy the smaller ContextStoreSpace DataGrid if enabling this feature on an existing DataGrid.

- All attributes that started with "EDM:"
- · All attributes that started with "GEO:"

Field	Description	
Cluster Deny Service on two node outage	Determines whether to deny or accept service when two nodes in a cluster are unavailable. If disabled, the last remaining node continues to attempt service requests. The accepted values are:	
	 true: If two nodes in a cluster are unavailable, the third node also denies service. 	
	 false: Even if two nodes in a cluster are unavailable, the third node tries to serve incoming requests. 	
	The default value is, <i>false</i> .	
	😵 Note:	
	This attribute is not applicable for one or two-node deployments.	
ContextStore DataGrid type	Mandatory attribute	
	The type of Context Store data grid. Four options are available:	
	• STANDARD: A single cluster deployment with non-provisioned data grid	
	GEO: A geo-redundant deployment with non-provisioned data grid	
	PROVISIONED: A single cluster deployment with provisioned data grid	
	 PROVISIONED-GEO: A geo-redundant deployment with provisioned data grid 	
	STANDARD is the default deployment.	
ContextStore ManagerSpace	Mandatory attribute	
DataGrid Settings	A comma-separated list of three numbers: {memoryCapacityPerContainer},{maximumMemoryCapacity}, {maximumRelocationsPerMachine}.	
	The default values are 1,2,1	
	The system interprets a numeric value only as gigabytes. You can specify megabytes with an m or mb after the number. For example, 2MB.	
	For values specific to your deployment type, see the <i>Certified Deployments section in Avaya Context Store Snap-in Release Notes</i> .	
ContextStoreSpace DataGrid Settings	Mandatory attribute	

Field	Description	
	A comma-separated list of three numbers: {memoryCapacityPerContainer},{maximumMemoryCapacity}, {maximumRelocationsPerMachine}.	
	The default values are 8,118,1	
	The system interprets a numeric value only as gigabytes. You can specify megabytes with an $\tt m$ or <code>mbafter</code> the number. For example, 1MB.	
	For values specific to your deployment type, see the <i>Certified Deployments section in Avaya Context Store Snap-in Release Notes</i> .	
CS Audit: Event limit	Configure the limit of event entries in the audit trail of context objects.	
	• Default: 0	
	• Range: 0 to 50	
	You can update this attribute dynamically. Changes you make do not become effective on a context until the next interaction with that object.	
	🛪 Note:	
	If you enable the Audit trail feature in a geo-redundant deployment, the CS Audit: Event limit attribute must be set identically in both clusters.	
CS Default Lease Time	Default lease time, in seconds, for context data to live in the in-memory data cache Context Store automatically removes a context if the context remains in Context Store for the lease period without any change.	
	This attribute specifies the default lease time that Context Store uses when you do not specify any lease time for a context entry.	
	Default: 7200	
	You can update this attribute dynamically.	
	For values specific to your deployment type, see the <i>Certified Deployments section in Avaya Context Store Snap-in Release Notes</i> .	
	😒 Note:	
	CS Default Lease Time is not applicable to the contexts in the CS_PROVISION table. The contexts in the CS_PROVISION table has an infinite lease time and remain in the data grid permanently until the contexts are deleted manually.	
CS Maximum Lease Time	Maximum lease time, in seconds, for Context data. Warnings will be logged for leases longer than this value	
	If the average lease time for the cluster exceeds this value, Context Store raises an error event. If a context is created or updated with a lease time that exceeds this value, Context Store logs only a warning.	
	• Default: 14400	
	You can update this attribute dynamically.	
<u></u>	Table continues	

Field	Description
CS Threshold: Instance High Requests per Second	High threshold on Context Store instance requests per second. Must be greater than related Minima. If the requests per second for an instance exceeds this value, the Context Store instance rejects the further requests and raises an event.
	• Default: 650
	• Range: 1 to 650
	You can update this attribute dynamically.
	For values specific to your deployment type, see the <i>Certified Deployments section in Avaya Context Store Snap-in Release Notes</i> .
CS Threshold: Instance Low Requests per Second	Low threshold on Context Store instance requests per second. Must be lower than related Maxima. If the requests per second for an instance exceeds this value, the Context Store instance raises an event, without rejecting any further requests.
	• Default: 550
	• Range: 1 to 650
	You can update this attribute dynamically.
	For values specific to your deployment type, see the <i>Certified Deployments section in Avaya Context Store Snap-in Release Notes</i> .
CS Threshold: Max Error Rate	Threshold for maximum tolerated Context Store request error rate in percentage
	• Default: 20
	• Range: 1 to 100
	You can update this attribute dynamically.
CS Threshold: Max Latency	Threshold for maximum tolerated Context Store request latency in milliseconds. When the average latency exceeds the value you have specified in this field, Context Store raises an event.
	• Default: 250
	• Range: 1 to 5000
	You can update this attribute dynamically.
	😿 Note:
	The average latency of a request in an hour is less than 250 milliseconds with a maximum latency of two seconds.
CS Threshold: Service High Requests per Second	High threshold on Context Store service requests per second. Must be greater than related Minima. If the service requests per second for a Context Store cluster exceeds the value you have specified in this attribute, Context Store rejects the further service requests and also raises an event.
	Default: 1240

Field	Description	
	• Range: 1 to 1240	
	You can update this attribute dynamically.	
	For values specific to your deployment type, see the <i>Certified Deployments section in Avaya Context Store Snap-in Release Notes.</i>	
CS Threshold: Service Low Requests per Second	Low threshold on Context Store service requests per second. Must be lower than related Maxima. If the service requests per second for a Context Store cluster exceeds the value you have specified in this attribute, Context Store raises and alarm, without rejecting the further service requests.	
	• Default: 1000	
	• Range: 1 to 1240	
	You can update this attribute dynamically.	
	For values specific to your deployment type, see the <i>Certified Deployments section in Avaya Context Store Snap-in Release Notes</i> .	
EDM: Database dialect	Dialect of the customer-provided External Data Mart database	
	Depending on the database , you must enter specific values:	
	• PostgreSQL: org.hibernate.dialect.PostgreSQLDialect	
	• Oracle: org.hibernate.dialect.Oracle10gDialect	
	• Microsoft SQL Server: org.hibernate.dialect.SQLServerDialect	
	You cannot update this attribute dynamically.	
EDM: Database driver class	Driver of the customer-provided External Data Mart database.	
	Depending on the database , you must enter specific values:	
	• PostgreSQL: org.postgresql.Driver	
	• Oracle: oracle.jdbc.driver.OracleDriver	
	 Microsoft SQL Server: com.microsoft.sqlserver.jdbc.SQLServerDriver 	
	You cannot update this attribute dynamically.	
EDM: Database password	Password of the customer-provided External Data Mart database	
	You cannot update this attribute dynamically.	
EDM: Database URL	URL of the customer-provided External Data Mart database.	
	Depending on the database , you must enter specific values:	
	• PostgreSQL : jdbc:postgresql://< datebase_IP>: <database port>/<database name=""></database></database 	
	• Oracle:jdbc:oracle:thin:@ <datebase_ip>:<database port>/<database name=""></database></database </datebase_ip>	
	Table continues	

Field	Description	
	• Microsoft SQL Server: jdbc:sqlserver:// <datebase_ip>:<database port="">;databaseName=<database name></database </database></datebase_ip>	
	You cannot update this attribute dynamically.	
EDM: Database username	Username of the customer-provided External Data Mart database	
	You cannot update this attribute dynamically.	
EDM: Enable Persistence to database	Setting this to 'true' will enable persistence of Context data to the customer-provided External Data Mart. The accepted values are:	
	 true: Enables persistence to the external data mart. 	
	 false: Disables persistence to the external data mart 	
	The default value is <i>false</i> .	
EDM: Enable Provisioning from database	Setting this to 'true' will enable provisioning of context data from the customer-provided External Data Mart. The accepted values are:	
	 true: Enables provisioning to the external data mart. 	
	 false: Disables provisioning to the external data mart 	
	The default value is <i>false</i> .	
EDM: Mirror Service	Memory required for the External Data Mart Mirror Service deployment.	
container size	The default value is 4.	
	The system interprets a numeric value only as gigabytes. You can specify megabytes with an m or mb after the number. For example, 2m.	
	For values specific to your deployment type, see the <i>Certified Deployments section</i> in <i>Avaya Context Store Snap-in Release Notes</i> .	
EDM: Space supports EDM database connection	Setting this to 'true' will configure ContextStoreSpace to persist Context data to the customer provided External Data Mart. The accepted values are:	
	 true: Enables persisting data to external data mart 	
	 false: Disables persisting data to external data mart 	
	The default value is <i>true</i> .	
	Enable this parameter for the External Data Mart persistence feature to work.	
Event Stream: Enable Event Streaming	Setting this to 'true' enables clients to subscribe for personalized events from Context Store.	
	The default value is <i>false</i> .	
	Enable this parameter for the Event Streams feature to work.	
	Table continues	

Field	Description	
	😵 Note:	
	If you want to enable the Event Streams feature, ensure that there is 6 GB memory on the Avaya Breeze [™] cluster.	
GEO: Enable session preservation	Setting this to 'true' enables Geo-Redundancy between configured Context Store clusters. The accepted values are:	
	true: Enables geo redundancy	
	false: Disables geo redundancy	
	The default value is <i>false</i> .	
Geo: Gateway Service	Memory required for Geo-Redundancy Gateway Service deployment.	
container size	The system interprets a numeric value only as gigabytes. You can specify megabytes with an m or mb after the number. For example, 2m.	
	For values specific to your deployment type, see the <i>Certified Deployments section in Avaya Context Store Snap-in Release Notes</i> .	
GEO: Keystore file name	Certificate name of the Geo-Redundancy keystore.	
GEO: Keystore password	Password of the Geo-Redundancy keystore.	
GEO: Target cluster Id	Name of the target cluster on the geo redundant site	
	Important:	
	Ensure that no spaces are included in the string.	
GEO: Target cluster lookup locators	Comma-separated list of IP addresses of the target cluster's lookup- locator nodes. Non-lookup-locator nodes must not be included.	
Supplier Id	The supplier Id that Avaya provides.	
	The default value is 10000000.	

Related links

<u>Context Store Event Streams</u> on page 25 <u>Configuring a cluster and installing mandatory services</u> on page 59

CSRest attribute descriptions

Field	Description	
Authorization Service Address	Enter the fully qualified domain name (FQDN) or IP of the node/cluster where the Authorization Service is installed.	
	😿 Note:	
	If the Authorization service is installed on the Context Store cluster, you need not set this attribute.	

Field	Description
Enable Breeze Authorization Service	Enables authorization against the Breeze Authorization Service. The accepted values are:
	true: Enables authorization against the Breeze Authorization Service
	false: Disables authorization against the Breeze Authorization Service
	The default value is false.
Require user for Breeze	Set to true to require user access only for Breeze Authorization Service
Authorization Service	If you enable this attribute, the system disables the Get Token and Get Token by Scope API methods.
Supplier Id	The supplier Id that Avaya provides.

Related links

Assigning permissions to an authorization client on page 66 Authorization on page 41 Configuring a cluster and installing mandatory services on page 59 Context Store REST on page 19

CSScreenPop attribute descriptions

Field	Description
Base for URL	You must provide this path if you set the override format as URL. You must specify a valid URL to which the system can pass parameters.
	The default URL is that of a demonstrative CSS file of Context Store. Replace the default URL with the URL of the CSS file.
	The default URL is: http://127.0.0.1/?
Context Store Rest Version	You must set this value as the version of the CSRest snap-in that CSScreenPop must use. If you fail to set this correctly, CSScreenPop requests fail as it cannot access Context Store.
	The default value is 3.0.0.0.xxx which does not work. You must change the value to point to the CSRest SVAR version that is deployed in the Context Storecluster.
CSS for HTML	You must provide this path if you set the override format as HTML. This path must point to a valid CSS file.

Field	Description
	The default URL is that of a demonstrative CSS file of Context Store. Replace the default URL with the URL of the CSS file.
	The default URL is: /services/CSScreenPop/ demo/css/demo.css
Identifier Delimit Character	Use this field to specify the character that delimits the UCID. Context Store extracts the contextId based on the value that you specify for this attribute and the default setting for the UCID delimit position.
	For example, if the values of:
	 The default setting for the UCID delimit character = \.
	• The UCID = 1111111.222222.333333.444444
	Then Context Store detects the contextId as 333333.
Identifier Delimit Position	This setting is the occurrence of the UCID delimiter that marks the start of a contextId in a UCID string. The next instance of the delimiter marks the end of the contextIdn.
	The default setting for the UCID delimit position = 2
Identifier Parsing Position	Use this field to detect a UCID from a string that contains the id. The valid value for this attribute must contain a comma separated list of two positive integers. The first integer is the start location of the id and the second number is the end location of the id. The default value is: 0,10.
JavaScript for HTML	The JavaScript file that must be included when selecting the html format. Provide the http link to where the JavaScript file is hosted.
User Rule 01 - 20	You can enter customized rules for Context Store Screen Pop. The system supports up to 20 user defined rules. This field is empty by default. Select the Override Default check box to enter the user defined rule.

CSNotifications attribute descriptions

Name	Description
Subscription <i>number</i>	Configure the attributes in each subscription field to subscribe for the notifications. The available
Where <i>number</i> is the serial number of subscription. One subscription is for one client. You can have a maximum of five subscriptions	attributes are:
	 endpointURI: This attribute is for configuring the receiver endpoint for CSNotifications. Specify the full URI of the endpoint that will receive notifications for this subscription.
	• tenantId : This attribute filters the notifications you receive. Only the contexts created with the specified tenantId will trigger notification for this subscription.
	• groupld : This attribute filters the notifications you receive. Only the contexts with the specified groupld will trigger notification for this subscription.
	• enable:
	 true: Enables the subscription
	 false: Disables the subscription

Related links

Context Store Notifications on page 23

CSRules attribute descriptions

Field	Description
Rule 01: Eventing Connector Family	Enter the Family value you entered when creating the event.
Rule 01: Eventing Connector Type	Enter the Type value you entered when creating the event.
Rule 01: Eventing Connector URL	Enter the HTTP location of the Eventing Connector where the ED Workflow is installed.
Rule 01: Eventing Connector Version	Rules Eventing Connector Version for rule 01. This should match the Family value you entered when creating the event.
Rule 01: Eventing Rule Priority	Enter priority for Rule 01.
	This should be a number between 1 and 5.

Field	Description	
	 Only one rule can fire and the priority determines which rule will fire when the context matches multiple rules. 	
Rule 01: Identifier	Enter a name for Rule 01.	
	This should be an alphanumeric string.	
Rule 01: Key	Enter the key for Rule 01.	
Rule 01: Operator	Enter operator for Rule 01.	
	This must be set to '=='	
Rule 01: Value	Enter a value for Rule 01.	
Supplier Id	Enter the Supplier Id that Avaya provided.	

Related links

Context Store Rules on page 24

CSQuery attribute descriptions

Field	Description
EDM: Database password	Enter database password.
EDM: Database username Enter the user name of the database.	
Supplier Id	The supplier Id that Avaya provides.

😵 Note:

After configuring the EDM: Database password and EDM: Database username attributes, you must restart all servers in the cluster simultaneously.

Related links

Context Store Query on page 21

CSSoap attribute descriptions

Field	Description
Context Store Rest Version	Enter the version of CSRest installed and selected on the cluster. For example, 3.2.0.0.xxx
Supplier Id	The supplier Id that Avaya provides.

Related links

Context Store SOAP on page 20

Chapter 7: High availability

High availability within a cluster

😵 Note:

- Context Store does not support high availability for single-node deployments. If the single node fails, you cannot recover the data.
- For a cluster with more than one node, Context Store supports data preservation for only one node failure. For more information about multiple node failure and high availability, see Avaya Context Store Snap-in Developer Guide.

Context Store uses Avaya Breeze[™] and data grid to achieve high availability. For High availability, the Context Store cluster must consist of two or more Avaya Breeze[™] nodes that are dedicated for Context Store. Context Store creates a data grid across the Avaya Breeze[™] servers in the cluster where you deploy Context Store, so that the servers can operate in an active/active mode.

To achieve high availability, Context Store data grid uses the following techniques:

- Self healing: The Context Store data grid has self healing and disaster recovery capabilities that minimize the chances of a downtime. The data grid also preserves its states so that, in case of a system failure, you can recover the data grid in its latest state.
- Data sharing: All the servers in a Context Store cluster shares the same data grid. Even if one server is unavailable, the other servers in the Context Store cluster can use the data present in the data grid.
- Data partition and redundancy: Context Store partitions the data that is present in the data grid and distributes the data across different machines. This distributed structure enables the system to hold more data than the capacity of a single machine and also helps attain high availability. The system keeps a backup of data from each partition so that if one source becomes unavailable, Context Store can retrieve the same data from the backup location.

The Context Store cluster is accessible through a cluster IP address that is maintained by a highly available load balancer. The load balancer distributes HTTP requests across each of the Avaya Breeze[™] servers in the cluster. If one of the servers in the Context Store cluster is unavailable, Context Store can still work without loss of data and significant impact to its performance. However, unavailability of two servers might result in loss of data and failing HTTP requests. If two servers are unavailable in a cluster, restart the cluster to clear old context data and restore Context Store to a known state. When the cluster is restored to a known state, data replication in the cluster is not accurate for updates that occur during the failover period. The data and EDM on the other cluster, which services the contexts during failover, is accurate.

Server failure

If any of the servers in the cluster are unavailable, Context Store redirects the client requests to the primary partition. If the primary partition is unavailable, Avaya Breeze[™] determines a new primary partition to direct the client requests. Context Store might have an increased response time during this negotiation process, until a new primary partition is assigned.

Server restoration

When an unavailable server becomes available, Avaya Breeze[™] readjusts the partitions to accommodate the new server. If the server that becomes available contains a primary partition, Avaya Breeze[™] determines a new primary partition to serve the client requests. Context Store might have an increased response time during this negotiation process, until a new primary partition is assigned.

Geo redundancy

Context Store Geo redundancy overview

Context Store Geo redundancy is an architecture that you can configure to enhance high availability of Context Store. Using Context Store Geo redundancy, you can have two Context Store clusters in active/active mode. These Context Store clusters can be either in the same data center or in two different data centers. To ensure a successful failover, you must add the two Context Store clusters to the same System Manager.

Context Store supports Geo redundancy with two Data centers only.

To enable Context Store Geo redundancy, you must:

- Configure the Context Store Geo attributes: You can access the Context Store Geo attributes on the same page as the CSManager attributes. Because Geo attributes are cluster specific, you must configure the attributes after the cluster is created and CSManager is installed. For Context Store to operate in a geo redundant manner, you must reboot the cluster after configuring the Geo attributes.
- Use a load balancer: You must provide and configure a highly available load balancer for the two Context Store clusters. The load balancer must provide:
 - A common address: Both the Context Store clusters must be reachable through a common address. For the third party applications that you integrate with Context Store, use this common address to access the clusters. You must use only the common address, and not the individual cluster IP address, to access the Context Store clusters.
 - Load balancing: The load can be distributed between the clusters as per your requirements, however, the traffic must be routed on the *rid parameter*, the routingId field of a context object. You cannot route requests using round robin, least busy server, or any other mechanism other than routing on the rid parameter.

For routing the requests and distributing the traffic between the clusters, Context Store uses an optional field, *rid parameter*, in each REST request. If you do not specify a value for the rid parameter, the load balancer routes the request to the default Context Store cluster. Due to the replication of the same context entry in the two clusters, Context Store uses a combination of the rid parameter and the contextId to uniquely identify a context entry.

The two geographically redundant Context Store clusters support the same traffic as one non geo redundant Context Store cluster supports.

Avaya Engagement Designer does not support the geo redundancy feature, rid parameter, of Context Store.

For more information about load balancer for a geo-redundant deployment and a reference configuration, see *Avaya Context Store Snap-in Developer Guide*.

Third party load balancer configuration requirement

For a third-party load balancer to route traffic correctly between two or more Context Store clusters, the following mandatory steps must be configured on the load balancer:

• Ensure that the traffic is routed on the rid parameter.

Each request for a particular context must be routed to the same Context Store cluster. To achieve this, Context Store uses an optional field, *rid parameter*, in each REST request. For example, all requests with rid parameter=1 must be directed to the nondefault cluster and any other requests must be sent to the default cluster. Requests for the same context must go to the same Context Store cluster as the time lag for replication between the two Context Store clusters is not instantaneous. You cannot route requests using round robin, least busy server, or any other mechanism other than routing on the rid parameter. You must ensure that each request for a particular context has the same rid parameter.

- If the load balancer receives responses with any of the following codes: 500, 502, 503, and 504, the load balancer must mark the Context Store cluster as down and redirect all subsequent requests to the other Context Store cluster. The 500 code signifies that only one of the Avaya Breeze[™] nodes in the Context Store cluster is operational and it cannot process requests.
- The load balancer must be able to forward the Context Store https requests. If the load balancer requires authentication, load the certificates in the load balancer. For more information about certificates, see <u>Certificate-based authentication</u> on page 99.

Related links

Failover scenarios on page 90

Failover scenarios

The following section displays the failover scenarios in geo redundancy:

• When a Context Store cluster is down, requests that are routed to the cluster will be redirected to the other cluster. This might result in GET requests going to a cluster which

does not contain that context. For example, the request will fail in the following sequence of events:


- 1. Context A is saved to cluster 1.
- 2. Cluster 1 goes down before context A has been replicated to cluster 1.
- 3. The load balancer attempts to route the GET request for context A to cluster 2.
- When a cluster is shut down and restarted, existing data on the active cluster is not replicated to the other cluster. For example, the following data is not replicated:
 - 1. Shut down cluster 1.
 - 2. Create new contexts on cluster 2 and update existing contexts on cluster 2.
 - 3. Restart cluster 1
 - 4. Only the newly created contexts on cluster 2 are replicated to cluster 1.

Related links

Third party load balancer configuration requirement on page 90

Architecture

The following diagram depicts the architecture of a Context Store geo redundant deployment:



Two Context Store clusters are deployed at two different data centers. All requests to Context Store are routed through a third party load balancer that is common between the two Context Store clusters. The load balancer can communicate with both the clusters at any time. The clusters are connected through WAN. The load balancer can reside on either data center.

Service preservation

Context Store geo redundancy provides service preservation through load balancing of requests across the two Context Store clusters, with both the clusters in active state simultaneously. These Context Store clusters can be in two separate LANs, connected by a WAN link. However, because the replication of data between the two Context Store clusters is not instantaneous, you must route all requests for a specific context to the same cluster.


If you enable the option *Cluster Deny Service on 2 node outage* from the CSManager attributes, the third Avaya Breeze[™] server in a Context Store cluster stops processing requests when the other two servers stop working. The third server then returns 500's as the status code, and the load balancer routes the traffic to the other cluster.

Session preservation

Context Store geo redundancy incorporates bi-directional replication of state and data across the two Context Store clusters to ensure preservation of session, in case of a cluster failure. The bidirectional replication strategy stores backup of all contexts in each Context Store cluster, so that if a cluster or a datacenter is unavailable, you can continue working with the backed up context.

Notifications in Context Store Geo


In a geo redundant architecture, Context Store uses the same notification subscription details on each cluster, so that you receive notifications from any of the two clusters. If the Context Store cluster to which you have sent your request is unavailable, Context Store reroutes your request to the other available cluster. The cluster then processes your request and generates the notifications. The following diagram depicts the working of CSNotifications in a Context Store geo redundant architecture.




Failover support

In a Context Store geo redundant setup, the load balancer detects that a cluster is unavailable, the load balancer routes the incoming requests to the available cluster. The geo redundant architecture supports the following failover scenarios:

• Both servers are unavailable: If the two Avaya Breeze[™] servers in a Context Store cluster are unavailable, the cluster IP address is also unavailable. The geo redundant load balancer detects the failure and routes all requests to the remaining active cluster.



• Either of the Avaya Breeze[™] servers and the other server of a Context Store cluster is unavailable, the remaining server detects the failure and returns a status code of 500. Upon receiving the failure information from the remaining server, the load balancer routes all requests to the other cluster in the geo redundant system.



• All three servers are unavailable: If all three Avaya Breeze[™] servers in a Context Store cluster are unavailable, the geo redundant load balancer routes all requests to the remaining Context Store cluster in the geo redundant system.

For the reference implementation, the nginx running on the Geo cluster will automatically detect if a Context Store cluster is back in service. There are no manual steps required for the Load Balancer to reintroduce a Context Store cluster back into receiving requests.

Chapter 8: Performance

Capacity and scalability specification

This topic provides the capacity specification for the Avaya certified deployment scenarios. Avaya has used these values as a benchmark for capacity verification.

Key considerations:

- The standard storage capacity of a context is 2 KB in raw JSON data. Note that the object might be significantly larger when stored in the data grid depending on the complexity of the object. When you enable optional features, which require memory resources, the size of the Context objects, lease time, or throughput must be decreased to achieve the certified performance. Also, when you use the aliasld feature, the 2 KB standard context must be reduced to 1.5 KB to achieve the certified performance level, in terms of throughput and lease time. Enabling the Audit feature also has an impact on Context Store capacity. You must reduce the context size based on the number of audit entries enabled. For more information, see Avaya Context Store Snap-in Developer Guide.
- The average latency of a request in an hour is less than 250 milliseconds with a maximum latency of two seconds regardless of the deployment size. Latency is the time interval between the client request and the Context Store response, in milliseconds.
- Context Store supports a maximum of three aliasIds.
- For production environments which require the Geo redundancy feature, each cluster must contain two or more Avaya Breeze[™] nodes with 16 GB of memory and 8 cores allocated to each node.
- If you want to enable the Event streams feature, you require 6 GB memory on the Avaya Breeze[™] cluster.
- For production deployments that are not certified with five notifications, if you increase the number of notification clients to five, the request per second capacity will be reduced to half.



For Release 3.2 of Context Store, performance is tested with only one notification client.

For the capacity certified for each Avaya certified deployments, see the *Certified Deployments* section in Avaya Context Store Snap-in Release Notes.

Chapter 9: Security

Overview

Context Store uses Avaya Breeze[™] to provide all security configurations for access to its services. Avaya Breeze[™] provides configuration for HTTPS, Mutual TLS (Client Certificate Challenge), Cross Origin Resource Sharing (CORS), Whitelists, and Trust Certificates. In addition, System Manager provides a flexible platform for administering certificates and authorities.

😵 Note:

When enabling the Geo Redundancy feature or using the CS Pluggable Data Connector for Orchestration Designer or a secured client of CSScreenPop, the CS SDK, or the CSNotifications service, additional security steps (certificates and/or licenses) are required. See individual feature sections for detailed information about required configuration. There are several options available when configuring certificates using System Manager; to help getting started, one particular approach is documented in the *Appendix section of Avaya Context Store Snap-in Developer Guide*.

For more information about security configuration, see Avaya Breeze[™]Overview and Specification and Avaya Aura[®] System Manager Overview and Specification.

Secure space

With Context Store Secure space, you can secure the data grid with your own unique password. The unique password prevents unauthorized access of the grid by tools. The secure user for the grid is dcmuser. After security is enabled, the username dcmuser and the password that you set in the **Cluster Attributes** page are applied to the data grid.

You can configure Space security when the cluster is being created or by editing the cluster configuration after the cluster is created.

🛕 Warning:

When you enable security after creating the cluster, the system deletes the existing unsecured data grid and all data that the grid contains automatically and the data grid is redeployed in secure mode.

Configuring space security

Procedure

- 1. On the System Manager web console, go to **Elements > Avaya Breeze > Cluster** Administration.
- 2. If you are creating a new secure cluster, click **New** on the **Cluster Administration** page.
- 3. If you are securing an existing cluster:
 - a. Select the check box of the cluster that you want to secure and select the **Deny New Service** option from the **Cluster State** drop-down menu.
 - b. On the Warning box, click **Continue**.

The system changes the state of the cluster to Denying.

- c. Click Edit.
- d. Go to Cluster Attributes > Cluster Editor > General tab.
- e. Enter the password that you want to use in the Grid password text box.
- f. Select the Use secure grid? check box.
- g. Click Commit.

The system prompts you to ensure that all Avaya Breeze[™] server restarts are complete before placing the cluster into the **Accept New Service** state.

- h. Click OK.
- i. Select the check box of the new/modified cluster.
- j. From the Cluster State drop-down menu, select Accept New Service.
- k. Click Continue in the Accept New Service dialog box.

The system displays the Accepting state in the Servers State column.

Certificate-based authentication

For the Context Store certificate-based authentication, you must perform the following procedures in the System Manager web portal:

- Configure the client certificate challenge in Avaya Breeze[™] Element Manager. The configuration is available on the **Avaya Breeze** > **Configuration** > **HTTP Security** page.
- Create a client key store.
- Download the Avaya Breeze[™] trusted certificate from System Manager.
- Authenticate browsers.

Ensure that client applications that access Context Store operations provide the location and credentials of the client certificate and trusted certificate to establish a secure session with the Context Store cluster.

For information about Avaya Breeze[™] certificate-based authentication, see the *Security* chapter in *Avaya Breeze[™] Overview and Specification*. For information about Avaya Aura[®] System Manager certificate-based authentication, see the *Security Enhancement* section in *Avaya Aura[®] System Manager Overview and Specification*.

Cross Origin Resource Sharing

Cross Origin Resource Sharing (CORS) enables access to Context Store requests that originate from other domains.

The configuration is available on the **Avaya Breeze** > **Configuration** > **HTTP Security** page.

😵 Note:

When you enable the client certificate challenge , web clients cannot authenticate through Javascript, that is, Ajax calls. As the browser and the Javascript layer are not connected, the required client certificate is not sent.

Port utilization

For Context Store port information, see the Avaya Breeze[™] 3.2 Port Matrix document at <u>https://</u><u>support.avaya.com/security</u>.

Chapter 10: Troubleshooting

Troubleshooting overview

This chapter provides information about the alarms and events that Avaya Context Store Snap-in generates. It also lists the Context Store log files. For information on troubleshooting issues related to Avaya Breeze[™], see the *Maintaining and Troubleshooting Avaya Breeze[™]* guide.

Alarms

Overview

Context Store generates alarms whenever an error occurs.

You can view, search, export, and configure alarms from the System Manager web portal. The alarms information is available in the **Services** > **Events** > **Alarms** page in System Manager.

Prerequisites

Using System Manager, you must create a simple network management protocol (SNMP) target profile and assign the profile to your network managing system (NMS).

For more information about creating and managing SNMP target profiles, see *Administering Avaya Aura*[®] *System Manager* available at <u>http://support.avaya.com</u>.

Alarm status

Context Store alarm statuses are consistent with those of the other snap-ins deployed on Avaya Breeze[™]. These alarms can have any of the following two statuses:

Status	Description
Raised	An alarm has been generated. Software recovery actions have failed to correct the problem.
Cleared	The problem has been fixed and the alarm has been cleared. This state must be set manually.

Context Store generates two alarm IDs for the same alarm- one when raising the alarm and the other when clearing the alarm. The alarm ID that Context Store generates for clearing an alarm contains *CLR* as a prefix in the original alarm ID that was in *Raised* state.

Alarm severities

Avaya Context Store Snap-in generates alarms with two severity types, as described in the following table:

Severity	Description
Major	All the Context Store alarms in Raised state are of Major severity.
Normal	Context Store generates a clear alarm with Normal severity.

For more information on alarm statuses and severities, see *Maintaining and Troubleshooting Avaya Aura[®] Avaya Breeze*[™].

ContextStoreManager_CS_EVT_1

Event ID ContextStoreManager CS EVT 1

Default event text Cluster requests per second is greater than the High configured threshold.

Event level Major

Trigger component ContextStoreRest: Processing number of requests

Problem description

The REST requests per second is greater than or equal to the configured high threshold for the service or the cluster.

The alarm is cleared automatically when the service request per second is lower than the value in the Context Store attribute **CS Threshold: Service Low Requests per Second**.

😵 Note:

You can configure the high threshold value by updating the ContextStoreManager attribute **CS** *Threshold: Service High Requests per Second*. The value is 1240.

Proposed solution

Procedure

Contact the support engineer to ensure that the traffic load is minimized.

CSManager_CS_EVT_2

Event ID	CSManager	CS	EVT	2
----------	-----------	----	-----	---

Default event text Cluster lacks enough CSRest instances to support the maximum requests/second load.

Event level Major

Trigger component CSREST: Number of live instances in a cluster

Problem description

Multiple instances of CSRest have failed and Context Store cannot support the service high availability requests for every second.

The system clears the alarm when the number of deployed CSRest interfaces is equal to or more than 2.

Proposed solution

Procedure

- 1. Ensure that all the Avaya Breeze[™] nodes in the cluster are running.
- 2. Ensure that all Avaya Breeze[™] nodes have network connection access.
- 3. Ensure that all Avaya Breeze[™] nodes have CSRest snap-in deployed.
- 4. Ensure that the Avaya Breeze[™] cluster has CSManager snap-in deployed.

ContextStoreManager_CS_EVT_3

Event ID ContextStoreManager CS EVT 3

Default event text Cluster lacks enough ContextStoreRest instances to support the maximum requests/second load and be highly available.

Event level Major

Trigger component ContextStoreRest: Number of live instances in a cluster

Problem description

The system cannot support the service high threshold requests per second in the event of another instance failure.

The alarm is cleared when number of REST instances in the cluster is equal to or more than 3.

Proposed solution

Procedure

- 1. Ensure that all Avaya Breeze[™] nodes in the cluster are running.
- 2. Ensure that all the Avaya Breeze[™] nodes have network connection access.
- 3. Ensure that all Avaya Breeze[™] nodes have CSRest snap-ins deployed.
- 4. Ensure that the Avaya Breeze[™] cluster have CSManager snap-in deployed.

CSManager_CS_EVT_4

Trigger component	CSManager: EDM deployment
Event level	Major
Default event text	Failed to persist item to external data mart.
Event ID	CSManager_CS_EVT_4

Problem description

System cannot persist information from datagrid to External Data Mart. This error occurs if Context Store cannot perform any of the following:

- · Connect to the database configured for External Data Mart.
- Validate schema or data of the database configured for External Data Mart.

The alarm is cleared when the connection with database is restored with External Data Mart.

Proposed solution

Procedure

- 1. Ensure that Context Store is able to connect to the external database.
- 2. Ensure that the values that you have specified for the External Data Mart attributes in the CSManager attributes page are correct. If the values are incorrect:
 - a. Update the values.
 - b. Redeploy CSManager and CSRest.
- 3. Ensure that the database schema is as per the Context Store requirements. If the database schema is incorrect:
 - a. Update the database schema.
 - b. Redeploy CSManager and CSRest.

CSManager_CS_EVT_5

Event ID	CSManager_CS_EV	r_5				
Default event text	CSNotifications Details.	Subscription	Disabled	see	log	for

Event level Major

Trigger component CSNotifications

Problem description

This alarm is raised when there is a failure to connect to an endpoint and the subscription of that endpoint is disabled automatically.

Proposed solution

Procedure

- 1. Check logviewer on System Manager to identify details about the subscription that is disabled.
- 2. Verify the validity of the endpoint and enable the subscription.

Events

Overview

Context Store generates events for warning purpose only.

You can view the events in Log viewer at the following directory: Home/Services/Events/Logs/Log Viewer.

CS_AUDIT_5

Event ID CS_AUDIT_5

Default event text Instance requests per second is greater than the configured threshold.

Event level Warning

Problem description

Context Store creates the CS_AUDIT_5 event log in System Manager when Context Store operates at the maximum capacity. The system operates at maximum capacity when the request per second is greater than or equal to the value of the CSManager attribute CS Threshold: Instance High Requests per Second.

Proposed solution

Procedure

Contact the support engineer to ensure that the traffic load is minimized.

CS_AUDIT_7

Event ID CS_AUDIT_7

Default event text Instance latency is greater than the configured threshold.

Event level Warning

Problem description

Context Store creates the CS_AUDIT_7 event log in System Manager when the average time for the context data to travel between the client and Context Store exceeds the value that you have specified for the CSManager attribute *CS Threshold: High Latency*.

Proposed solution

Procedure

- 1. Ensure that all Avaya Breeze[™] nodes in the cluster are running.
- 2. Ensure that all Avaya Breeze[™] nodes have network access.
- 3. Ensure that all Avaya Breeze[™] nodes have CSRest snap-in deployed.
- 4. Ensure that all Avaya Breeze[™] clusters have CSManager snap-in deployed.
- 5. Verify that the context size of the requests is as per the Context Store requirement.

CS_AUDIT_8

Event ID CS_AUDIT_8

Default event text Instance error rate is greater than the configured threshold.

Event level Warning

Problem description

Context Store creates the CS_AUDIT_8 event log in System Manager when the rate of the failed requests returned to the client from Context Store exceeds the threshold value that you have specified in the CSManager attribute *CS Threshold: High Error Rate.*

Proposed solution

Procedure

- 1. Ensure that all Avaya Breeze[™] nodes in the cluster are running.
- 2. Ensure that all Avaya Breeze[™] nodes have network access.

- 3. Ensure that all Avaya Breeze[™] nodes have CSRest snap-in deployed.
- 4. Verify that all Avaya Breeze[™] clusters have CSManager snap-in deployed.
- 5. Ensure that the traffic load does not exceed the high threshold request per second.

CS_AUDIT_10

Event ID CS_AUDIT_10

Default event text Cluster average lease time is greater than the configured threshold.

Event level Warning

Problem description

Context Store creates the CS_AUDIT_10 event log in System Manager when the average lease time for data stored by Context Store exceeds the threshold value.

Proposed solution

Procedure

No corrective action is required.

CS_AUDIT_11

Event ID CS_AUDIT_11

Default event text Cluster requests per second is greater than the configured Low threshold.

Event level Information

Problem description

Context Store creates the CS_AUDIT_11 event log when cluster requests per seconds is greater than the configured low threshold value.

CS_AUDIT_13

Event ID CS AUDIT 13

Default event text Instance requests per second is greater than the configured Low threshold.

Event level Warning

Problem description

Context Store creates the CS_AUDIT_13 event log in System Manager when the instance requests per second is greater than the configured Low threshold.

Proposed solution

Procedure

- 1. Ensure that all the Avaya Breeze[™] nodes in the cluster are in the running state.
- 2. Ensure that all the Avaya Breeze[™] nodes have network access.
- 3. Ensure that all Avaya Breeze[™] nodes have the CSRest snap-in deployed.
- 4. Ensure that all Avaya Breeze[™] clusters have CSManager snap-in deployed.

Logging

Context Store log files

The following table describes the log name and location of the logs related to Context Store:

Log name	Location	Description
Context Store <service> logs</service>	/var/log/Avaya/services/ <servicename>/ <servicename>.log</servicename></servicename>	Logs related to Context Store services, such as CSManager, CSRest, and so on.
External Data Mart logs	/var/log/Avaya/dcm/pu/CSManager/CSManager-cs- edm-3.2.0.0.xxx_ <x>.log</x>	Logs related to the External Data Mart feature.
ASM logs	/var/log/Avaya/sm/asm.log	Logs related to Avaya Breeze for platform APIs and features used by Snap-ins.
Text logs	/var/log/Avaya/sm/TextLog_date_time.log	Provides information on problems that might be blocking services.
Event logs	/var/log/Avaya/services/event.log	Alarms and events raised by Context Store snap- ins.
Data grid logs	/var/log/Avaya/dcm/	Data grid log file location.

Log level configuration

You can adjust the logging level of all snap-in services individually from **Home > Elements > Avaya Breeze > Configuration > Logging**.

Log file configuration

As with the data grid size attributes in CSManager, the log file sizes are configured for the default Context Store deployment (certified deployment id 9: cluster of three nodes with 64GB of memory, 8 vCPUs, and 300GB hard disk each).

The Context Store service log files are configured to store up to 200 log files of maximum 100MB each.

This size and number of log files stored, is configurable for each individual Context Store service in the /opt/Avaya/Common/conf/log4j.properties file:

- log4j.appender.<service-name>.MaxFileSize=100MB
- log4j.appender.<service-name>.MaxBackupIndex=200

Frequently asked questions

Where do I find documentation for Context Store?

Context Store documents are available at the Avaya support portal: <u>https://support.avaya.com/</u><u>documents</u>.

For each major release of Context Store there are three documents published:

- · Avaya Context Store Snap-in Release Notes
 - Describes new features and feature modifications in the release.
 - Describes prerequisites for installation and upgrade procedures and provides the PLDS ID and MD5 checksum for every available component.
 - Lists known issues that exist in the present release as well as issues which have been resolved in this release since the previous release.
 - Contains the attribute configurations for all certified Context Store deployments.
- Avaya Context Store Snap-in Reference
 - Contains overview information about Context Store and its features.
 - Contains detailed instructions for the deployment and configuration of Context Store.
 - Discusses high availability, performance and security aspects of Context Store.
 - Contains some troubleshooting information
- Avaya Context Store Snap-in Developer Guide
 - Contains detailed usage information for Context Store features and interfaces.

- Contains tutorial sections for certain features.
- Provides complete API references for all interfaces to Context Store (CSRest).

Where do I get plugins, SDKs, and sample resources for Context Store?

Sample resources, plugins, and SDKs for Context Store can be downloaded from the Avaya DevConnect portal:<u>https://www.devconnectprogram.com/site/global/products_resources/avaya_breeze/avaya_snap_ins/context_store/overview/index.gsp</u>

In the Releases > Downloads section you will find:

- Links to download the documents applicable to the release (Release Notes, Reference Guide and Developer Guide)
- Context Store components which are not distributed as Avaya Breeze[™] snap-in services
 - Context Store Java SDK
 - Context Store Pluggable Data Connector for Orchestration Designer / Avaya Aura Experience Portal
- The Capacity Planner Tool for estimating sizes when designing a CS deployment
- · Sample client applications
 - Event Streams sample application
 - CSNotifications sample consumer
 - Sample workflows for Avaya Engagement Designer
 - Sample workflows for Orchestration Designer / Avaya Aura® Experience Portal
- Sample implementations
 - Example of Audit Trail user interface application
 - Example of ScreenPop application which sorts the returned data

How do I verify if Context Store is successfully deployed?

The most reliable way to verify deployment is to create and retrieve test Contexts through the CSRest interface. You can submit requests to the Cluster IP address (which will round-robin request to each available CSRest instance) or directly to the security module IP address of a server to verify that each is working as expected.

Helpful hint: If you create contexts without specified contextIds with the shortid=true parameter (http://clusterIP/services/CSRest/cs/contexts/?shortid=true), the first 1-3 digits of the returned, auto-generated contextId match the last octet of the security module IP address of the server on which the context was created. So with just a few simple create requests to the cluster IP address, you can verify that each of the servers is processing requests and therefore CSRest is functioning correctly.

Submit test requests using either a ReST client such as Postman (for Google Chrome) or the live API built-in to CSRest itself (http://clusterIP/services/CSRest/)

Note:

Sample Postman request collections are available to download from the Context Store DevConnect for all CSRest operations and features.

How do I determine the appropriate size for my Context Store deployment?

The appropriate size for a Context Store deployment is based on the following variables:

- · The average size of context objects created
- · The average lease time of the created context objects
- · The rate at which new context objects are being created
- The inclusion of additional Context Store features, such as External Data Mart, georedundancy, high availability, Context Store Event Streams, Audit Trail, and aliasIds, which themselves have memory requirements.

The Context Store Release Notes, available on Avaya Support site, contains the CSManager attribute configurations for 13 certified deployments of varying sizes; from a single-node with 8 GB of memory up to a cluster of three nodes with 128 GB of memory each.

You can also download a Capacity Planner Tool that assists you with custom sizing, from <u>http://</u><u>www.avaya.com/devconnect</u>. This tool accepts inputs for the four variables and provides the bestestimate recommendations

Related links

How do I determine the appropriate size for my External Data Mart deployment? on page 112

How do I verify if Context Store is successfully connected to the External Data Mart?

If you have access to the database itself, the simplest way to verify is:

- 1. Create a context with the persistToEDM flag set to true =>
 {"contextId":"PersistedContext","persistToEDM":"true","data":
 {"key1_name":"value1_data"}
- 2. Run an SQL query to search the database for this context => select * from cs operation where context id = 'PersistedContext'

If you cannot query the database directly, you can use CSQuery ReST interface to verify that the context has been written to the External Data Mart => http://clusterIP/services/ CSQuery/edm/contexts/audit/{{contextId}}/?data=true

How do I determine the appropriate size for my External Data Mart deployment?

There is not "one size fits all" answer for External Data Mart (EDM) size. The appropriate size for the EDM is directly linked to the sizing variables listed in "How do I determine the appropriate size for my Context Store deployment?"

You must also consider questions such as, how long the context data will remain in the EDM and will the data be truncated after a certain period of time.

Though the exact details might vary from vendor to vendor, the following table is a rough guide to the amount of disk space consumed by the EDM attached to a system running at high capacity with a large percentage of create and update operations.

Average context size (KB)	Requests per second	GB per hour written to EDM
2	1240	8.35
16	1000	55
32	800	88
64	500	110

Calculating specific quantities when the Audit Trail feature is enabled (required for Customer Journey) is a bit different as it depends entirely on the length of the audit trail stored for each context. The audit trail is the number of interactions with that context during its life span. It also depends on the amount of additional information being stored within the context object.

In an Avaya Oceana[™] Solution deployment, you must include the required Avaya Oceana[™] Solution service data and the additional customer created data in estimations.

For example, based on analysis of some sample data from an Avaya Oceana[™] Solution lab for a voice and chat contact, the minimum context required for Avaya Oceana[™] Solution (and assuming three elements created in the Customer Journey), the storage per contact is ~3 KB

Related links

How do I determine the appropriate size for my Context Store deployment? on page 111

How do I submit requests to CSRest interface if access through external ReST client is blocked?

If customer's network blocks access for ReST clients such as Postman (for Google Chrome) or the live API built-in to CSRest itself (http://clusterIP/services/CSRest/) you can submit CURL requests from command line on a machine which has tunnel/proxy access to the environment.

Create a context:

```
curl -H "Content-Type: application/json" -X POST -d
'{"contextId":"DemoContext1","groupId":"demo","data":
{"key1_name":"value1_data","key2_name":"value2_data","key3_name":"value3
_data"}}'http://clusterIP/services/CSRest/cs/contexts/
```

Retrieve a context:

curl http://clusterIP/services/CSRest/cs/contexts/DemoContext1/

Problems with data grid deployment

If the resources available in the cluster of Avaya Breeze[™] servers is not sufficient for the configured deployment (data grid size plus optional features selected), the deployment fails. For attribute values for each certified deployment, see Avaya Context Store Snap-in Release Notes.

If deployment issues occur, check your configuration settings are correct, check the /var/log/ Avaya/services/CSManager and /var/log/Avaya/dcm/gs-esm-<X> logfiles for errors related to deployment.

The following errors indicate there has been a data-grid deployment failure:

- Instead of the CSManager status page located at: http://<IP_ADDRESS>/services/ CSManager/, the following error is displayed: Error 503: Internal error Could not read statistics object, check CSSpace settings. EDM PU deployment failed, check EDM settings, or try accessing the homepage via load balancer IP or other node GEO PU deployment failed, review GEO settings, or try accessing the homepage via load balancer IP or other node.
- A 404 not found response is returned for non-read request. For example, Error 404: javax.servlet.UnavailableException: Space ContextStoreManagerSpace could not be found in 60000 milliseconds to create a listener.
- The following error is displayed: Number of retries (100) to create proxy to grid has been exhausted, machine restart required.

Note:

It is imperative that nodes are shut down at the same time to ensure that the data-grid is fully undeployed before the next deployment attempt takes place. The last node standing will keep the data-grid alive. So when nodes have already started back up before that last-man-standing shuts down, the data grid does not get redeployed. This necessity is stated in the documentation, this is what we mean by "simultaneous restart".

- After a correct fresh start of the cluster, you will see these lines in the CSManager log file (on whichever node has taken charge of the deployment. Whoever got there first)
 - grid.EsmGrid INFO [M eployElasticSpace][T:null]. ContextStoreManagerSpace not found, deploying...
 - grid.EsmGrid INFO [M eployElasticPU][T:null]. ContextStoreSpace not found, deploying...
 - grid.EsmGrid INFO [M:deployStateless][T:null]. EDM-Mirror-Service is deployed with status BROKEN.
 - Followed quickly by manager.AbstractPUManager INFO -[M:checkDeploymentStatus][T:null]. [EDM-Mirror-Service] is in status [INTACT] a few seconds later

- If these deploying messages do not appear on any CSManager logs since restart and instead you get already deployed messages, you have not restarted the cluster correctly.
 - grid.EsmGrid INFO [M eployElasticSpace][T:null]. space with name ContextStoreManagerSpace is already deployed.
 - grid.EsmGrid ERROR [M:deployElasticPU][T:null]. space ContextStoreSpace is already deployed.

How do I verify if connection between geo-redundant clusters is successfully established?

The easiest way to verify connection between the clusters is to create a context in one cluster and then retrieve it from the other cluster.

- 1. Create a context on Cluster A.
- 2. Retrieve the context from Cluster A (to verify it was created successfully)
- 3. Retrieve the context from Cluster B (to verify it was replicated to the other cluster successfully)
- 4. Create a context on Cluster B (to verify replication is working in both directions).
- 5. Retrieve the context from Cluster B.
- 6. Retrieve the context from Cluster A.

Additionally, you can identify the Grid Services Container (GSC) in each cluster which is hosting the Gateway service used for geo redundancy replication by searching for the term "GEO-Gateway-Service". In that file (in each cluster) you can then easily find the state changes for the Gateway link between the two clusters: Connection delegator: moved to state: *CONNECTED/ DISCONNECTED*.

Why is the CSRest interface returning 503 Service Temporarily Unavailable for all my requests?

The 503 errors indicate that either the Avaya Breeze[™] servers or the cluster which hosts Context Store is in **Denying** state.

On the main Cluster Administration page, select the check box beside the affected cluster and change the **Cluster State** to **Accept New Service**. If the state is already set as expected, try toggling the state to **Deny New Service** and then set it back to **Accept New Service**.

Why can't I set the state of my cluster to Accept New Service?

If it is not possible to activate the cluster, check the license status of the Avaya Breeze[™] servers in the cluster.

On the main Cluster Administration page, check that the License Mode column for each Avaya Breeze[™] server used in the affected cluster shows a green check-mark. This means that the license is valid.

What is the maximum lease time permitted for a context?

There is effectively no limit on context lease but it is vital to take lease time into consideration when sizing a Context Store deployment as this can drastically change the amount RAM required in the cluster to store the context data for such a long time.

The default lease time is 2 hours (7200 seconds) and the maximum lease time threshold (above which a warning will be logged but request will not be blocked) is 4 hours (14400 seconds).

Both of these figures can be set anywhere within the range specified in the Context Store documentation. As per the description of lease parameter in the Avaya Context Store Developer Guide, "The valid lease must be in the range 1 to 2147483647." (2147483647 is the maximum value permitted for an integer field such as this.)

In the Capacity Planner tool, configuration sizing options are offered for up to 90 hours or days (though if you're storing data for 90 days, what you need is a database and not Context Store!)

Why can't I access Context Store from a web client?

Due to JavaScript's same-origin policy, requests from a script stored on a server can only send requests back to that server. When blocked, the JavaScript XMLHttpRequest status = 0

To allow a script to send requests to and receive responses from Context Store, you must enable the Allow Cross-origin Resource Sharing for all setting on Home > Elements > Avaya Breeze > Configuration > HTTP Security > HTTP CORS

CORS must be enabled when using any web client such as the Streams client, the Customer Journey Visualization application (part of the CSQuery service) or website integration (using JavaScript SDK or integration with CSRest interface).

Why is Customer Journey unable to retrieve data?

- 1. Verify that Cross Origin Resource Sharing (CORS) has been enabled in System Manager through **Avaya Breeze** > **Configuration** > **HTTP Security**.
- 2. Check your External Data Mart configuration as per the attributes configuration provided in the *Why is the External Data Mart not working?* section.

Why is the External Data Mart not working?

The following checks need to be performed to troubleshoot an EDM connection issue to ensure the configuration is correct:

Verify the following System Manager attributes are set for CSManager:

Attribute name	Value	Sample value	Notes
EDM: Enable Persistence to database	True	True	This must be set to true to enable EDM
EDM: Space supports EDM database connection	True or False	True	You must set this attribute to True to enable EDM.
EDM: Database dialect	 PostgreSQL: org.hibernate.dial ect.PostgreSQLDial ect Oracle: org.hibernate.dial ect.Oracle10gDiale ct Microsoft SQL Server: org.hibernate.dial ect.SQLServerDiale ct 	org.hibernate.dia lect.PostgreSQLDi alect	You must enter the correct prefix, depending on the type of database.
EDM: Database URL	<pre>Prefix Prefix PostgreSQL: jdbc:postgresql:// <ip_address>:<port>/<database_name> Oracle: jdbc:oracle:thin:@ <ip_address>:<port>:<database_name> Microsoft SQL Server: jdbc:sqlserver:// <ip_address>:<port>;dat abaseName=<database_ name=""> </database_></port></ip_address></database_name></port></ip_address></database_name></port></ip_address></pre>	<pre>jdbc:postgresql: // 10.20.30.40:5432/ edm jdbc:oracle:thin: @10.20.30.40:1521 :edm jdbc:sqlserver:// 10.20.30.40:1433; databaseName=edm</pre>	The DB URL format varies depending on the type of database. Check the format carefully. Also, ensure the configured database name matches the actual name of the created database.
EDM: Username	<db_username></db_username>	edm_user	Verify in pgAdmin that the DB user has access to the CS_OPERATION table
EDM: Password	<db_user-password></db_user-password>	edmpassword	

Verify the following System Manager attributes are set for CSQuery:

Attribute name	Value	Sample value	Notes
EDM: Username	<db_username></db_username>	edm_user	This is the same value set in CSManager attributes
EDM: Password	<db_user-password></db_user-password>	edmpassword	This is the same value set in CSManager attributes

DB Viewer (if available)

Verify the database user specified in the attribute **EDM: Username** in System Manager has access to the CS_OPERATION table. Verify the database name specified matches the database name specified the **EDM: Database URL** attribute in System Manager

API Validation

Download and install the POSTMAN web client via Chrome. Download the Context Store Postman Request Collection on DevConnect. Import the ContextStore-EDM_Operations.json and ContextStore32-CSQuery_Operations.json into the POSTMAN client. Within EDM Operations Collection run "Create Persisted Context" (this runs via CSRest) and subsequently verify the context has been persisted to the database. Use the CS-Query Collection to check that the context can be retrieved via the CS-Query interface

MIcrosoft SQL Server DB User

If you are using Microsoft SQL Server:

- The db user configured for the EDM feature must have database ownership or the system administrator privileges for this connection to be successful.
- From the security profile of the database user, you must set the Context Store database as the default database for this user.

Chapter 11: Related resources

Documentation

Title	Use this document to understand:	Audience
Installing		
Deploying Avaya	The procedures on deploying the	System administrators
Breeze™	Avaya Breeze [™] services.	 Services and Support personnel
		Avaya Professional Services
		Implementation engineers
Avaya Breeze [™] Overview and Specification	Avaya Breeze [™] requirements.	Anyone who wants to have a high-level understanding of Avaya Breeze [™] features, functions, capacities, and limitations.
Deploying Avaya Aura®	The procedures for deploying the	Implementation Engineers
System Manager on VMware [®] in Virtualized	Avaya Aura [®] System Manager virtual application in Avaya Aura [®]	Field Technicians
Environment	Virtualized Environment.	Business Partners
		Solution Providers
		Customers
Maintaining		
Avaya Context Store	The known issues, patches, and	Avaya Professional Services
Snap-in Release Notes	workarounds specific toContext Store.	 Implementation engineers
Avaya Breeze [™] Port	Context Store port information.	Implementation Engineers
Matrix document		Field Technicians
		Business Partners
		Solution Providers
		Customers
Maintaining and Troubleshooting Avaya Breeze [™]	Avaya Breeze [™] alarm statuses and severities.	Anyone who needs information about maintaining and troubleshooting Avaya Breeze [™] .

See the following related documents at <u>http://support.avaya.com</u>.

Table continues...

Title	Use this document to understand:	Audience
Administering		
Avaya Context Store Snap-in Developer Guide	Developer information for all applicable Context Store features and how to write applications using the Context Store REST Interfaces.	 Business process analysts Developers Services and Support personnel Avaya Professional Services
Administering Avaya Breeze™	The procedures to administer and configure the Avaya Breeze [™] services.	System administratorsServices and Support personnel
Administering Avaya Aura [®] System Manager	The procedures to administer and configure System Manager.	System administratorsServices and Support personnel
Avaya Aura [®] Orchestration Designer Developer's Guide	How to write software using Orchestration Designer that interacts with Context Store.	Business process analystsDevelopers
Avaya Aura [®] System Manager Overview and Specification	Avaya Aura [®] System Manager certificate-based authentication.	Anyone who wants to have a high-level understanding of System Manager features, functions, capacities, and limitations.
Avaya Engagement Designer Developer's Guide	How to write software using Avaya Engagement Designer that interacts with Context Store. Detailed usage information for the Context Store Task Type for Engagement Designer is documented in the Avaya Context Store Snap-in Developer Guide.	Business process analystsDevelopers

Related links

Finding documents on the Avaya Support website on page 119

Finding documents on the Avaya Support website

About this task

Use this procedure to find product documentation on the Avaya Support website.

Procedure

- 1. Use a browser to navigate to the Avaya Support website at http://support.avaya.com/.
- 2. At the top of the screen, enter your username and password and click Login.
- 3. Put your cursor over **Support by Product**.
- 4. Click Documents.

- 5. In the **Enter your Product Here** search box, type the product name and then select the product from the drop-down list.
- 6. If there is more than one release, select the appropriate release number from the **Choose Release** drop-down list.
- 7. Use the **Content Type** filter on the left to select the type of document you are looking for, or click **Select All** to see a list of all available documents.

For example, if you are looking for user guides, select **User Guides** in the **Content Type** filter. Only documents in the selected category will appear in the list of documents.

8. Click Enter.

Related links

Documentation on page 118

Training

The following courses are available on the Avaya Learning website at <u>www.avaya-learning.com</u>. Enter the course code in the **Search** field, and click **Go** to search for the course.

Course code	Course title
2519W	Introducing Avaya Context Store Snap-in (Self- paced, On-demand)

Support

Go to the Avaya Support website at <u>http://support.avaya.com</u> for the most up-to-date documentation, product notices, and knowledge articles. You can also search for release notes, downloads, and resolutions to issues. Use the online service request system to create a service request. Chat with live agents to get answers to questions, or request an agent to connect you to a support team if an issue requires additional expertise.

Index

Numerics

503 Service Ten	nporarily Unavailable	e requests	 114

Α

acquire license <u>51</u> activate the cluster
Additional databases
JDBC driver
administer
grants to authorization client
alarms
event 1
event 2
event 3
event 4 <u>104</u>
event 5 <u>104</u>
overview
status
severities <u>101</u>
aliasId
appropriate size
context store deployment <u>111</u>
external data mart deployment
architecture
Avaya Breeze <u>14, 51</u>
Context Store <u>14</u> , <u>51</u>
attributes
cluster61
Attributes
CSRules
Audit trail
audit entry <u>39</u>
capacity planning
setting limit
authentication
authorize
clients
Avaya Breeze
Avaya Breeze cluster
scaling up
average latency
<u>91</u>

В

bi-directional data

С

call intercept snap-in description 15	
can't access Context Store	

can't access Context Store (continued)	
web client	
capacity5	
certified deployment	<u>53</u>
checklist	<u>54</u>
client	<u>26</u>
cluster	<u>59</u>
scaling out	<u>44</u>
cluster attributes	
cluster delete	
cluster state	
Accept New Service	114
component diagram	
configuration	
external datamart	30
configuration requirement	
configure	
attributes	
secure space	
connection issues	<u></u>
EDM	115
External Data Mart	
connector snap-ins	-
context	10
maximum lease time	115
context alias	
context and context store	
Context Store	12
JavaScript SDK	27
Context Store connection	<u>21</u>
External Data Mart	111
ContextStoreManager_CS_EVT_1	
ContextStoreManager_CS_EVT_1	
Context Store Query	<u>105</u>
audit trail	21
context store rules	<u>21</u>
CSRules	24
Context Store service	
	<u>04</u>
ContextStoreSpace Context Store Manager	10
snap-in	<u>19</u>
Context Store Task Type	<u>4 1</u> 70
import old workflows	
context time	
CPU usage	<u>97</u>
CRM	~
integration	
CS Geo notifications	
CSManager	
parameters	<u>77</u>
CSManager_CS_EVT_2	<u>102</u>
CSManager_CS_EVT_4	
CSManager_CS_EVT_5	<u>104</u>

CSQuery parameters
CSQuery snap-in
customer journey visualization
CSRest
parameters
CSRest interface returning 503 Service Temporarily
Unavailable requests
CSRules
attributes
CSScreenPop
parameters84
cssoap snap-in
geo redundancy <u>20</u>
CSSoapt
parameters87
CS Task Tpe
non-OSGi workflows <u>72</u>
CS task type
deployment
CS task type <u>71</u>
overview
CS Task Type
install <u>72</u>
overview
customer journey
interactions <u>37</u>
unable to retrieve data <u>115</u>
view
customer journey visualization
audit trail
CS Query Snap-in

D

database JDBC driver 35 database planning 29 database prerequisites 29 database tables 30 databse 30
MSSQL
Oracle <u>35</u>
data grid <u>19, 27</u>
data model <u>13</u>
data replication
delete
delete a cluster
deleting service snap-ins $\overline{76}$
deployment
checklist
configuration53
configuration information $\frac{53}{53}$
design
diagram of components
documentation

documentation (continued)	
Context Store <u>109</u>	3
document changes	<u>9</u>

Е

EDM
provisioning
EDM connection issues
EDM provisioning enable <u>69</u> enable
enable <u>69</u> enable
enable
Enable
EDM provisioning
enabling CORS
event
CS_AUDIT_10 <u>107</u>
CS_AUDIT_11 <u>107</u>
CS_AUDIT_13 <u>107</u>
CS_AUDIT_5 <u>105</u>
CS_AUDIT_7 <u>106</u>
CS_AUDIT_8
events
overview
status
warning105
Event streams
events
event streams
Experience Portal
AEP
OD
Orchestration Desginer
external database
provision <u>34</u>
external datamart
external data mart <u>28</u>
External Data Mart
provisioning
External Data Mart connection issues <u>115</u>

F

failover	<u>90, 95</u>
scenarios	
finding Context Store	
documentation	<u>109</u>
plugins, SDK, and sample resources	<u>110</u>

G

geo	
geo redundancy	
enable	
geo redundant architecture	<u>91</u>

goal <u>12</u>

Н

НА	88 80
hardware	
high availability	

I

identity certificates install	
install license	
Integration	
CRM	24

J

Java	
JavaScript SDK	
client library	
JDBC providers	
field description <u>35</u>	

Κ

key value pair	
SDK	
UCID	

L

lease time legal notices	
license	
Load	
snap-in service	<u>58</u>
snap-in service svar file	
	<u>58</u>

Μ

mapping
maximum lease time
context
memory

Ν

navigate	
go back to original location	<u>11</u>
new	<u>17</u>
new features	<u>17, 38</u>
node	<u>43–45</u>

notices legal	
notification	
Notify	_
agents	<u>25</u>

0

overview	5
Context Store Manager73	
CSRest	
	1

Ρ

parameters	
CSManager	<u>77</u>
CSNotifications	<u>86</u>
CSQuery	<mark>87</mark>
CSRest	
CSScreenPop	84
CSSoap	
PDC	
deploy	<u>70</u>
plugins	<u>110</u>
plugins, SDK, and sample resources	
Context Store	<u>110</u>
ports	100
problems	
data grid deployment	<u>113</u>

R

related documentation	<u>118</u>
release	<u>17</u>
requirements	
REST interface	<u>19</u>

S

sample resources scalability scale up scaling out	<u>97</u>
Avaya Breeze cluster	44
scaling up	<u></u>
cluster	<u>46</u>
Screen Pop	
Screen Pop clients	<u>22</u>
SDK	
Secure space	
space security	<u>98</u>
security	<u>98, 100</u>
sensitive data	<u>13</u>
service HA	<u>92</u>
service preservation	<u>43</u> , <u>66</u>
services	
CSNotifications	<u>23</u>

services (continued)
snap ins
session HA <u>93</u>
skills <u>9</u>
snap in <u>18</u>
snap-ins
benefits <u>15</u>
defined <u>15</u>
soap interface
cssoap api
soap api
solution
solution overview <u>12</u>
space security
configure
status
submitting requests to CSRest interface
when external ReST client access is blocked
support
support failover
synchronized
Avaya Breeze servers57
servers
system manager
, , , , , , , , , , , , , , , , , , , ,

Т

<u>90</u>
. <u>13</u>
13
99
39
20
01
.15

U

unable to retrieve data	
customer journey	<u>115</u>
uninstall	
uninstallation	
uninstalling service snap-ins	
update	
database tables	<u>33</u>
updating	
non-OSGi flows	
old workflows	<u>73</u>
upgrade	<u>73</u>
Upgrade	
CS Task Type	
Context Store Task Type	72
Upsert method	
aliasid	40

Upsert method (continued)	
contextId	<u>40</u>
create	<u>40</u>
update	
versionId	

V

verification	65
verify deletion	
verifying	
connection between geo-redundant clusters	<u>114</u>
Context Store connection to External Data Mart	<u>111</u>
Context Store deployment	<u>110</u>
verifying connection between geo-redundant clusters .	<u>114</u>
view	
customer interactions	<u>37</u>
customer journey	<u>37</u>
virtual machines	<u>48</u>

W