

Deploying Avaya Breeze[™] on Kernel-based Virtual Machine

© 2017-2018, Avaya Inc. All Rights Reserved.

Notice

While reasonable efforts have been made to ensure that the information in this document is complete and accurate at the time of printing, Avaya assumes no liability for any errors. Avaya reserves the right to make changes and corrections to the information in this document without the obligation to notify any person or organization of such changes.

Documentation disclaimer

"Documentation" means information published in varying mediums which may include product information, operating instructions and performance specifications that are generally made available to users of products. Documentation does not include marketing materials. Avaya shall not be responsible for any modifications, additions, or deletions to the original published version of Documentation unless such modifications, additions, or deletions were performed by or on the express behalf of Avaya. End User agrees to indemnify and hold harmless Avaya, Avaya's agents, servants and employees against all claims, lawsuits, demands and judgments arising out of, or in connection with, subsequent modifications, additions or deletions to this documentation, to the extent made by End User.

Link disclaimer

Avaya is not responsible for the contents or reliability of any linked websites referenced within this site or Documentation provided by Avaya. Avaya is not responsible for the accuracy of any information, statement or content provided on these sites and does not necessarily endorse the products, services, or information described or offered within them. Avaya does not guarantee that these links will work all the time and has no control over the availability of the linked pages.

Warranty

Avaya provides a limited warranty on Avaya hardware and software. Refer to your sales agreement to establish the terms of the limited warranty. In addition, Avaya's standard warranty language, as well as information regarding support for this product while under warranty is available to Avaya customers and other parties through the Avaya Support website: https://support.avaya.com/helpcenter/getGenericDetails?detailld=C20091120112456651010 under the link "Warranty & Product Lifecycle" or such successor site as designated by Avaya. Please note that if You acquired the product(s) from an authorized Avaya Channel Partner outside of the United States and Canada, the warranty is provided to You by said Avaya Channel Partner and not by Avaya.

"Hosted Service" means an Avaya hosted service subscription that You acquire from either Avaya or an authorized Avaya Channel Partner (as applicable) and which is described further in Hosted SAS or other service description documentation regarding the applicable hosted service. If You purchase a Hosted Service subscription, the foregoing limited warranty may not apply but You may be entitled to support services in connection with the Hosted Service as described further in your service description documents for the applicable Hosted Service. Contact Avaya or Avaya Channel Partner (as applicable) for more information.

Hosted Service

THE FOLLOWING APPLIES ONLY IF YOU PURCHASE AN AVAYA HOSTED SERVICE SUBSCRIPTION FROM AVAYA OR AN AVAYA CHANNEL PARTNER (AS APPLICABLE), THE TERMS OF USE FOR HOSTED SERVICES ARE AVAILABLE ON THE AVAYA WEBSITE, HTTPS://SUPPORT.AVAYA.COM/LICENSEINFO UNDER THE LINK "Avaya Terms of Use for Hosted Services" OR SUCH SUCCESSOR SITE AS DESIGNATED BY AVAYA, AND ARE APPLICABLE TO ANYONE WHO ACCESSES OR USES THE HOSTED SERVICE. BY ACCESSING OR USING THE HOSTED SERVICE, OR AUTHORIZING OTHERS TO DO SO, YOU, ON BEHALF OF YOURSELF AND THE ENTITY FOR WHOM YOU ARE DOING SO (HEREINAFTER REFERRED TO INTERCHANGEABLY AS "YOU" AND "END USER"), AGREE TO THE TERMS OF USE. IF YOU ARE ACCEPTING THE TERMS OF USE ON BEHALF A COMPANY OR OTHER LEGAL ENTITY, YOU REPRESENT THAT YOU HAVE THE AUTHORITY TO BIND SUCH ENTITY TO THESE TERMS OF USE. IF YOU DO NOT HAVE SUCH AUTHORITY, OR IF YOU DO NOT WISH TO ACCEPT THESE TERMS OF USE, YOU MUST NOT ACCESS OR USE THE HOSTED SERVICE OR AUTHORIZE ANYONE TO ACCESS OR USE THE HOSTED SERVICE.

Licenses

THE SOFTWARE LICENSE TERMS AVAILABLE ON THE AVAYA WEBSITE, HTTPS://SUPPORT.AVAYA.COM/LICENSEINFO UNDER THE LINK "AVAYA SOFTWARE LICENSE TERMS (Avaya Products)" OR SUCH SUCCESSOR SITE AS DESIGNATED BY AVAYA, ARE APPLICABLE TO ANYONE WHO DOWNLOADS, USES AND/OR INSTALLS AVAYA SOFTWARE, PURCHASED FROM AVAYA INC., ANY AVAYA AFFILIATE, OR AN AVAYA CHANNEL PARTNER (AS APPLICABLE) UNDER A COMMERCIAL AGREEMENT WITH AVAYA OR AN AVAYA CHANNEL PARTNER. UNLESS OTHERWISE AGREED TO BY AVAYA IN WRITING AVAYA DOES NOT EXTEND THIS LICENSE IF THE SOFTWARE WAS OBTAINED FROM ANYONE OTHER THAN AVAYA, AN AVAYA AFFILIATE OR AN AVAYA CHANNEL PARTNER; AVAYA RESERVES THE RIGHT TO TAKE LEGAL ACTION AGAINST YOU AND ANYONE ELSE USING OR SELLING THE SOFTWARE WITHOUT A LICENSE. BY INSTALLING, DOWNLOADING OR USING THE SOFTWARE, OR AUTHORIZING OTHERS TO DO SO, YOU, ON BEHALF OF YOURSELF AND THE ENTITY FOR WHOM YOU ARE INSTALLING, DOWNLOADING OR USING THE SOFTWARE (HEREINAFTER REFERRED TO INTERCHANGEABLY AS "YOU" AND "END USER"), AGREE TO THESE TERMS AND CONDITIONS AND CREATE A BINDING CONTRACT BETWEEN YOU AND AVAYA INC. OR THE APPLICABLE AVAYA AFFILIATE ("AVAYA").

Avaya grants You a license within the scope of the license types described below, with the exception of Heritage Nortel Software, for which the scope of the license is detailed below. Where the order documentation does not expressly identify a license type, the applicable license will be a Designated System License as set forth below in the Designated System(s) License (DS) section as applicable. The applicable number of licenses and units of capacity for which the license is granted will be one (1), unless a different number of licenses or units of capacity is specified in the documentation or other materials available to You. "Software" means computer programs in object code, provided by Avaya or an Avaya Channel Partner, whether as stand-alone products, pre-installed on hardware products, and any upgrades, updates, patches, bug fixes, or modified versions thereto. "Designated Processor" means a single stand-alone computing device. "Server" means a set of Designated Processors that hosts (physically or virtually) a software application to be accessed by multiple users. "Instance" means a single copy of the Software executing at a particular time: (i) on one physical machine; or (ii) on one deployed software virtual machine ("VM") or similar deployment.

License types

Designated System(s) License (DS). End User may install and use each copy or an Instance of the Software only: 1) on a number of Designated Processors up to the number indicated in the order; or 2) up to the number of Instances of the Software as indicated in the order, Documentation, or as authorized by Avaya in writing. Avaya may require the Designated Processor(s) to be identified in the order by type, serial number, feature key, Instance, location or other specific designation, or to be provided by End User to Avaya through electronic means established by Avaya specifically for this purpose.

Heritage Nortel Software

"Heritage Nortel Software" means the software that was acquired by Avaya as part of its purchase of the Nortel Enterprise Solutions Business in December 2009. The Heritage Nortel Software is the software contained within the list of Heritage Nortel Products located at https://support.avaya.com/LicenseInfo under the link "Heritage Nortel Products" or such successor site as designated by Avaya. For Heritage Nortel Software, Avaya grants Customer a license to use Heritage Nortel Software provided hereunder solely to the extent of the authorized activation or authorized usage level, solely for the purpose specified in the Documentation, and solely as embedded in, for execution on, or for communication with Avaya equipment. Charges for Heritage Nortel Software may be based on extent of activation or use authorized as specified in an order or invoice.

Copyright

Except where expressly stated otherwise, no use should be made of materials on this site, the Documentation, Software, Hosted Service, or hardware provided by Avaya. All content on this site, the documentation, Hosted Service, and the product provided by Avaya including the selection, arrangement and design of the content is owned either by Avaya or its licensors and is protected by copyright and other intellectual property laws including the sui generis rights relating to the protection of databases. You may not modify, copy, reproduce, republish, upload, post, transmit or distribute in any way any content, in whole or in part, including any code and software unless expressly authorized by Avaya. Unauthorized reproduction, transmission, dissemination, storage, and or use without the express written consent of Avaya can be a criminal, as well as a civil offense under the applicable law.

Virtualization

The following applies if the product is deployed on a virtual machine. Each product has its own ordering code and license types. Note, unless otherwise stated, that each Instance of a product must be separately licensed and ordered. For example, if the end user customer or Avaya Channel Partner would like to install two Instances of the same type of products, then two products of that type must be ordered.

Third Party Components

"Third Party Components" mean certain software programs or portions thereof included in the Software or Hosted Service may contain software (including open source software) distributed under third party agreements ("Third Party Components"), which contain terms regarding the rights to use certain portions of the Software ("Third Party Terms"). As required, information regarding distributed Linux OS source code (for those products that have distributed Linux OS source code) and identifying the copyright holders of the Third Party Components and the Third Party Terms that apply is available in the products, Documentation or on Avaya's website at: https:// support.avaya.com/Copyright or such successor site as designated by Avaya. The open source software license terms provided as Third Party Terms are consistent with the license rights granted in these Software License Terms, and may contain additional rights benefiting You, such as modification and distribution of the open source software. The Third Party Terms shall take precedence over these Software License Terms, solely with respect to the applicable Third Party Components to the extent that these Software License Terms impose greater restrictions on You than the applicable Third Party

The following applies only if the H.264 (AVC) codec is distributed with the product. THIS PRODUCT IS LICENSED UNDER THE AVC PATENT PORTFOLIO LICENSE FOR THE PERSONAL USE OF A CONSUMER OR OTHER USES IN WHICH IT DOES NOT RECEIVE REMUNERATION TO (i) ENCODE VIDEO IN COMPLIANCE WITH THE AVC STANDARD ("AVC VIDEO") AND/OR (ii) DECODE AVC VIDEO THAT WAS ENCODED BY A CONSUMER ENGAGED IN A PERSONAL ACTIVITY AND/OR WAS OBTAINED FROM A VIDEO PROVIDER LICENSED TO PROVIDE AVC VIDEO. NO LICENSE IS GRANTED OR SHALL BE IMPLIED FOR ANY OTHER USE. ADDITIONAL INFORMATION MAY BE OBTAINED FROM MPEG LA, L.L.C. SEE http://www.mpegla.com/

Service Provider

THE FOLLOWING APPLIES TO AVAYA CHANNEL PARTNER'S HOSTING OF AVAYA PRODUCTS OR SERVICES. THE PRODUCT OR HOSTED SERVICE MAY USE THIRD PARTY COMPONENTS SUBJECT TO THIRD PARTY TERMS AND REQUIRE A SERVICE PROVIDER TO BE INDEPENDENTLY LICENSED DIRECTLY FROM THE THIRD PARTY SUPPLIER. AN AVAYA CHANNEL PARTNER'S HOSTING OF AVAYA PRODUCTS MUST BE AUTHORIZED IN WRITING BY AVAYA AND IF THOSE HOSTED PRODUCTS USE OR EMBED CERTAIN THIRD PARTY SOFTWARE, INCLUDING BUT NOT LIMITED TO MICROSOFT SOFTWARE OR CODECS, THE AVAYA CHANNEL PARTNER IS REQUIRED TO INDEPENDENTLY OBTAIN ANY APPLICABLE LICENSE AGREEMENTS, AT THE AVAYA CHANNEL PARTNER'S EXPENSE, DIRECTLY FROM THE APPLICABLE THIRD PARTY SUPPLIER.

WITH RESPECT TO CODECS, IF THE AVAYA CHANNEL PARTNER IS HOSTING ANY PRODUCTS THAT USE OR EMBED THE G.729 CODEC, H.264 CODEC, OR H.265 CODEC, THE

AVAYA CHANNEL PARTNER ACKNOWLEDGES AND AGREES THE AVAYA CHANNEL PARTNER IS RESPONSIBLE FOR ANY AND ALL RELATED FEES AND/OR ROYALTIES. THE G.729 CODEC IS LICENSED BY SIPRO LAB TELECOM INC. SEE WWW.SIPRO.COM/CONTACT.HTML. THE H.264 (AVC) CODEC IS LICENSED UNDER THE AVC PATENT PORTFOLIO LICENSE FOR THE PERSONAL USE OF A CONSUMER OR OTHER USES IN WHICH IT DOES NOT RECEIVE REMUNERATION TO: (I) ENCODE VIDEO IN COMPLIANCE WITH THE AVC STANDARD ("AVC VIDEO") AND/OR (II) DECODE AVC VIDEO THAT WAS ENCODED BY A CONSUMER ENGAGED IN A PERSONAL ACTIVITY AND/OR WAS OBTAINED FROM A VIDEO PROVIDER LICENSED TO PROVIDE AVC VIDEO. NO LICENSE IS GRANTED OR SHALL BE IMPLIED FOR ANY OTHER USE. ADDITIONAL INFORMATION FOR H.264 (AVC) AND H.265 (HEVC) CODECS MAY BE OBTAINED FROM MPEG LA, L.L.C. SEE HTTP://

Compliance with Laws

You acknowledge and agree that it is Your responsibility for complying with any applicable laws and regulations, including, but not limited to laws and regulations related to call recording, data privacy, intellectual property, trade secret, fraud, and music performance rights, in the country or territory where the Avaya product is used.

Preventing Toll Fraud

"Toll Fraud" is the unauthorized use of your telecommunications system by an unauthorized party (for example, a person who is not a corporate employee, agent, subcontractor, or is not working on your company's behalf). Be aware that there can be a risk of Toll Fraud associated with your system and that, if Toll Fraud occurs, it can result in substantial additional charges for your telecommunications services

Avaya Toll Fraud intervention

If You suspect that You are being victimized by Toll Fraud and You need technical assistance or support, call Technical Service Center Toll Fraud Intervention Hotline at +1-800-643-2353 for the United States and Canada. For additional support telephone numbers, see the Avaya Support website: https://support.avaya.com or such successor site as designated by Avaya.

Security Vulnerabilities

Information about Avaya's security support policies can be found in the Security Policies and Support section of https://support.avaya.com/security.

Suspected Avaya product security vulnerabilities are handled per the Avaya Product Security Support Flow (https://support.avaya.com/css/P8/documents/100161515).

Downloading Documentation

For the most current versions of Documentation, see the Avaya Support website: https://support.avaya.com, or such successor site as designated by Avaya.

Contact Avaya Support

See the Avaya Support website: https://support.avaya.com for product or Hosted Service notices and articles, or to report a problem with your Avaya product or Hosted Service. For a list of support telephone numbers and contact addresses, go to the Avaya Support website: https://support.avaya.com (or such successor site as designated by Avaya), scroll to the bottom of the page, and select Contact Avaya Support.

Trademarks

The trademarks, logos and service marks ("Marks") displayed in this site, the Documentation, Hosted Service(s), and product(s) provided by Avaya are the registered or unregistered Marks of Avaya, its affiliates, its licensors, its suppliers, or other third parties. Users are not permitted to use such Marks without prior written consent from Avaya or such third party which may own the Mark. Nothing contained in this site, the Documentation, Hosted Service(s) and product(s) should be construed as granting, by implication, estoppel, or otherwise, any license or right in and to the Marks without the express written permission of Avaya or the applicable third party.

Avaya is a registered trademark of Avaya Inc.

All non-Avaya trademarks are the property of their respective owners. Linux $^{\otimes}$ is the registered trademark of Linus Torvalds in the U.S. and other countries.

Contents

Chapter 1: Introduction	7
Purpose	7
Prerequisites	7
Chapter 2: Overview	8
Kernel-based Virtual Machine overview	8
Chapter 3: Planning	9
Planning checklist	
Supported tools	9
Configuration tools and utilities	. 10
Release details of Avaya Breeze [™] KVM OVA	. 10
Supported footprints	10
Supported hardware	. 11
Key customer configuration information	. 11
Chapter 4: Deployment	. 14
Prerequisites for deploying KVM OVA	14
Deploying the OVA by using Virt Manager	14
Deploying the OVA by using CLI	
Deploying application by using OpenStack	16
Connecting to OpenStack Dashboard	16
Uploading the qcow2 image	17
Flavors	
Creating a security group	
Adding rules to a security group	
Deploying the application by using OpenStack	
Configuring the Avaya Breeze [™] cluster	
Deploying application by using Nutanix	
Logging on to the Nutanix Web console	
Transferring the qcow2 image	
Uploading the qcow2 image	
Creating the virtual machine by using Nutanix	
Starting a virtual machine	
Deploying application by using Red Hat Virtualization Manager	
Logging on to the Red Hat Virtualization Manager Web console	
Uploading the disk	
Creating the virtual machine by using Red Hat Virtualization Manager	
Starting a virtual machine	
Chapter 5: Configuration	
Changing the Avaya Breeze profile	
Configuring the virtual machine	30

Contents

Chapter 6: Resources	
Documentation	3 ²
Finding documents on the Avaya Support website	
Training	
Viewing Avaya Mentor videos	
Support	34
Using the Avava InSite Knowledge Base	

Chapter 1: Introduction

Purpose

This document describes how to deploy and configure Avaya Breeze[™] Kernel-based Virtual Machine (KVM) OVA.

This document is intended for people who install and configure Avaya Breeze[™] KVM OVA at a customer site.

Prerequisites

Before deploying the Avaya Breeze[™] KVM OVA, ensure that you have the following knowledge, skills and tools.

Knowledge

- KVM hypervisor installation and set up
- Linux[®] Operating System
- Avaya Breeze[™]

Skills

To administer the KVM hypervisor and Avaya Breeze[™].

Tools

For information about tools and utilities, see "Configuration tools and utilities".

Chapter 2: Overview

Kernel-based Virtual Machine overview

Kernel-based Virtual Machine (KVM) is a virtualization infrastructure for the Linux kernel that turns the Linux kernel into a hypervisor. You can remotely access the hypervisor to deploy applications on the KVM host.

KVM virtualization solution is:

- · Cost effective for the customers.
- Performance reliable and highly scalable.
- Secure as it uses the advanced security features of SELinux.
- Open source software that can be customized as per the changing business requirements of the customers.

Chapter 3: Planning

Planning checklist

Ensure that you complete the following before deploying Avaya Breeze[™] on KVM:

No.	Task	Reference	Notes	~
1	Download the required software.	See Configuration tools and utilities on page 10 and Release details of Avaya Breeze KVM OVA on page 10		
2	Purchase the required licenses.	_		
3	Register for PLDS and activate license entitlements.	Go to Avaya Product Licensing and Delivery System at https://plds.avaya.com/ .		
4	Install the KVM hypervisor.	_		
5	Install the MobaXterm and Xming softwares.	_	To remotely access the KVM hypervisor, use the Virt Manager GUI or virsh command line interface.	
6	Record information that you require for the deployment.	Key customer configuration information on page 11		

Supported tools

- Virt Manager: A user interface for managing virtual machines through libvirt.
- virsh: A command line interface tool for deploying the OVA.
- virt-manager or virt-viewer: A command line interface tool for configuring the OVA.
- OpenStack: A web-based user interface to OpenStack services.
- Nutanix: An end-to-end management solution for virtualized datacenter environments that streamlines and automates common workflows, eliminating the need for multiple management solutions across datacenter operations.

• Red Hat Virtualization Manager: A feature-rich web interface to manage the virtual infrastructure. Red Hat Virtualization Manager provides host management, guest management, storage management, and high availability infrastructure.

Configuration tools and utilities

- Avaya Breeze[™] OVA
- A browser for accessing Avaya Breeze[™]
- PuTTY
- WinSCP
- MobaXterm

Release details of Avaya Breeze[™] KVM OVA

You can download the following OVA file from the Avaya PLDS website at http://plds.avaya.com/.

Product name	Release version	OVA file name
Avaya Breeze [™]	3.5	Breeze-3.5.0.0.xxxxxxx-kvm-xxx.ova

Supported footprints

Product name	Footprint	Release	CPUs (GHz)	Number of vCPUs	RAM (GB)	HDD (GB)	NICs
Presence Services	Profile 2	3.5	2.2	4	8	80	2
Presence Services	Profile 3	3.5	2.2	6	10	80	2
Presence Services	Profile 4	3.5	2.2	8	16	150	2
Presence Services	Profile 5	3.5	2.2	12	27	300	2

Supported hardware

To deploy the Avaya Breeze[™] KVM OVA on a customer-provided server, the server must be on the Red Hat supported server list for Red Hat Enterprise Linux 7.2 or 7.3.

Key customer configuration information

You require the following information to install and configure Avaya Breeze[™]. Have this information before you begin the installation.

Network Settings

Field	Information to enter	Notes
IP Address	Enter server's IP address	Management IP address to be assigned to Avaya Breeze [™] .
Short Hostname	Enter server's hostname	
Network Domain	Enter network domain or 'none'	
Netmask	Enter netmask	
Default gateway	Enter gateway IP address	Default gateway for Avaya Breeze [™] management network interface.
DNS servers	Enter the Primary, Secondary, and Tertiary DNS server IP address	You can have up to three DNS servers.

Proxy settings

Field	Information to enter	Notes
HTTP Proxy Server	Enter the IP address or FQDN of the HTTP proxy server.	
HTTP Proxy Port	Enter the HTTP proxy port.	
HTTPS Proxy Server	Enter the IP address or FQDN of the HTTPS proxy server.	
HTTPS Proxy Port	Enter the HTTPS proxy port.	
HTTP Proxy exclusion list	Enter the HTTPS proxy severs with a delimiter of " ".	
	For example, *ca.avaya.com *.us.avaya.com 135.9.95.*	

Table continues...

Field	Information to enter	Notes
	By default, the customer domain will be added to the proxy exclusion list. The proxy exclusion list can be added with the CEnetSetup command or using the OVA properties during deployment. If the destination for the HTTP request matches any address in the exclusion list, the HTTP request will be sent directly to the destination instead of the proxy.	

System Time Settings

Field	Information to enter	Notes
Timezone	Select the timezone from this field.	This configuration is mandatory for Avaya Breeze [™] to function. The timezone configured on Avaya Breeze [™] must match the timezone on System Manager.
NTP Servers	Enter IP/FQDN of Primary NTP Server	You can have up to three NTP servers.
		Enter a value in this field only when the VMware host does not synchronize on its own.

User access

Field	Information to enter	Notes
Enhanced Access	Enter one of the following:	
Security Gateway (EASG)	• 1 to enable EASG.	
	• 2 to disable EASG.	

Customer Login Settings

Field	Information to enter	Notes
Login Name	Enter Login ID to use for the customer account (cust).	Login ID and password for customer account you will create during OVA deployment.
Enter Password	Enter the customer account password.	

System Manager Settings

Field	Information to enter	Notes
Primary System Manager IP	Enter the IP Address of the Primary System Manager that will be used to manage this Avaya Breeze™ server.	
Enrollment Password	Enter the Enrollment Password that matches the value in System Manager administration.	You must know the Enrollment Password, and the password must not have expired. The password is set on System Manager at Security > Certificates > Enrollment Password. On this page, verify that the Time Remaining is greater than zero. If you do not know the password, create a new one.

SIP Entity (Security Module Interface) Networking Information

This information is required for administering Avaya Breeze[™] SIP Entity and Avaya Breeze[™]instance.

Required information	Value
IP address	
Subnet Mask	
Gateway	

Chapter 4: Deployment

Prerequisites for deploying KVM OVA

Procedure

- 1. Access the KVM host remotely using MobaXterm.
- 2. Create a folder on the KVM host.
- 3. Copy the KVM OVA to the folder.
- 4. Run the command following command: tar -xvf Breeze-3.5.0.0.xxxxxxx-kvm-xxx.ova

The system extracts the files from the application KVM OVA.

5. Copy the gcow2 image to /var/lib/libvirt/images or an appropriate directory.

Deploying the OVA by using Virt Manager

Procedure

- 1. Log in to the KVM host by using MobaXterm.
- 2. Navigate to the KVM OVA directory.
- 3. Run the command: virt-manager.
- 4. In the Virtual Machine Manager window, click File > New Virtual Machine.
- On the Create a new virtual machine Step 1 of 4 window, select Import existing disk image.
- 6. Click Forward.
- 7. On the Create a new virtual machine Step 2 of 4 window, do the following:
 - a. In the **Provide the existing storage path** field, click **Browse**, and select the qcow2 image.
 - b. In the **OS type** field, select **Linux**.
 - c. In the Version field, select Red Hat Linux Enterprise 7.3.
 - d. Click Forward.

- 8. On the Create a new virtual machine Step 3 of 4 window, do the following:
 - a. In **Memory (RAM)**, enter the required memory based on the profile.
 - b. In **CPUs**, enter the number of CPUs for the virtual machine based on the profile.
 - c. Click Forward.
- 9. On the Create a new virtual machine Step 4 of 4 window, do the following:
 - a. In the **Name** field, assign a name to the virtual machine.
 - b. Select the Customize Configuration before Install check box.
 - c. In the **Network selection** field, verify the required network interface.
 - d. Click Finish.
- 10. In the navigation pane, click **Add Hardware**, and do the following:
 - a. In the Advanced options section, click Network.
 - b. In the **Network source** field, select the required network source.
 - c. Change the device to virtio.
 - d. Click Finish.
 - e. Click Apply.
- 11. Click Begin Installation.

The system creates the virtual machine.

12. Configure the virtual machine.

Related links

Configuring the virtual machine on page 30

Deploying the OVA by using CLI

Procedure

- 1. Log in to the KVM host CLI by using PuTTY.
- Navigate to the KVM OVA directory.
- 3. Run the command: bash Breeze-3.5-s1-KVM-installer.sh
- 4. In the **Enter Profile** field, type the required Avaya Breeze[™] profile:
 - 2
 - 3
 - 4
 - 5

For more information, see "Supported footprints".

- 5. In the **Enter VM name [Breeze]** field, type the name of the virtual machine.
- 6. In the **Enter drive storage location** field, type the storage location.
- 7. In the **Public** field, select the appropriate network.
- 8. In the **Out of Band Management** field, select the appropriate network.
- 9. Type Y to continue.

The system displays the following:

```
Deploying image

Starting install...

Creating domain...

Domain Creation completed.
```

Next steps

Configure the virtual machine.

Related links

<u>Supported footprints</u> on page 10 <u>Configuring the virtual machine</u> on page 30

Deploying application by using OpenStack

Connecting to OpenStack Dashboard

Before you begin

- Create an OpenStack account.
- Acquire adequate permission to upload and deploy the KVM ova.

Procedure

1. In your web browser, type the OpenStack URL.

For example, http://<openstack.xyz.com>/horizon.

- 2. In **Domain**, type the domain name.
- 3. In **User Name**, type the user name.
- 4. Click Connect.

The system displays the Instance Overview - OpenStack Dashboard page.

Uploading the qcow2 image

Procedure

- 1. Log in to the OpenStack dashboard.
- 2. In the navigation pane, click **Project > Compute > Images**.
- 3. On the Images page, click Create Image.

The system displays the Create An Image dialog box.

- 4. In the **Name** field, assign a name to the image.
- 5. In the **Description** field, type the description of the image.
- 6. In the **Image Source** field, select one of the following check boxes:
 - **Image Location**: Type the URL of the qcow2 image.
 - Image File : Click Browse to select the qcow2 image, and then click Open.
- 7. In the Format field, select QCOW2 QEMU Emulator.
- 8. In the **Architecture** field, type x86 64.
- 9. In the Minimum Disk (GB) field, type the details based on the profile.
- 10. In the Minimum RAM (GB) field, type the details based on the profile.
- 11. Click Create Image.

The system displays the created image on the Images page.

Flavors

Flavors are footprints of an application. The administrator must create flavors for each application.

For information about the footprints, see the profiles and footprints information for the application.

Creating a security group

About this task

Security groups are sets of IP filter rules. Each user must create security groups to specify the network settings for the application.

Procedure

- 1. Connect to OpenStack Dashboard.
- 2. In the left navigation pane, click **Project > Compute > Access & Security**.
- 3. On the Access & Security page, click **Create Security Group**.

The system displays the Create Security Group dialog box.

- 4. In **Name**, type the name of the security group.
- 5. In **Description**, type the description of the security group.
- 6. Click Create Security Group.

The system displays the created security group on the Access & Security page.

Next steps

Add rules to security group.

Adding rules to a security group

Before you begin

Create a security group.

For information about the application-specific ports and protocols, see the port matrix document at http://support.avaya.com/security.

Procedure

- 1. On the Access & Security page, click **Manage Rules** that is corresponding to the created security group.
- 2. On the Access & Security / Manage Security Group Rules page, click Add Rule.

The system displays the Add Rule dialog box.

3. In Rule, click a rule

The system displays the fields that are associated with the selected rule.

- 4. Enter the appropriate values in the fields.
- 5. Click Add.

The system displays the created rule on the Access & Security / Manage Security Group Rules page.

Deploying the application by using OpenStack

Before you begin

- · Create flavors.
- Create a security group.

Procedure

- 1. Log in to the OpenStack dashboard.
- 2. In the navigation pane, click **Project > Compute > Instances**.

3. On the Instance page, click Launch Instance.

The system displays the Launch Instance dialog box.

- 4. In the Details section, do the following:
 - a. In the **Instance Name** field, assign a name to the instance.
 - b. In the **Availability zone** field, select the availability zone.
 - c. Click Next.
- 5. In the Source section, do the following:
 - a. In the **Available** field, select the check box corresponding to an instance image.

The system displays the selected image in the **Allocated** field.

- b. Click Next.
- 6. In the Flavors section, do the following:
 - a. In the Available field, select a check box corresponding to a flavor.

The system displays the selected flavor in the **Allocated** field.

- b. Click Next.
- 7. In the Networks section, do the following:
 - a. In the **Available** field, select a check box corresponding to a network.

The system displays the selected network in the **Allocated** field.

- b. Click Next.
- 8. In the Network Ports section, retain the default settings, and click **Next**.
- 9. In the Security Groups section, do the following:
 - a. In the **Available** field, select a check box corresponding to a security group.

The system displays the selected security group in the **Allocated** field.

- b. Click Next.
- 10. In the Key Pair section, retain the default settings, and click **Next**.
- 11. In the Configuration section, retain the default settings, and click **Next**.
- 12. In the Metadata section, retain the default settings.
- 13. Click Launch Instance.

The system displays the created instance on the Instances page.

14. Note down the Management IP address of the virtual machine.

This IP address is for eth0.

- 15. When the **Status** field shows **Running**, attach another network interface:
 - a. Select the virtual machine, and click **Create Snapshot** > **Attach interface**.

- b. In the **Network** field, enter the network name.
- c. Click Attach Interface.
- 16. Note down the IP address that the system populates.

This IP address is for eth1.

- 17. Configure the Avaya Breeze[™] details in System Manager.
- 18. Ensure that the FQDN entries of the Management IP address are configured in System Manager or in DNS.
- 19. Configure Avaya Breeze[™].
- 20. Repeat Step 3 to Step 19 to start another Avaya Breeze[™] instance on OpenStack.
- 21. Configure the Avaya Breeze[™] cluster for more than one Avaya Breeze[™] instance.

Related links

Configuring the virtual machine on page 30

Configuring the Avaya Breeze[™] cluster

About this task

Use this procedure when you have deployed more than one Avaya Breeze[™] instance.

Procedure

- 1. Log in to the OpenStack CLI.
- 2. To create a port for the cluster, run the command: neutron port-create <port name>.

For example, neutron port-create Lab Public Network.

```
| binding:vif details
{ }
| binding:vif_type
                     1
unbound
| binding:vnic_type |
normal
| created at
2017-09-13T07:27:40
 description
 device id
 device owner
 extra_dhcp_opts
           | {"subnet_id": "8372210e-e019-4d38-b40d-4e4c04cc9cb6",
 fixed ips
"ip_address": "10.133.51.175"} |
             | dd7aacce-
f22c-447d-9116-2e182d04a742
| name
             | 33f709ce-974a-4f1a-
| network id
ad74-23a2e5113c4f
| port_security_enabled |
True
| security_groups |
e8bd3ea8-846b-4724-8a12-43d4ae03df15
| status
                    DOWN
| tenant id
f554311a7ce54a75a18b1ba8eb7bf03b
| updated at
2017-09-13T07:27:40
```

The system assigns a cluster IP address.

Ensure that this IP address is not associated to any other virtual machine.

- 3. For the security module port of the Avaya Breeze[™] virtual machines (eth1), add the cluster IP address as the address pair.
 - a. To view the port IDs, run the command: neutron port-list | grep <securitymoduleIP>.

```
For example, neutron port-list | grep 10.133.51.173.

neutron CLI is deprecated and will be removed in the future. Use openstack CLI instead.

| 76489c2e-68f4-4e1c-bd5d-4f4dbc3398fc | | f554311a7ce54a75a18b1ba8eb7bf03b
```

b. For each port ID, run the command: neutron port-update <securitymodule-portid> --allowed_address_pairs list=true type=dict ip address=<CLUSTERIP>.

For example, neutron port-update 76489c2e-68f4-4e1c-bd5d-4f4dbc3398fc --allowed_address_pairs list=true type=dictip_address=10.133.51.175.

neutron CLI is deprecated and will be removed in the future. Use openstack CLI instead.
Updated port: 76489c2e-68f4-4e1c-bd5d-4f4dbc3398fc

- 4. Configure the Avaya Breeze[™] server in System Manager.
- 5. Repeat Step 2 to Step 4 for each Avaya Breeze[™] server.
- 6. Create an Avaya Breeze[™] cluster in System Manager.

Deploying application by using Nutanix

Logging on to the Nutanix Web console

Procedure

- 1. To log on to the Nutanix Web console, in your web browser, type the PRISM URL. For example, http://<PRISM IPAddress>/.
- 2. In **username**, type the user name.
- 3. In **password**, type the password.
- 4. Press Enter.

The system displays the Home page.

Transferring the qcow2 image

Procedure

- 1. Use WinSCP or a similar file transfer utility to connect to the Nutanix container.
- 2. Transfer the qcow2 image from your system to the Nutanix container.

Uploading the qcow2 image

Procedure

- 1. Log on to the Nutanix Web console.
- 2. Click Settings icon () > Image Configuration.

The system displays the Image Configuration dialog box.

3. Click + Upload Image.

The system displays the Create Image dialog box.

- 4. In **NAME**, type the name of the image.
- 5. In **ANNOTATION**, type the description of the image.
- 6. In IMAGE TYPE, click DISK.
- 7. In **STORAGE CONTAINER**, click the storage container of the image.
- 8. In **IMAGE SOURCE**, perform one of the following:
 - Select From URL, type the exact URL of the qcow2 image. For example: nfs:// <127.0.0.1>/<Storage Container Name>/<Image Name>
 - Select **Upload a file**, click **Browse**. In the Choose File to Upload dialog box, select the gcow2 image from your local system, and click **Open**.
- 9. Click Save.

The system displays the created image on Image Configuration.

Creating the virtual machine by using Nutanix

Before you begin

- Upload the qcow2 image.
- Configure the network.
- Create the network for High Availability (HA).

Procedure

- 1. Log on to the Nutanix Web console.
- 2. Click Home > VM.
- 3. Click + Create VM.

The system displays the Create VM dialog box.

- 4. In the General Configuration section, perform the following:
 - a. In **NAME**, type the name of the virtual machine.
 - b. In **DESCRIPTION**, type the description of the virtual machine.
- 5. In the Compute Details section, perform the following:
 - a. In **VCPU(S)**, type the number of virtual CPUs required for the virtual machine.
 - b. In **NUMBER OF CORES PER VCPU**, type the number of core virtual CPUs required for the virtual machine.
 - c. In **Memory**, type the memory required for the virtual machine.

The value must be in GiB.

You must select the CPU and Memory according to the application footprint profile.

- 6. In the Disk section, perform the following:
 - a. Click + Add New Disk.

The system displays the Add Disk dialog box.

- b. In TYPE, click DISK.
- c. In **OPERATION**, click **Clone from Image Service**.
- d. In **IMAGE**, click the application image.
- e. In BUS TYPE, click IDE.
- f. Click **Add**.

The system displays the added disk in the **Disk** section.

- 7. In the Disk section, select a boot device.
- 8. In the Network Adopters (NIC) section, perform the following:
 - a. Click Add New NIC.

The system displays the Create NIC dialog box.

b. In **VLAN NAME**, click the appropriate NIC.

The system displays **VLAN ID**, **VLAN UUID**, and **NETWORK ADDRESS / PREFIX** for the selected NIC.

c. Click Add.

The system displays the added NIC in the Network Adopters (NIC) section.

You must select one more NIC for configuring Out of Band Management.

- 9. In the VM Host Affinity section, perform the following:
 - a. Click Set Affinity.

The system displays the Set VM Host Affinity dialog box.

b. Select one or more host to deploy the virtual machine.

For the HA deployment where both the systems need to be connected directly:

- Select the same host for both the virtual machines.
- Duplication link must use the network that is created for HA.
- c. Click Save.

The system displays the added hosts in the VM Host Affinity section.

10. Click Save.

The system displays the message: Received operation to create VM <name of the VM>.

After the operation is successful, the system displays the created virtual machine on the VM page.

Next steps

Start the virtual machine.

Starting a virtual machine

Before you begin

Create the virtual machine.

Procedure

- 1. Click Home > VM.
- 2. On the VM page, click **Table**.
- 3. Select the virtual machine.
- 4. At the bottom of the table, click **Power On**.

The system starts the virtual machine.

Next steps

Launch the console. On the first boot of the virtual machine, provide the configuration and networking parameters

Related links

Configuring the virtual machine on page 30

Deploying application by using Red Hat Virtualization Manager

Logging on to the Red Hat Virtualization Manager Web console Procedure

- 1. In your web browser, type the Red Hat Virtualization Manager URL.
 - For example, https://<RedHatVirtualizationManager_IPAddress>/ovirt-engine/.
- 2. To log in, click **Not Logged In > Login**.
 - The system displays the Red Hat Virtualization Manager Log In page.
- 3. In **Username**, type the user name.
- 4. In Password, type the password.
- 5. In **Profile**, click the appropriate profile.
- 6. Click Log In.

The system displays the Red Hat Virtualization Manager Web Administration page.

Uploading the disk

Before you begin

You must import the <code>ovirt-engine</code> certificate into your browser by accessing the <code>http://sengine_url>/ovirt-engine/services/pki-resource?resource=ca-certificate&format=X509-PEM-CA link to get the certificate. Establish the trust for the new Certificate Authority (CA) with the website.</code>

Procedure

- 1. Log on to the Red Hat Virtualization Manager Web console.
- 2. In the left navigation pane, click **System**.
- 3. On the **Disks** tab, click **Upload > Start**.

The system displays the Upload Image dialog box.

- 4. Click Browse.
- 5. In the Choose File to Upload dialog box, select the qcow2 disk image from your local system, and click **Open**.
- 6. In **Size(GB)**, type the size of the disk.
- 7. In **Alias**, type the name of the disk.

- 8. In **Description**, type the description of the disk.
- 9. In **Data Center**, click the data center to store the disk.
- 10. In **Storage Domain**, click the storage domain of the disk.
- 11. In **Disk Profile**, click disk profile.
- 12. In **Use Host**, click the host of the disk.
- 13. Click **OK**.

The system displays the uploaded image on the **Disks** tab. Once the disk image is successfully uploaded, the **Status** column displays OK.

Creating the virtual machine by using Red Hat Virtualization Manager

Before you begin

- Upload the gcow2 disk image.
- · Create an instance type.
- Configure the network.

Procedure

- 1. Log on to the Red Hat Virtualization Manager Web console.
- 2. In the left navigation pane, click **System**.
- On the Virtual Machines tab, click New VM.

The system displays the New Virtual Machine dialog box.

- 4. In Operating System, click Linux.
- 5. In **Instance Type**, click an instance type.

You must select the instance type according to the application footprint profile.

- In Optimized for, click Server.
- 7. In **Name**, type the name of the virtual machine.
- 8. In **Description**, type the description of the virtual machine.
- 9. In the Instance Images section, perform the following:
 - a. Click Attach.

The system displays the Attach Virtual Disks dialog box.

- b. In Interface, click VirtIO.
- c. Click OK.

The system displays the added disk in the Instance Images section.

- 10. In **nic1**, click a vNIC profile for management IP address.
- 11. In **nic2**, click a vNIC profile for security module IP address.
- 12. Click **OK**.

After the operation is successful, the system displays the created virtual machine on the **Virtual Machines** tab.

Next steps

Start the virtual machine.

Starting a virtual machine

Before you begin

Create the virtual machine.

Procedure

Right-click the virtual machine and click Run.

When the system starts the virtual machine, the system displays a green upward arrow key () corresponding to the virtual machine name.

Next steps

Launch the console. On the first boot of the virtual machine, provide the configuration and networking parameters

Related links

Configuring the virtual machine on page 30

Chapter 5: Configuration

Changing the Avaya Breeze[™] profile

Procedure

- 1. To change the Avaya Breeze[™] profile using KVM host:
 - a. To power off the virtual machine, run the command: virsh shutdown <VM name>.
 - b. Determine the location of the hard disk image.
 - c. To view the current image size, run the command: qemu-img info /var/lib/ libvirt/images/<image name>.
 - d. Based on the profile, determine the required disk increase if needed.

For example, if you are changing from Profile 2 to Profile 4, you need to add 70G. Profile 2 to Profile 3 would not require an increase of the disk.

- e. To increase the disk size, run the command: qemu-img resize /var/lib/libvirt/images/<hard disk image> +70G.
- f. To change the number CPUs to match the profile: run the command: virsh edit <VM name> and change the value of vcpu.

For example:

```
<vcpu placement='static'>6</vcpu>
```

- g. To change the memory to match the profile, run the commands:
 - virsh setmaxmem <VM name> 8G --config
 - virsh setmem <VM name> 8G --config
- h. Run the command: virsh start <VM name>.
- 2. To change the Avaya Breeze[™] profile using OpenStack:
 - a. Log in to the OpenStack dashboard.
 - b. Select the virtual machine, and click **Create Snapshot** > **Resize instance**.
 - c. Select the new flavor.
 - d. Click Confirm Resize/Migrate.
 - e. Verify that the status of the virtual machine shows **Running**.

Configuring the virtual machine

Procedure

- 1. Start the virtual machine and access the **Console**.
- 2. When the system prompts to configure the virtual machine, enter yes.
- 3. To accept the End User License Agreement, scroll to the end using the Spacebar key, and enter yes.
- 4. When the system prompts, enter the configuration information.
 - See "Key customer configuration information".
 - To alter the configuration settings later, see *Maintaining and Troubleshooting Avaya Breeze*[™].
- 5. Run the CEnetSetup command to change the value of any OVA property specified during deployment.

Chapter 6: Resources

Documentation

See the following related documents at http://support.avaya.com.

Title	Use this document to:	Audience
Understanding		
Avaya Breeze [™] Overview and	Understand the Avaya Breeze [™] platform,	Sales engineers
Specification	customer requirements, and design considerations.	Programmers
Considerations.	Solidardione.	System administrators
		Services and support personnel
Avaya Aura® System Manager	Understand System Manager customer	Sales engineers
Overview and Specification	requirements and design considerations.	Programmers
		System administrators
		Services and support personnel
Implementing		
Deploying Avaya Breeze [™]	Deploy and configure Avaya Breeze [™] .	Services and support personnel
		System administrators
Deploying Zang-Enabled Avaya Breeze [™]	Deploy and configure Zang-enabled Avaya Breeze [™] .	Services and support personnel
		System administrators
Upgrading Avaya Breeze [™]	Upgrade Avaya Breeze [™] .	Services and support personnel
Implementing and Administering Avaya Aura [®] Media Server	Deploy and configure Avaya Aura [®] Media Server.	System administrators

Table continues...

Title	Use this document to:	Audience
		Services and support personnel
Deploying and Updating Avaya Aura [®] Media Server Appliance	Deploy and configure Avaya Aura® Media Server when it is installed on customer-	System administrators
	provided servers.	Services and support personnel
Deploying Avaya Aura® System Manager	Deploy and configure Avaya Aura® System Manager in a virtualized environment using	System administrators
	VMware.	Services and support personnel
Avaya Aura [®] System Manager Solution Deployment Manager Job-	Use Solution Deployment Manager.	System administrators
Aid		Services and support personnel
Migrating and Installing Avaya Aura® Appliance Virtualization Platform	Deploy and configure Avaya Aura [®] Appliance Virtualization Platform.	System administrators
		Services and support personnel
Deploying Avaya Session Border Controller for Enterprise	Deploy and configure Avaya Aura® Session Border Controller.	System administrators
		Services and support personnel
Customizing		'
Getting Started with the Avaya Breeze [™] SDK	Deploy and configure the Eclipse IDE, Apache Maven, and the Avaya Breeze [™] SDK.	Programmers
Avaya Breeze [™] Snap-in Development Guide	Understand the key concepts needed to develop the different types of Avaya Breeze [™] snap-ins.	Programmers
Avaya Breeze [™] FAQ and Troubleshooting for Snap-in Developers	Troubleshoot Avaya Breeze [™] .	Programmers
Avaya Breeze [™] API Javadocs	Understand API classes and uses.	Programmers
Supporting		
Maintaining and Troubleshooting Avaya Breeze [™]	Troubleshoot Avaya Breeze [™] .	Services and support personnel
		System administrators
Troubleshooting Avaya Aura® Session Manager	Troubleshoot Avaya Aura [®] Session Manager.	Services and support personnel

Table continues...

Title	Use this document to:	Audience
Troubleshooting Avaya Aura® System Manager	Troubleshoot System Manager.	Services and support personnel
Using		
Quick Start to deploying the HelloWorld Snap-in	Install, configure, and test an Avaya Breeze [™] snap-in service, specifically the	Programmers
Tronctiona Grap III	HelloWorld call-intercept snap-in.	System administrators
Administering Avaya Breeze [™]	Administer Avaya Breeze [™] and snap-ins.	System Administrators
		Services and Support personnel
Administering Avaya Aura® Session Manager	Administer Avaya Aura® Session Manager.	System Administrators
		Services and support personnel
Administering Avaya Aura® System Manager	Administer Avaya Aura® System Manager.	System Administrators
		Services and support personnel
Administering Avaya Session Border Controller for Enterprise	Administer Avaya Aura® Session Border Controller.	System Administrators
		Services and support personnel

Finding documents on the Avaya Support website

Procedure

- 1. Navigate to http://support.avaya.com/.
- 2. At the top of the screen, type your username and password and click **Login**.
- 3. Click Support by Product > Documents.
- 4. In **Enter your Product Here**, type the product name and then select the product from the list.
- 5. In **Choose Release**, select an appropriate release number.
- 6. In the **Content Type** filter, click a document type, or click **Select All** to see a list of all available documents.
 - For example, for user guides, click **User Guides** in the **Content Type** filter. The list displays the documents only from the selected category.
- 7. Click Enter.

Training

The following courses are available on the Avaya Learning website at http://www.avayalearning.com. After logging in to the website, enter the course code or the course title in the **Search** field, and click **Go** to search for the course.

Course code	Course title
20970W	Introducing Avaya Device Adapter

Viewing Avaya Mentor videos

Avaya Mentor videos provide technical content on how to install, configure, and troubleshoot Avaya products.

About this task

Videos are available on the Avaya Support website, listed under the video document type, and on the Avaya-run channel on YouTube.

Procedure

- To find videos on the Avaya Support website, go to http://support.avaya.com and perform one of the following actions:
 - In Search, type Avaya Mentor Videos to see a list of the available videos.
 - In Search, type the product name. On the Search Results page, select Video in the Content Type column on the left.
- To find the Avaya Mentor videos on YouTube, go to www.youtube.com/AvayaMentor and perform one of the following actions:
 - Enter a key word or key words in the **Search Channel** to search for a specific product or
 - Scroll down Playlists, and click the name of a topic to see the available list of videos posted on the website.



🔀 Note:

Videos are not available for all products.

Support

Go to the Avaya Support website at http://support.avaya.com for the most up-to-date documentation, product notices, and knowledge articles. You can also search for release notes, downloads, and resolutions to issues. Use the online service request system to create a service request. Chat with live agents to get answers to questions, or request an agent to connect you to a support team if an issue requires additional expertise.

Using the Avaya InSite Knowledge Base

The Avaya InSite Knowledge Base is a web-based search engine that provides:

- Up-to-date troubleshooting procedures and technical tips
- Information about service packs
- Access to customer and technical documentation
- Information about training and certification programs
- Links to other pertinent information

If you are an authorized Avaya Partner or a current Avaya customer with a support contract, you can access the Knowledge Base without extra cost. You must have a login account and a valid Sold-To number.

Use the Avaya InSite Knowledge Base for any potential solutions to problems.

- 1. Go to http://www.avaya.com/support.
- Log on to the Avaya website with a valid Avaya user ID and password.The system displays the Avaya Support page.
- 3. Click Support by Product > Product Specific Support.
- 4. In Enter Product Name, enter the product, and press Enter.
- 5. Select the product from the list, and select a release.
- 6. Click the **Technical Solutions** tab to see articles.
- Select relevant articles.

Index

A		L	
adding		log on	
rule	<u>18</u>	Nutanix Web console	<u>22</u>
add rules		Red Hat Virtualization Manager Web console	<u>26</u>
security group	<u>18</u>	-	
		N	
C			_
alveter		Nutanix	<u>9</u>
cluster	20		
configuring		0	
configuration information			
configuration tools	<u>10</u>	Openstack	<u>9</u>
connecting OpenStack Deathboard	16		
OpenStack Dashboard	<u>10</u>	P	
creating	22 27	•	
application virtual machine		planning checklist	<mark>9</mark>
security group		power on VM	_
customer configuration information	<u>11</u>	prerequisites	
		profile	
D		changing	29
		3 3	
deploying		•	
CLI		Q	
KVM OVA by using Virt Manager	<u>14</u>	qcow2 image	17
Deploying		qcowz iiiage	11
Openstack	<u>18</u>		
		R	
E			
		Red Hat Virtualization Manager	
extracting		run virtual machine	<u>28</u>
KVM OVA	14		
		S	
F			
•		start VM	
flavor	<u>17</u>	support	
footprints	<u>10</u>	supported hardware	<u>11</u>
		-	
I		I	
		tools	9
InSite Knowledge Base	<u>35</u>	training	_
		Transferring	
K		Transisting	<u>20</u>
	_	U	
KVM		U	
footprints	<u>10</u>	uploading	
KVM OVA		qcow2 disk image on Red Hat Virtualization	26
Release version	<u>10</u>	qcow2 image on Nutanixqcow2 image on Nutanix	
		953112 111085 511 1 1000111/	<u></u> 0

٧

videos	
virsh	
Virt Manager	
virtual machine	
configuring	30