

# Administering Avaya Call Management System

Release 19.2 Issue 1 March 2021

#### Notice

While reasonable efforts have been made to ensure that the information in this document is complete and accurate at the time of printing, Avaya assumes no liability for any errors. Avaya reserves the right to make changes and corrections to the information in this document without the obligation to notify any person or organization of such changes.

#### **Documentation disclaimer**

"Documentation" means information published in varying mediums which may include product information, operating instructions and performance specifications that are generally made available to users of products. Documentation does not include marketing materials. Avaya shall not be responsible for any modifications, additions, or deletions to the original published version of Documentation unless such modifications, additions, or deletions were performed by or on the express behalf of Avaya. End User agrees to indemnify and hold harmless Avaya, Avaya's agents, servants and employees against all claims, lawsuits, demands and judgments arising out of, or in connection with, subsequent modifications, additions or deletions to this documentation, to the extent made by End User.

#### Link disclaimer

Avaya is not responsible for the contents or reliability of any linked websites referenced within this site or Documentation provided by Avaya. Avaya is not responsible for the accuracy of any information, statement or content provided on these sites and does not necessarily endorse the products, services, or information described or offered within them. Avaya does not guarantee that these links will work all the time and has no control over the availability of the linked pages.

#### Warranty

Avaya provides a limited warranty on Avaya hardware and software. Refer to your sales agreement to establish the terms of the limited warranty. In addition, Avaya's standard warranty language, as well as information regarding support for this product while under warranty is available to Avaya customers and other parties through the Avaya Support website: <u>https://support.avaya.com/helpcenter/</u> <u>getGenericDetails?detailId=C20091120112456651010</u> under the link

getGenericDetails?detailId=C20091120112456651010 under the link "Warranty & Product Lifecycle" or such successor site as designated by Avaya. Please note that if You acquired the product(s) from an authorized Avaya Channel Partner outside of the United States and Canada, the warranty is provided to You by said Avaya Channel Partner and not by Avaya.

#### **Hosted Service**

THE FOLLOWING APPLIES ONLY IF YOU PURCHASE AN AVAYA HOSTED SERVICE SUBSCRIPTION FROM AVAYA OR AN AVAYA CHANNEL PARTNER (AS APPLICABLE), THE TERMS OF USE FOR HOSTED SERVICES ARE AVAILABLE ON THE AVAYA WEBSITE, HTTPS://SUPPORT.AVAYA.COM/LICENSEINFO UNDER THE LINK "Avaya Terms of Use for Hosted Services" OR SUCH SUCCESSOR SITE AS DESIGNATED BY AVAYA, AND ARE APPLICABLE TO ANYONE WHO ACCESSES OR USES THE HOSTED SERVICE. BY ACCESSING OR USING THE HOSTED SERVICE, OR AUTHORIZING OTHERS TO DO SO, YOU, ON BEHALF OF YOURSELF AND THE ENTITY FOR WHOM YOU ARE DOING SO (HEREINAFTER REFERRED TO INTERCHANGEABLY AS "YOU" AND "END USER"), AGREE TO THE TERMS OF USE. IF YOU ARE ACCEPTING THE TERMS OF USE ON BEHALF A COMPANY OR OTHER LEGAL ENTITY, YOU REPRESENT THAT YOU HAVE THE AUTHORITY TO BIND SUCH ENTITY TO THESE TERMS OF USE. IF YOU DO NOT HAVE SUCH AUTHORITY, OR IF YOU DO NOT WISH TO ACCEPT THESE TERMS OF USE, YOU MUST NOT ACCESS OR USE THE HOSTED SERVICE OR AUTHORIZE ANYONE TO ACCESS OR USE THE HOSTED SERVICE.

#### Licenses

THE SOFTWARE LICENSE TERMS AVAILABLE ON THE AVAYA WEBSITE, <u>HTTPS://SUPPORT.AVAYA.COM/LICENSEINFO</u>, UNDER THE LINK "AVAYA SOFTWARE LICENSE TERMS (Avaya Products)" OR SUCH SUCCESSOR SITE AS DESIGNATED BY AVAYA, ARE APPLICABLE TO ANYONE WHO DOWNLOADS,

USES AND/OR INSTALLS AVAYA SOFTWARE, PURCHASED FROM AVAYA INC., ANY AVAYA AFFILIATE, OR AN AVAYA CHANNEL PARTNER (AS APPLICABLE) UNDER A COMMERCIAL AGREEMENT WITH AVAYA OR AN AVAYA CHANNEL PARTNER. UNLESS OTHERWISE AGREED TO BY AVAYA IN WRITING, AVAYA DOES NOT EXTEND THIS LICENSE IF THE SOFTWARE WAS OBTAINED FROM ANYONE OTHER THAN AVAYA, AN AVAYA AFFILIATE OR AN AVAYA CHANNEL PARTNER; AVAYA RESERVES THE RIGHT TO TAKE LEGAL ACTION AGAINST YOU AND ANYONE ELSE USING OR SELLING THE SOFTWARE WITHOUT A LICENSE. BY INSTALLING, DOWNLOADING OR USING THE SOFTWARE, OR AUTHORIZING OTHERS TO DO SO, YOU, ON BEHALF OF YOURSELF AND THE ENTITY FOR WHOM YOU ARE INSTALLING, DOWNLOADING OR USING THE SOFTWARE (HEREINAFTER REFERRED TO INTERCHANGEABLY AS "YOU" AND "END USER"), AGREE TO THESE TERMS AND CONDITIONS AND CREATE A BINDING CONTRACT BETWEEN YOU AND AVAYA INC. OR THE APPLICABLE AVAYA AFFILIATE ("AVAYA").

Avaya grants You a license within the scope of the license types described below, with the exception of Heritage Nortel Software, for which the scope of the license is detailed below. Where the order documentation does not expressly identify a license type, the applicable license will be a Designated System License as set forth below in the Designated System(s) License (DS) section as applicable. The applicable number of licenses and units of capacity for which the license is granted will be one (1), unless a different number of licenses or units of capacity is specified in the documentation or other materials available to You. "Software" means computer programs in object code, provided by Avaya or an Avaya Channel Partner, whether as stand-alone products, pre-installed on hardware products, and any upgrades, updates, patches, bug fixes, or modified versions thereto. "Designated Processor" means a single stand-alone computing device. "Server" means a set of Designated Processors that hosts (physically or virtually) a software application to be accessed by multiple users. "Instance" means a single copy of the Software executing at a particular time: (i) on one physical machine; or (ii) on one deployed software virtual machine ("VM") or similar deployment.

#### License type(s)

Designated System(s) License (DS). End User may install and use each copy or an Instance of the Software only: 1) on a number of Designated Processors up to the number indicated in the order; or 2) up to the number of Instances of the Software as indicated in the order, Documentation, or as authorized by Avaya in writing. Avaya may require the Designated Processor(s) to be identified in the order by type, serial number, feature key, Instance, location or other specific designation, or to be provided by End User to Avaya through electronic means established by Avaya specifically for this purpose.

Concurrent User License (CU). End User may install and use the Software on multiple Designated Processors or one or more Servers, so long as only the licensed number of Units are accessing and using the Software at any given time as indicated in the order, Documentation, or as authorized by Avaya in writing. A "Unit" means the unit on which Avaya, at its sole discretion, bases the pricing of its licenses and can be, without limitation, an agent, port or user, an email or voice mail account in the name of a person or corporate function (e.g., webmaster or helpdesk), or a directory entry in the administrative database utilized by the Software that permits one user to interface with the Software. Units may be linked to a specific, identified Server or an Instance of the Software.

Shrinkwrap License (SR). End User may install and use the Software in accordance with the terms and conditions of the applicable license agreements, such as "shrinkwrap" or "clickthrough" license accompanying or applicable to the Software ("Shrinkwrap License") as indicated in the order, Documentation, or as authorized by Avaya in writing.

#### Heritage Nortel Software

"Heritage Nortel Software" means the software that was acquired by Avaya as part of its purchase of the Nortel Enterprise Solutions Business in December 2009. The Heritage Nortel Software is the software contained within the list of Heritage Nortel Products located at <u>https://support.avaya.com/LicenseInfo</u> under the link "Heritage Nortel Products" or such successor site as designated by Avaya. For Heritage Nortel Software, Avaya grants Customer a license to use Heritage Nortel Software provided hereunder solely to the extent of the authorized activation or authorized usage level, solely for the purpose specified in the Documentation, and solely as embedded in, for execution on, or for communication with Avaya equipment. Charges for Heritage Nortel Software may be based on extent of activation or use authorized as specified in an order or invoice.

#### Copyright

Except where expressly stated otherwise, no use should be made of materials on this site, the Documentation, Software, Hosted Service, or hardware provided by Avaya. All content on this site, the documentation, Hosted Service, and the product provided by Avaya including the selection, arrangement and design of the content is owned either by Avaya or its licensors and is protected by copyright and other intellectual property laws including the sui generis rights relating to the protection of databases. You may not modify, copy, reproduce, republish, upload, post, transmit or distribute in any way any content, in whole or in part, including any code and software unless expressly authorized by Avaya. Unauthorized reproduction, transmission, dissemination, storage, and or use without the express written consent of Avaya can be a criminal, as well as a civil offense under the applicable law.

#### Virtualization

The following applies if the product is deployed on a virtual machine. Each product has its own ordering code and license types. Unless otherwise stated, each Instance of a product must be separately licensed and ordered. For example, if the end user customer or Avaya Channel Partner would like to install two Instances of the same type of products, then two products of that type must be ordered.

#### **Third Party Components**

"Third Party Components" mean certain software programs or portions thereof included in the Software or Hosted Service may contain software (including open source software) distributed under third party agreements ("Third Party Components"), which contain terms regarding the rights to use certain portions of the Software ("Third Party Terms"). As required, information regarding distributed Linux OS source code (for those products that have distributed Linux OS source code) and identifying the copyright holders of the Third Party Components and the Third Party Terms that apply is available in the products, Documentation or on Avaya's website at: https:// support.avaya.com/Copyright or such successor site as designated by Avaya. The open source software license terms provided as Third Party Terms are consistent with the license rights granted in these Software License Terms, and may contain additional rights benefiting You, such as modification and distribution of the open source software. The Third Party Terms shall take precedence over these Software License Terms, solely with respect to the applicable Third Party Components to the extent that these Software License Terms impose greater restrictions on You than the applicable Third Party Terms.

The following applies only if the H.264 (AVC) codec is distributed with the product. THIS PRODUCT IS LICENSED UNDER THE AVC PATENT PORTFOLIO LICENSE FOR THE PERSONAL USE OF A CONSUMER OR OTHER USES IN WHICH IT DOES NOT RECEIVE REMUNERATION TO (i) ENCODE VIDEO IN COMPLIANCE WITH THE AVC STANDARD ("AVC VIDEO") AND/OR (ii) DECODE AVC VIDEO THAT WAS ENCODED BY A CONSUMER ENGAGED IN A PERSONAL ACTIVITY AND/OR WAS OBTAINED FROM A VIDEO PROVIDER LICENSED TO PROVIDE AVC VIDEO. NO LICENSE IS GRANTED OR SHALL BE IMPLIED FOR ANY OTHER USE. ADDITIONAL INFORMATION MAY BE OBTAINED FROM MPEG LA, L.L.C. SEE <u>HTTP://WWW.MPEGLA.COM</u>.

#### Service Provider

THE FOLLOWING APPLIES TO AVAYA CHANNEL PARTNER'S HOSTING OF AVAYA PRODUCTS OR SERVICES. THE PRODUCT OR HOSTED SERVICE MAY USE THIRD PARTY COMPONENTS SUBJECT TO THIRD PARTY TERMS AND REQUIRE A SERVICE PROVIDER TO BE INDEPENDENTLY LICENSED DIRECTLY FROM THE THIRD PARTY SUPPLIER. AN AVAYA CHANNEL PARTNER'S HOSTING OF AVAYA PRODUCTS MUST BE AUTHORIZED IN WRITING BY AVAYA AND IF THOSE HOSTED PRODUCTS USE OR EMBED CERTAIN THIRD PARTY SOFTWARE, INCLUDING BUT NOT LIMITED TO MICROSOFT SOFTWARE OR CODECS, THE AVAYA CHANNEL PARTNER IS REQUIRED TO INDEPENDENTLY OBTAIN ANY APPLICABLE LICENSE AGREEMENTS, AT THE AVAYA CHANNEL PARTNER'S EXPENSE, DIRECTLY FROM THE APPLICABLE THIRD PARTY SUPPLIER.

WITH RESPECT TO CODECS, IF THE AVAYA CHANNEL PARTNER IS HOSTING ANY PRODUCTS THAT USE OR EMBED THE H.264 CODEC OR H.265 CODEC, THE AVAYA CHANNEL PARTNER ACKNOWLEDGES AND AGREES THE AVAYA CHANNEL PARTNER IS RESPONSIBLE FOR ANY AND ALL RELATED FEES AND/OR ROYALTIES. THE H.264 (AVC) CODEC IS LICENSED UNDER THE AVC PATENT PORTFOLIO LICENSE FOR THE PERSONAL USE OF A CONSUMER OR OTHER USES IN WHICH IT DOES NOT RECEIVE REMUNERATION TO: (I) ENCODE VIDEO IN COMPLIANCE WITH THE AVC STANDARD ("AVC VIDEO") AND/OR (II) DECODE AVC VIDEO THAT WAS ÈNCODED BY A CONSUMER ENGAGED IN A PERSONAL ACTIVITY AND/OR WAS OBTAINED FROM A VIDEO PROVIDER LICENSED TO PROVIDE AVC VIDEO. NO LICENSE IS GRANTED OR SHALL BE IMPLIED FOR ANY OTHER USE. ADDITIONAL INFORMATION FOR H.264 (AVC) AND H.265 (HEVC) CODECS MAY BE OBTAINED FROM MPEG LA, L.L.C. SEE HTTP:// WWW.MPEGLA.COM.

#### **Compliance with Laws**

You acknowledge and agree that it is Your responsibility for complying with any applicable laws and regulations, including, but not limited to laws and regulations related to call recording, data privacy, intellectual property, trade secret, fraud, and music performance rights, in the country or territory where the Avaya product is used.

#### Preventing Toll Fraud

"Toll Fraud" is the unauthorized use of your telecommunications system by an unauthorized party (for example, a person who is not a corporate employee, agent, subcontractor, or is not working on your company's behalf). Be aware that there can be a risk of Toll Fraud associated with your system and that, if Toll Fraud occurs, it can result in substantial additional charges for your telecommunications services.

#### Avaya Toll Fraud intervention

If You suspect that You are being victimized by Toll Fraud and You need technical assistance or support, call Technical Service Center Toll Fraud Intervention Hotline at +1-800-643-2353 for the United States and Canada. For additional support telephone numbers, see the Avaya Support website: <a href="https://support.avaya.com">https://support.avaya.com</a> or such successor site as designated by Avaya.

#### **Security Vulnerabilities**

Information about Avaya's security support policies can be found in the Security Policies and Support section of <u>https://</u>support.avaya.com/security.

Suspected Avaya product security vulnerabilities are handled per the Avaya Product Security Support Flow (<u>https://</u>support.avaya.com/css/P8/documents/100161515).

#### **Downloading Documentation**

For the most current versions of Documentation, see the Avaya Support website: <u>https://support.avaya.com</u>, or such successor site as designated by Avaya.

#### **Contact Avaya Support**

See the Avaya Support website: <u>https://support.avaya.com</u> for product or Hosted Service notices and articles, or to report a problem with your Avaya product or Hosted Service. For a list of support telephone numbers and contact addresses, go to the Avaya Support website: <u>https://support.avaya.com</u> (or such successor site as designated by Avaya), scroll to the bottom of the page, and select Contact Avaya Support.

#### Trademarks

The trademarks, logos and service marks ("Marks") displayed in this site, the Documentation, Hosted Service(s), and product(s) provided by Avaya are the registered or unregistered Marks of Avaya, its affiliates, its licensors, its suppliers, or other third parties. Users are not permitted to use such Marks without prior written consent from Avaya or such third party which may own the Mark. Nothing contained in this site, the Documentation, Hosted Service(s) and product(s) should be construed as granting, by implication, estoppel,

or otherwise, any license or right in and to the Marks without the express written permission of Avaya or the applicable third party.

Avaya is a registered trademark of Avaya Inc.

All non-Avaya trademarks are the property of their respective owners. Linux<sup>®</sup> is the registered trademark of Linus Torvalds in the U.S. and other countries.

## Contents

Chapter 1: Introduction	
Chapter 2: About CMS administration	
About CMS administration	
CMS overview	
How CMS stores ACD data	
How CMS stores ACD data	
How CMS physically stores ACD data	
ACD administration	
How CMS tracks ACD data	
How CMS tracks ACD data	
Events that start or stop data collection	
Chapter 3: Getting started with CMS Supervisor.	
About getting started with CMS Supervisor	
Common operational features of the Web Client	
Common operational features of the PC Client	
Before using the Options window	
Controller features	
Chapter 4: Administering Dictionary names for call center entities About using the Dictionary to name call center entities	
About using the Dictionary to name can center entities	
Before using the Dictionary	
Dictionary rules	
About searching the Dictionary using the PC Client	
Permissions required to search the Dictionary	
Searching the Dictionary	
Dictionary global search results	
About administering ACD names in the Dictionary	
Permissions required to administer ACD names	
Adding an ACD name using the Web Client	
Modifying an ACD name using the Web Client	
Deleting an ACD name using the Web Client	
Adding an ACD name using the PC Client	
Modifying an ACD name using the PC Client	
Deleting an ACD name using the PC Client	
About administering ACD Groups in the Dictionary	
Before using ACD groups	
Permissions required for ACD groups	
Listing all ACD Groups using the Web Client	

Viewing the contents of an ACD Group using the Web Client	51
Listing all ACD Groups using the PC Client	
Viewing the contents of an ACD Group using the PC Client	51
About administering agent groups in the Dictionary	
Permissions required to administer agent groups	52
Considerations when sizing and reporting on agent groups	
Adding an agent group using the Web Client	
Copying an agent group using the Web Client	53
Deleting an agent group using the Web Client	54
Listing agents in an agent group using the Web Client	54
Adding agents to an agent group using the Web Client	
Deleting agents from an agent group using the Web Client	
Adding an agent group using the PC Client	56
Copying an agent group using the PC Client	56
Deleting an agent group using the PC Client	57
Listing agents in an agent group using the PC Client	57
Adding agents to an agent group using the PC Client	58
Deleting agents from an agent group using the PC Client	58
About administering agent string values in the Dictionary	59
Permissions required to administer agent string values	
Modifying agent string value descriptions using the Web Client	
Modifying agent string value descriptions using the PC Client	60
Agent string value field descriptions	
About administering announcement names in the Dictionary	
Permissions required to administer announcement names	
Before administering announcement names	
Viewing an announcement name using the Web Client	
Adding an announcement name using the Web Client	
Modifying an announcement name using the Web Client	
Deleting an announcement name using the Web Client	
Viewing an announcement name using the PC Client	
Listing all announcement names for an ACD using the PC Client	
Adding an announcement name using the PC Client	
Modifying an announcement name using the PC Client	
Deleting an announcement name using the PC Client	
About administering AUX reason code names in the Dictionary	
Permissions required to administer AUX reason code names	
Before administering AUX reason code names	
Viewing an AUX reason code name using the Web Client	
Adding an AUX reason code name using the Web Client	
Modifying an AUX reason code name using the Web Client	
Deleting an AUX reason code name using the Web Client	
Viewing an AUX reason code name using the PC Client	70

Listing all AUX reason code names using the PC Client	. 70
Adding an AUX reason code name using the PC Client	. 71
Modifying an AUX reason code name using the PC Client	. 71
Deleting an AUX reason code name using the PC Client	. 72
About administering calculations in the Dictionary	. 73
Permissions required to administer calculations	. 73
Before administering calculations	73
Viewing calculations using the Web Client	. 74
Adding a custom calculation using the Web Client	74
Modifying a custom calculation using the Web Client	. 75
Deleting a custom calculation using the Web Client	. 76
Viewing calculations using the PC Client	. 76
Listing all calculations using the PC Client	. 77
Adding a custom calculation using the PC Client	. 77
Modifying a custom calculation using the PC Client	. 78
Deleting a custom calculation using the PC Client	. 79
About administering call work codes in the Dictionary	. 79
Permissions required to administer call work codes	. 79
Before using call work codes	
Viewing a call work code name using the Web Client	. 80
Adding a name to a call work code using the Web Client	. 80
Modifying a call work code name using the Web Client	. 81
Deleting a call work code name using the Web Client	. 82
Viewing a call work code name using the PC Client	
Listing all call work code names using the PC Client	
Adding a name to a call work code using the PC Client	
Modifying a call work code name using the PC Client	. 83
Deleting a call work code name using the PC Client	. 84
About administering constants in the Dictionary	
Permissions required to administer constants	
Viewing a constant using the Web Client	
Adding a constant using the Web Client	. 85
Modifying a constant using the Web Client	. 86
Deleting a constant using the Web Client	. 86
Viewing a constant using the PC Client	. 87
Listing all constants using the PC Client	
Adding a constant using the PC Client	. 87
Modifying a constant using the PC Client	88
Deleting a constant using the PC Client	88
About administering custom database items in the Dictionary	. 89
Permissions required to administer custom database items	. 89
Before using custom database items	89
Viewing a custom database item using the Web Client	. 89

Adding a custom database item using the Web Client	90
Modifying a custom database item using the Web Client	90
Deleting a custom database item using the Web Client	
Viewing a custom database item using the PC Client	91
Listing all custom database items using the PC Client	92
Adding a custom database item using the PC Client	
Modifying a custom database item using the PC Client	
Deleting a custom database item using the PC Client	
About administering generic string value synonyms in the Dictionary	
Permissions required to administer generic string value synonyms	
Viewing generic string values using the Web Client	
Modifying generic string values using the Web Client	94
Viewing generic string values using the PC Client	95
Modifying generic string values using the PC Client	95
About administering location IDs in the Dictionary	96
Permissions required to administer location IDs	96
Viewing a location ID using the Web Client	
Adding a location ID using the Web Client	96
Modifying a location ID using the Web Client	97
Deleting a location ID using the Web Client	98
Viewing a location ID using the PC Client	98
Listing all location IDs using the PC Client	99
Adding a location ID using the PC Client	99
Modifying a location ID using the PC Client	99
Deleting a location ID using the PC Client	. 100
About administering login ID names in the Dictionary	. 100
Permissions required to administer login ID names	. 101
Before using login ID names	. 101
Viewing a login ID name using the Web Client	. 101
Adding a name to a login ID using the Web Client	. 102
Modifying a login ID name using the Web Client	102
Deleting a login ID name using the Web Client	103
Adding a name to a login ID using the PC Client	. 103
Listing all login ID names using the PC Client	. 104
Adding a name to a login ID using the PC Client	. 104
Modifying a login ID name using the PC Client	105
Deleting a login ID name using the PC Client	105
About administering logout reason code names in the Dictionary	. 106
Permissions required to administer logout reason code names	
Before using logout reason code names	106
Viewing a logout reason code name using the Web Client	. 107
Adding a logout reason code name using the Web Client	. 107
Modifying a logout reason code name using the Web Client	108

Deleting a logout reason code name using the Web Client	. 108
Viewing a logout reason code name using the PC Client	109
Listing all logout reason code names using the PC Client	. 109
Adding a logout reason code name using the PC Client	. 110
Modifying a logout reason code name using the PC Client	. 110
Deleting a logout reason code name using the PC Client	. 111
About administering split or skill names in the Dictionary	. 112
Permissions required to administer split or skill names	. 112
Before using split or skill names	. 112
Viewing a skill name using the Web Client	. 112
Adding a skill name using the Web Client	. 113
Modifying a skill name using the Web Client	. 113
Deleting a skill name using the Web Client	. 114
Viewing a split or skill name using the PC Client	. 114
Listing all split or skill names using the PC Client	. 115
Adding a split or skill name using the PC Client	. 115
Modifying a split or skill name using the PC Client	. 116
Deleting a split or skill name using the PC Client	. 116
About administering split or skill string values in the Dictionary	. 117
Permissions required to administer split or skill string values	. 117
Before using split or skill string values	. 117
Viewing skill string values using the Web Client	. 118
Modifying skill string values using the Web Client	. 118
Viewing split or skill string values using the PC Client	
Modifying split or skill string values using the PC Client	. 119
Split or skill string value field descriptions	. 119
About viewing standard CMS database items in the Dictionary	
Permissions required to view standard CMS database items	121
Viewing standard CMS database items using the Web Client	. 121
Viewing a standard CMS database item using the PC Client	. 121
Viewing all standard CMS database items alphabetically using the PC Client	. 122
About administering tenant names in the Dictionary	122
Permissions required to administer tenant names	. 123
Before using tenant names	. 123
Viewing a tenant name using the Web Client	. 123
Adding a tenant name using the Web Client	123
Modifying a tenant name using the Web Client	. 124
Deleting a tenant name using the Web Client	. 125
Viewing a tenant name using the PC Client	
Listing all tenant names using the PC Client	. 126
Adding a tenant name using the PC Client	. 126
Modifying a tenant name using the PC Client	
Deleting a tenant name using the PC Client	. 127

About administering trunk group names in the Dictionary	127
Permissions required to administer trunk group names	127
Before using trunk group names	128
Viewing a trunk group name using the Web Client	128
Adding a trunk group name using the Web Client	
Modifying a trunk group name using the Web Client	129
Deleting a trunk group name using the Web Client	130
Viewing a trunk group name using the PC Client	130
Listing all trunk group names using the PC Client	131
Adding a trunk group name using the PC Client	131
Modifying a trunk group name using the PC Client	131
Deleting a trunk group name using the PC Client	132
About administering trunk string values in the Dictionary	132
Permissions required to administer trunk string values	133
Administering trunk string values using the Web Client	133
Administering trunk string values using the PC Client	133
Trunk string values field descriptions	134
About administering VDN names in the Dictionary	135
Permissions required to administer VDN names	136
Before using VDN names	136
Viewing a VDN name using the Web Client	136
Adding a VDN name using the Web Client	137
Modifying a VDN name using the Web Client	
Deleting a VDN name using the Web Client	138
Viewing a VDN name using the PC Client	138
Listing all VDN names	139
Adding a VDN name using the PC Client	139
Modifying a VDN name using the PC Client	
Deleting a VDN name using the PC Client	
About administering vector names in the Dictionary	
Permissions required to administer vector names	141
	141
Viewing a vector name using the Web Client	
Adding a vector name using the Web Client	
Modifying a vector name using the Web Client	
Deleting a vector name using the Web Client	
Viewing a vector name using the PC Client	
Listing all vector names using the PC Client	
Adding a vector name using the PC Client	
Modifying a vector name using the PC Client	
Deleting a vector name using the PC Client	
Chapter 5: Administering call center features	
About administering call center features	147

Before administering call center features	. 147
About administering ACD groups	. 147
Before using ACD groups	. 147
Benefits of using ACD groups	. 148
ACD groups feature interfaces	. 149
Permissions required to administer ACD groups	149
Listing ACD groups using the Web Client	149
Viewing the contents of an ACD group using the Web Client	. 150
Adding an ACD group using the Web Client	
Adding an ACD to an ACD group using the Web Client	151
Deleting an ACD from an ACD group using the Web Client	
Deleting an ACD group using the Web Client	
Listing ACD groups using the PC Client	153
Viewing the contents of an ACD group using the PC Client	
Adding an ACD group using the PC Client	
Adding an ACD to an ACD group using the PC Client	
Modifying an ACD group name using the PC Client	
Deleting an ACD from an ACD group using the PC Client	
Deleting an ACD group using the PC Client	
About administering call work codes	
Before using call work codes	
Permissions required to administer call work codes	
Viewing call work codes using the Web Client	
Adding call work codes using the Web Client	
Deleting call work codes using the Web Client	
Viewing call work codes using the PC Client	
Listing all call work codes using the PC Client	
Adding call work codes using the PC Client	
Deleting call work codes using the PC Client	
About administering VDN skill preferences	
Before using VDN skill preferences	. 163
Permissions required to administer VDN skill preferences	. 163
Viewing VDN skill preferences using the Web Client	. 164
Changing VDN skill preferences using the Web Client	
Viewing VDN skill preferences using the PC Client	
Listing all VDN skill preferences using the PC Client	
Changing VDN skill preferences using the PC Client	
About administering split or skill call profiles	
Before using split or skill call profiles	
Permissions required to administer split or skill call profiles	
Viewing split or skill call profiles using the Web Client	
Adding split or skill call profiles using the Web Client	
Modifying a split or skill call profile using the Web Client	

Deleting a split or skill call profile using the Web Client	169
Viewing split or skill call profiles using the PC Client	170
Adding split or skill call profiles using the PC Client	171
Modifying a split or skill call profile using the PC Client	172
Deleting a split or skill call profile using the PC Client	173
About viewing trunk group assignments	174
Before viewing trunk group assignments	174
Permissions required to view trunk group assignments	174
Viewing trunk group assignments using the Web Client	
Viewing all trunk group assignments using the PC Client	175
Viewing a single trunk group assignment using the PC Client	175
Viewing a trunk group assignment by VDN or split using the PC Client	176
About administering VDN assignments	176
Before using VDN assignments	177
Permissions required to administer VDN assignments	177
Administering VDN assignments using the Web Client	177
Viewing VDN assignments using the PC Client	178
Listing VDNs associated with a vector using the PC Client	178
About administering VDN call profiles	179
Before using VDN call profiles	179
Permissions required to administer VDN call profiles	
Viewing a VDN call profile using the Web Client	180
Adding a VDN call profile using the Web Client	180
Modifying a VDN call profile using the Web Client	181
Deleting a VDN call profile using the Web Client	182
Viewing a VDN call profile using the PC Client	182
Adding a VDN call profile using the PC Client	
Modifying a VDN call profile using the PC Client	
Deleting a VDN call profile using the PC Client	
Administering a data summarization time zone using the PC Client	
Data summarization time zone fields	187
Chapter 6: Administering call center agents	189
About administering call center agents	189
Administering agent skills	189
Before changing agent skills	189
Permissions required to change agent skills	190
About changing agent skills using the Web Client	190
About changing agent skills using the PC Client	193
Administering multi-agent skill change	198
Before changing skills for multiple agents	198
Permissions required to change skills for multiple agents	199
About administering multi-agent skill change using the Web Client	199
About administering multi-agent skill change using the PC Client	201

Administering agent trace	203
About starting or stopping an agent trace	203
Viewing current agent trace states using the Web Client	
Viewing current agent trace states using the PC Client	205
About listing agents traced	206
Administering splits using the PC Client	208
About administering splits using the PC Client	208
About changing extension split assignments	208
Move extensions between splits	209
About running a split members report	211
Chapter 7: Administering users and user permissions	213
About administering users and user permissions	
Before using the User Permissions subsystem	
Example of user permissions	
About administering users	214
Viewing CMS users	214
Adding a CMS user	
Modifying CMS users	220
Deleting CMS users	221
About changing user passwords using the Web Client	223
About administering access to CMS features	225
Before administering access to CMS features	225
Permissions required to administer access to CMS features	226
Viewing and modifying feature access permissions using the Web Client	226
Viewing feature access user permissions using the PC Client	227
Listing all feature access user permissions using the PC Client	227
Modifying feature access user permissions using the PC Client	228
About administering custom menu items and access	229
Before using custom menu items and access	229
Permissions required to administer custom menu items and access	229
Viewing, adding, or modifying custom menu items and access using the Web Client	
Viewing custom menu items and access using the PC Client	230
Listing all custom menu items and access using the PC Client	
Assigning or modifying custom menu items and access using the PC Client	
About administering access to splits or skills	
Before administering access to splits or skills	
Permissions required to administer access to splits or skills	
Viewing split or skill user permissions using the Web Client	
Adding split or skill user permissions using the Web Client	
Modifying split or skill user permissions using the Web Client	
Deleting split or skill user permissions using the Web Client	
Viewing split or skill user permissions using the PC Client	
Listing all split or skill user permissions using the PC Client	236

Adding split or skill user permissions using the PC Client	. 237
Modifying split or skill user permissions using the PC Client	. 237
Deleting split or skill user permissions using the PC Client	. 238
About administering access to trunk group data	. 239
Before administering access to trunk group data	. 239
Permissions required to administer access to trunk group data	240
Viewing trunk group data user permissions using the Web Client	240
Adding trunk group data user permissions using the Web Client	. 241
Modifying trunk group data user permissions using the Web Client	. 241
Deleting trunk group data user permissions using the Web Client	. 242
Viewing trunk group data user permissions using the PC Client	242
Listing all trunk group data user permissions using the PC Client	243
Adding trunk group data user permissions using the PC Client	. 244
Modifying trunk group data user permissions using the PC Client	. 244
Deleting trunk group data user permissions using the PC Client	. 245
About administering access to ACDs	246
Before administering access to ACDs	246
Permissions required to administer access to ACDs	. 247
Viewing ACD access permissions using the Web Client	. 247
Adding ACD access permissions using the Web Client	. 248
Modifying ACD access permissions using the Web Client	. 248
Deleting ACD access permissions using the Web Client	. 249
Viewing ACD user permissions using the PC Client	
Listing all ACD user permissions using the PC Client	250
Adding ACD user permissions using the PC Client	. 250
Modifying ACD user permissions using the PC Client	. 251
Deleting ACD user permissions using the PC Client	. 251
About administering access to vector data	. 252
Before administering access to vector data	. 252
Permissions required to administer access to vector data	253
Viewing vector data user permissions using the Web Client	253
Adding vector data user permissions using the Web Client	254
Modifying vector data user permissions using the Web Client	254
Deleting vector data user permissions using the Web Client	255
Viewing vector data user permissions using the PC Client	255
Listing all vector data user permissions using the PC Client	256
Adding vector data user permissions using the PC Client	256
Modifying vector data user permissions using the PC Client	. 257
Deleting vector data user permissions using the PC Client	. 258
About administering access to VDN data	
Before administering access to VDN data	. 259
Permissions required to administer access to VDN data	260
Viewing VDN data user permissions using the Web Client	260

Adding VDN data user permissions using the Web Client	260
Modifying VDN data user permissions using the Web Client	261
Deleting VDN data user permissions using the Web Client	262
Viewing VDN data user permissions using the PC Client	262
Listing all VDN data user permissions using the PC Client	263
Adding VDN data user permissions using the PC Client	263
Modifying VDN data user permissions using the PC Client	264
Deleting VDN data user permissions using the PC Client	265
About administering access to tenant data	266
Before administering access to tenant data	266
Permissions required to administer access to tenant data	267
Viewing tenant data user permissions using the Web Client	267
Adding tenant data user permissions using the Web Client	267
Modifying tenant data user permissions using the Web Client	268
Deleting tenant data user permissions using the Web Client	268
Administering access to tenant data using the PC Client	269
Tenant access operations using the PC Client	270
Chapter 8: Administering exceptions	271
About administering exceptions	
About exceptions.	271
Types of exceptions	272
Notification when exceptions occur	273
Exception capacities	273
Before using exceptions	274
Permissions required to administer exceptions	274
About administering exception notification using the PC Client	275
Changing exception notification using the PC Client	
About administering agent exceptions	
Before using agent exceptions	276
Permissions required to administer agent exceptions	276
Administering agent exceptions using the Web Client	277
Adding agent exceptions using the PC Client	278
Modifying agent exceptions using the PC Client	279
Deleting agent exceptions using the PC Client	280
Agent exception definitions	281
About administering split or skill exceptions	284
Before using split or skill exceptions	284
Permissions required to administer split or skill exceptions	284
Administering split or skill exceptions using the Web Client	285
Adding split or skill exceptions using the PC Client	286
Modifying split or skill exceptions using the PC Client	287
Deleting split or skill exceptions using the PC Client	
Split or skill exception definitions	288

About administering trunk group exceptions	290
Before using trunk group exceptions	290
Permissions required to administer trunk group exceptions	290
Administering trunk group exceptions using the Web Client	290
Adding trunk group exceptions using the PC Client	292
Modifying trunk group exceptions using the PC Client	293
Deleting trunk group exceptions using the PC Client	294
Trunk group exception definitions	294
About administering VDN exceptions	295
Before using VDN exceptions	295
Permissions required to administer VDN exceptions	296
Administering VDN exceptions using the Web Client	296
Adding VDN exceptions using the PC Client	297
Modifying VDN exceptions using the PC Client	298
Deleting VDN exceptions using the PC Client	299
VDN exception definitions	300
About administering vector exceptions	301
Before using vector exceptions	302
Permissions required to administer vector exceptions	302
Administering vector exceptions using the Web Client	302
Adding vector exceptions using the PC Client	303
Modifying vector exceptions using the PC Client	304
Deleting vector exceptions using the PC Client	305
Vector exception definitions	306
About the real-time exceptions log	307
Before using the real-time exceptions log	307
Viewing the real-time exceptions log using the Web Client	308
Viewing the real-time exceptions log using the PC Client	308
Chapter 9: Administering tenant features	309
About the CMS Tenancy feature	309
Tenant user access restrictions	310
Administering tenant features using the PC Client	312
About administering tenant features	312
Administering tenant features	312
PC Client tenant administration sub-menus	313
Chapter 10: Configuring CMS system settings	320
About administering system settings	
Before configuring CMS system settings	
About viewing Switch Setup data	
Before using Switch Setup	
Permissions required to use Switch Setup	
Viewing Switch Setup data using the Web Client	
Viewing Switch Setup data using the PC Client	

Listing all Switch Setup data using the PC Client	322
About administering pseudo-ACDs	
Before administering pseudo-ACDs	323
Permissions required to administer pseudo-ACDs	
Viewing pseudo-ACDs using the Web Client	
Adding pseudo-ACDs using the Web Client	
Deleting pseudo-ACDs using the Web Client	324
Viewing pseudo-ACDs using the PC Client	325
Adding a pseudo-ACD using the PC Client	325
Deleting a pseudo-ACD using the PC Client	328
About backing up data from a real ACD to load on a pseudo-ACD	328
Before backing up data from a real ACD to load on a pseudo-ACD	
Scenario for backing up data from a real ACD to load on a pseudo-ACD	
Permissions required to back up data from a real ACD to load on a pseudo-ACD	
Backing up specific tables to load on a pseudo-ACD	
About loading pseudo-ACD data	
Before loading pseudo-ACD data	
Permissions required to load pseudo-ACD data	333
Verifying that the backup data can be read	
Loading pseudo-ACD data using the Web Client	
Loading pseudo-ACD data using the PC Client	
About administering Data Storage Allocation	
Before using Data Storage Allocation	
Permissions required to administer Data Storage Allocation	338
Viewing Data Storage Allocation using the Web Client	
Viewing Data Storage Allocation using the PC Client	
About modifying Data Storage Allocation	
About viewing Free Space Allocation	
Before viewing Free Space Allocation	342
Permissions required to view Free Space Allocation	342
Viewing Free Space Allocation using the Web Client	342
Viewing Free Space Allocation using the PC Client	343
Viewing Free Space Allocation detailed values using the PC Client	343
About administering storage intervals	344
Before administering storage intervals	344
Permissions required to administer storage intervals	344
Viewing storage interval settings using the Web Client	345
Viewing storage interval settings using the PC Client	345
About modifying the intrahour interval	
About modifying the switch time zone	347
About modifying the data summarizing time settings	348
About administering custom menu items	
Viewing custom menu items using the Web Client	352

Adding custom menu items using the Web Client	352
Modifying custom menu items using the Web Client	353
Deleting custom menu items using the Web Client	353
About CMS operational states	354
Before changing the CMS operational state	354
Permissions required to change CMS operational states	. 355
Changing the CMS operational state using the Web Client	. 355
Changing the CMS operational state using the PC Client	355
Changing the master ACD using the Web Client	356
Changing the master ACD using the PC Client	356
About turning data collection on and off	357
Before turning data collection on and off	
Permissions required to turn data collection on and off	358
Turning data collection on and off using the Web Client	
Turning data collection on and off using the PC Client	358
About running data summarizing	. 359
Before running data summarizing	359
Permissions required to run data summarizing	360
Running data summarizing using the Web Client	. 360
Running data summarizing using the PC Client	361
Administering a data summarization time zone using the Web Client	361
Administering a data summarization time zone using the PC Client	362
About External Application Status	364
Before using External Application Status	364
Permissions for External Application Status	364
Enabling or disabling the External Application Status feature	365
Viewing the states of external applications	365
Starting or stopping external applications	. 366
About migrating data	. 367
Before migrating data	. 367
Permissions required to migrate data	368
Migrating data using the Web Client	368
Migrating data using the PC Client	369
Migrate Data field descriptions	370
Chapter 11: Maintaining CMS	. 373
About maintaining CMS	. 373
Before using the Maintenance window	373
Rebooting your CMS server regularly	374
About backing up data	
About CMSADM backups	375
About maintenance backups	
Tape drives and cartridges	376
USB/network backup/restore devices	

Considerations when backing up or restoring data	376
About doing a CMSADM backup	381
About doing a maintenance backup	385
About binary database backups	. 393
Adding a Full Maintenance Backup Timetable for an ACD using the PC Client	395
About restoring data	398
Before restoring data	398
Permissions required to restore data	. 399
Doing an automatic restore using the Web Client	399
Doing a manual restore using the Web Client	400
Doing an automatic restore using the PC Client	401
Doing a manual restore using the PC Client	402
Restoring the database from a binary backup	404
About administering backup and restore devices	. 404
Permissions required to administer backup and restore devices	. 404
Viewing backup or restore devices using the Web Client	404
Adding a backup or restore device using the Web Client	. 405
Modifying a backup or restore device using the Web Client	. 405
Deleting a backup or restore device using the Web Client	. 406
Viewing backup or restore devices using the PC Client	. 406
Listing all backup and restore devices using the PC Client	. 407
Adding a backup or restore device using the PC Client	. 407
Modifying a backup or restore device using the PC Client	. 408
Deleting a backup or restore device using the PC Client	. 408
About administering a printer	. 409
Before administering a printer	. 409
Permissions required to administer a printer	409
Viewing printers using the Web Client	410
Adding a printer using the Web Client	410
Modifying printer options using the Web Client	. 411
Deleting a printer using the Web Client	. 411
Listing all printers using the PC Client	412
Adding a printer using the PC Client	412
Modifying printer options using the PC Client	. 413
Deleting a printer using the PC Client	. 414
About administering report properties	. 414
Before administering report properties	. 415
Permissions required to administer report properties	415
Modifying report properties using the Web Client	
Modifying report properties using the ASCII (text) Client	416
About viewing connection status	
Permissions required to view connection status	
Viewing connection status using the Web Client	. 417

Viewing connection status of an ACD using the PC Client	417
Listing connection status of all ACDs using the PC Client	417
Connection status field descriptions	418
About viewing ACD status	419
Before viewing ACD status	419
Permissions required to view ACD status	420
Viewing ACD status using the Web Client	420
Viewing ACD status using the PC Client	420
Listing ACD status using the PC Client	421
ACD status field descriptions	421
About viewing archiving status	421
Permissions required to view archiving status	422
Viewing archiving status using the Web Client	422
Viewing archiving status of a single ACD using the PC Client	422
Viewing archiving status of all ACDs using the PC Client	423
Archiving status field descriptions	423
Viewing firewall status using the Web Client	424
Viewing the CMS licensed features and status	424
Administering LDAP	425
About LDAP integration	425
Configuring LDAP	
Advanced Debugging window	427
Chapter 12: Using administration and maintenance reports	428
About administration and maintenance reports	428
About Dictionary reports	428
Permissions required to run Dictionary reports	428
Types of Dictionary reports	429
Printing dictionary reports	
Running an agent group members report	431
About exception reports	431
Running the Agent Exceptions by Location report using the Web Client	
Running the Data Collection Exceptions report using the Web Client	433
Running the Malicious Call Trace report using the Web Client	434
Running the Split or Skill Exceptions report using the Web Client	
Running the Trunk Group by Location Exceptions report using the Web Client	436
Running the VDN Exceptions report using the Web Client	437
Running the Vector Exceptions report using the Web Client	438
Running the Agent Exceptions by Location report using the PC Client	
Running the Data Collection Exceptions report using the PC Client	
Running the Malicious Call Trace report using the PC Client	
Running the Split or Skill Exceptions report using the PC Client	
Running the Trunk Group by Location Exceptions report using the PC Client	
Running the VDN Exceptions report using the PC Client	446

Running the Vector Exceptions report using the PC Client	448
About Trunk Group Members reports	449
Before using the Trunk Group Members report	449
Permissions required to use the Trunk Group Members report	449
Running the Trunk Group Members report using the Web Client	450
Running the Trunk Group Members report using the PC Client	450
About Vector Configuration reports	451
Before using the Vector Configuration report	451
Permissions required to use the Vector Configuration report	451
Running the Vector Configuration report using the Web Client	451
Running the Vector Configuration report using the PC Client	452
About tenant administration reports	452
Running the Tenant Agent Group Members report using the Web Client	453
Running the Tenant Agent Group Members report using the PC Client	453
Running the Tenant Agent Groups report using the PC Client	453
About maintenance reports	454
About the ACD Administration Log report	454
About the Maintenance Error Log report	456
Chapter 13: Scripting CMS operations	483
Scripting CMS operations	
Before you begin scripting CMS operations	483
Tasks scripts can automate	483
Interactive and automatic scripts	
Script creation	
Scripting options description	
Setting user ID and password	
Setting users procedure	486
Scripting reports	487
Creating an interactive report script	
Creating an automatic report script	487
Creating a script to export report data	
Creating a script to export report data as HTML	488
Scripting operational tasks	
About scripting an input window	
Scripting an action	
Organizing scripts	
Error and warning messages	
Chapter 14: Administrative tasks using the operating system	494
Using the operating system	
Before using the operating system	494
Logging in to CMS	494
Logging in to CMS from the remote console	
Logging in to CMS from the server console	495

Administering passwords	496
Before administering passwords	496
Changing a user's password	
Administering password aging	498
Chapter 15: Using timetables and shortcuts	499
About using timetables and shortcuts	
Timetables	499
Before using timetables	499
Permissions for timetables	500
Creating and scheduling a timetable	501
Adding tasks to a timetable	504
Listing all timetables	506
Copying a timetable	507
Copying timetable tasks	509
Modifying timetable tasks	511
Editing timetables globally	514
Globally editing tasks in a timetable	516
Deleting tasks from a timetable	519
Deleting a timetable	521
Shortcuts	523
Before using shortcuts	523
Permissions for shortcuts	523
Creating a shortcut	524
Adding tasks to a shortcut	525
Running a shortcut	526
Modifying a shortcut description	527
Copying a shortcut	528
Copying shortcut tasks	529
Modifying shortcut tasks	531
Deleting shortcut tasks	532
Deleting a shortcut	533
Chapter 16: Resources	535
Documentation	535
Finding documents on the Avaya Support website	539
Accessing the port matrix document	539
Avaya Documentation Center navigation	540
Viewing Avaya Mentor videos	541
Support	541
Using the Avaya InSite Knowledge Base	
Appendix A: Updating time zones	
Updating time zones displayed to users	
Glossary	

# **Chapter 1: Introduction**

# Purpose

This document describes how to administer call center features of Avaya Call Management System (CMS) using CMS Supervisor.

CMS Supervisor is available in two client interfaces:

- · Web Client, where you access CMS using a web browser.
- PC Client, where you access CMS using a software package installed on a user's personal computer (PC).

Most administrative tasks are available using either client, but some tasks are only available using one client or the other. Procedures in this document identify which tasks are available from the Web Client or the PC Client.

This document is intended for:

- CMS administrators.
- Supervisors with access to CMS.

# **Chapter 2: About CMS administration**

# **About CMS administration**

This section provides introductory information on Avaya CMS Supervisor and how you use CMS Supervisor to administer the CMS. Basic information about the different CMS Supervisor interfaces and how to use them is found in *Avaya CMS Supervisor Clients Installation and Getting Started*.

This section contains the following topics:

- CMS overview on page 24
- How CMS stores ACD data on page 25
- ACD administration on page 30
- <u>About the CMS Tenancy feature</u> on page 309

# **CMS** overview

CMS is a software product for businesses and organizations that have an Avaya Aura<sup>®</sup> Communication Manager system that receives a large volume of telephone calls that the Automatic Call Distribution (ACD) feature of Communication Manager processes. CMS collects call-traffic data, formats management reports, and provides an administrative interface to the ACD feature on the Communication Manager system.

### Important:

From the perspective of CMS, a Communication Manager system is known as an "ACD", which is also the term used to represent the feature Automatic Call Distribution. In CMS, when the documentation says "an ACD" or "administer the ACD", what it really means is "a Communication Manager system" or "administer the Communication Manager system".

A CMS administrator or supervisor using CMS Supervisor accesses the CMS database, generates reports, administers ACD parameters, and monitors call activities to determine the most efficient service for the customers that are calling that business.

## 😒 Note:

Use the tenancy feature to restrict user access to CMS reporting data and functionality within the call center.

The following servers support Avaya CMS:

- Avaya Solutions Platform servers running specific versions of Linux<sup>®</sup>.
- Specific Dell servers running specific versions of Linux<sup>®</sup>.
- Specific HPE servers running specific versions of Linux<sup>®</sup>.

CMS uses the operating system to communicate with terminals and printers, log errors, and execute processes. CMS uses the Informix Software, Inc. INFORMIX database management system, which provides an interface to the CMS historical database.

# How CMS stores ACD data

CMS stores ACD data in two ways:

- · Logically: How CMS organizes data for processing.
- Physically: How CMS mechanically stores the data on the disk drive.

# How CMS logically stores ACD data

The logical storage of the ACD data has more impact on the CMS user than does the physical storage. The logical data storage controls how a CMS user can gain access to and work with ACD data. CMS stores all ACD data received from the communication server in the real-time and historical databases.

## **Real-time databases**

Real-time databases include tables for the current intrahour interval data and the previous intrahour interval data. The storage interval can be 15, 30, or 60 minutes.

## **Historical databases**

Historical databases include tables for the intrahour, daily, weekly, and monthly data. The following table shows all historical database tables and the maximum time that the data can be stored in a particular table:

Historical database tables	Maximum time for data storage
Intrahour historical data	370 days

Table continues...

Historical database tables	Maximum time for data storage
Daily historical data	5 years (1825 days)
Weekly historical data	10 years (520 weeks)
Monthly historical data	10 years (120 months)

### Note:

You can use historical data to predict future call traffic and future agent and trunk requirements. For more information see *Avaya CMS Forecast User Guide*.

## Data summarizing

When CMS collects data from the ACD, the real-time database stores the data for the current interval. At the end of the current interval, the following events occur:

- The data that was in current interval database table is archived to the previous interval database table.
- The data that was in previous interval database table is archived in the historical database as intrahour historical data.


The data remains in the historical database as intrahour historical data for a maximum of 370 days. At your designated data summarizing time, the intrahour historical data is summarized into daily historical data.

The daily historical data is summarized on a weekly and monthly basis. At the end of your designated week, the daily historical data is summarized into weekly historical data. On the first day of a new month, the daily historical data is summarized into monthly historical data for the previous month.

For more information, see Data storage on page 26.


## Data storage

The following figure shows how CMS stores data.



# How CMS physically stores ACD data

CMS uses Informix Dynamic Server (IDS) as the relational database. IDS manages the CMS data in specific dbspaces. The historical database can span multiple disks. Hardware RAID spans multiple disks of the CMS system. CMS systems use RAID 10 which stripes the data across multiple disks and also mirrors pairs of the striped disks.



The *cmsdbs* dbspace contains the CMS historical data.

## 😵 Note:

This figure is an example based on a physical disk system consisting of four disks. The CMS system that you actually use can have a different number of total disks. CMS also supports a small system that only has one disk. The small system does not have any striping or mirroring of data on the system.

## Dbspace

A dbspace is a logical database that consists of one or more chunks. Dbspaces can exist across multiple disks. A CMS system contains the following dbspaces:


- rootdbs
- physdbs
- logdbs
- dbtemp
- cmsdbs

## Important:

Do not try to alter rootdbs, physdbs, logdbs, dbtemp, or cmsdbs. Contact CMS services if you think that you have a problem with any of these dbspaces.

## Chunks

A chunk is a unit of physical disk space used to store database data that IDS manages. For CMS, each dbspace contains one chunk. The size of each chunk depends on the data requirement specification of CMS. The following figure shows an example of chunk sizing. IDS requires the rootdbs, physdb, and logdbs dbspaces, but these databases store minimal data. Dbspace dbtemp is larger and is used for temporary data space. Dbspace cmsdbs is the location that stores all CMS data and contains the largest chunk of data.



# **ACD** administration

CMS provides an administrative interface to Communication Manager ACD features. From the CMS Supervisor interface, you can view or change parameters on Communication Manager related to ACDs, Call Vectoring, and Expert Agent Selection (EAS). An administrator can also run reports that describe your call center configuration.

For example, an administrator can:

- · Add or remove agents from splits or skills
- · Move extensions between splits
- Change skill assignments
- · Change trunk group-to-split
- Change trunk group-to-VDN
- Change VDN-to-vector assignments
- Start an agent trace
- List the agents that are traced
- · Create, copy, and edit call vectors

# How CMS tracks ACD data

CMS uses the data in the real-time and historical databases to generate standard reports that help you monitor your call center activities. Various agents, split/skill, trunk, trunk group, vector, and VDN activities are tracked at different points in the call process.


## How CMS tracks a call

The following diagram shows how CMS tracks a call from the time the call seizes a trunk until an agent ends after-call-work (ACW) activity.

The trunk table, trunk group table, vector table, VDN table, split/skill table, agent table, and call work code (CWC) table are CMS database tables that store call data. In the following diagram, the positions of the CMS database tables identify the points where CMS begins to collect call data. The arrowheads identify the points where data collection ends. CMS does not record the data in the tables until the call and any ACW is complete.

#### 😵 Note:

With vectoring, the **stop** command stops the processing of vector commands.



## Events that start or stop data collection

Data collection starts or stops when one of these events occur:

- The Agent table starts collecting data on non-ACD calls when the agent answers or completes dialing.
- The Split/Skill table stops collecting data when:
  - The ACW for an ACD call ends
  - The call leaves the split queue and is forwarded to another destination . For example, intraflow.
  - The caller abandons the call
- The Vector table stops collecting data for the current vector when the call is:
  - Sent to an ACD agent
  - Connected to a station or trunk
  - Routed to a VDN or vector
  - Abandoned by the caller

#### Note:

Time in the vector stops, but the vector tracks the call disposition to determine if the call is answered or abandoned.

- The VDN table stops collecting data for the current VDN when:
  - The ACW for an ACD call ends
  - The call is routed to a trunk or VDN
  - The call is transferred
  - The caller abandons the call

# Chapter 3: Getting started with CMS Supervisor

# About getting started with CMS Supervisor

This chapter describes how to get started using the CMS Supervisor clients:

- The Web Client, which is a browser-based tool that runs on the CMS server.
- The PC Client, which is a software program you install on your PC.

The Web Client and the PC Client both allow you to administer users and features of your call center, and report on usage of your call center. Most of the administration and reporting functionality are the same between the two clients.

This chapter describes some of the common functionality and initial setup of the Web Client and the PC Client. For basic software installation, log on, and log out procedures for CMS Supervisor, see *Avaya CMS Supervisor Clients Installation and Getting Started*.

Prior to Release 19.2, you could log on to CMS using the same user ID from different PCs. With Release 19.2 using the CMS Supervisor Web Client, you can only log on once using the same user ID. When you try to log on a second time from the a browser interface, the system prompts you to end the current logon session and start a new session.

😵 Note:

The limit of a single logon session only applies to the Web Client interface. You can log on to both the CMS Supervisor Web Client and PC Client interfaces from the same IP address, but each session consumes a CMS Supervisor license.

# **Common operational features of the Web Client**

This section describes some of the common operational features of the Web Client. These features operate the same way whether you are administering features on your call center, running reports, or doing maintenance procedures on CMS.

#### Searching for and ordering data within a set of results

Many of the Web Client tasks display results for the task when you first enter the window. The results displayed for the task can be much longer than what can be shown in the browser window.

The Web Client allows you to enter a string of characters to filter and show you only the information you want to see.

Once you display the filtered results, you can click on the table headers to display the information in alphabetic and numeric order.

#### Exporting results to a file

You can export results from administrative tasks or reports to either a text file format or a spreadsheet file format. The Web Client supports the following file formats:

- .txt
- .csv
- .xls

To export results to a file:

- 1. Click the **Export to CSV** icon ( ... ) or button.
- 2. Click **Save as** (administration tasks only).
- 3. Browse to where you want to save the file.
- 4. Enter a file name with the file extension you want to use.
- 5. Click Save.

#### Printing administration results or reports

You can print administration results or reports data using a printer administered on your PC. To print results or reports:

- 1. Click the **Print** icon ( →) or button.
- 2. Select the printer to which you want to print. You can also print to PDF and save the PDF file.
- 3. Click Print.

If printing to PDF, browse to where you want to save the file, enter a file name, and click **Save**.

# **Common operational features of the PC Client**

This section contains information about how to configure the CMS Supervisor PC Client through the Options window.

The Options window allows you to adjust and control the following types of settings:

- · The default ACD for all operations and reports windows
- · Scripting defaults
- · Colors used in CMS Supervisor reports
- Formatting of the different types of fields displayed in CMS Supervisor reports

## Before using the Options window

Except for the CMS Servers tab, all other tabs of the Options window are only available after a successful login to a CMS server. The CMS Servers tab is disabled when you are logged in to a CMS server.

## **Controller features**

## **Overview of the Controller**

When you are logged in to the CMS server, the toolbar, status bar, and menu bar have more functions. Your CMS user permissions determines which of the menu items and toolbar buttons are available to you.

## Toolbar

The toolbar contains buttons for quick access to specific features of the application. When you move your cursor over a toolbar button, a tooltip displays with a brief description of the command the button performs and a tooltip. For more information, see the specific sections on these features.

## **Status indicators**

These indicators on the status bar indicate the state of CMS.

Name	Description
Login status	A green light if you are connected to the CMS server, and a gray light if you are not connected.
Exception counter	An exception count of the ACDs for which you have exception permissions. The count is zero at the beginning of an interval.
ACD Status	Icons for the ACDs that are supported by the CMSIf the link to an ACD is not working, the icon is crossed out. If the CMS server is connected to the ACD through a TCP/IP connection and the connection is in a transient (stalled) state, the icon changes to a straight line. If you put your mouse over an indicator, a tooltip displays the name of the ACD.
Date and time	The current date and time of the CMS server that you are logged in to.

### Status messages

The status bar of the Controller window and other Avaya CMS Supervisor windows might display any of the following Avaya CMS status messages.

Name	Description
Working	An action is incomplete. The window is locked during this time.
Successful	An action completes without errors.
Error	A syntactical error is identified in a field. An error message with field help also displays.
Failed	An action request cannot complete. An Acknowledgement window explains why the request failed.
Does not exist	A record that you are trying to change, delete, or a record for which you are searching is not in the database.
Already exists	A record you are trying to add is in the database. This message also displays when you try to add a range of items, some of which exist and some of which do not. You can add the records that do not exist to the database. The record that already exist remain unchanged.
Cancelled	You cancel a potentially destructive action in an Acknowledgement window.
No matches found	A Find one action completes.
[Number] matches found; permitted ones displayed	A <b>List all</b> action completes, reminding you that you might not have permission to view or change all matches.
No permission	You do not have read permission for the match or matches identified in the search. This issue might occur on the first match identified doing a <b>Find one</b> or on any match identified doing a <b>Next</b> or <b>Previous</b> .
See status window	A status window displays to further explain the condition.

## Menu bar

This section identifies the five menus that are available after you log in to the CMS server: **Commands**, **Connect**, **Tools**, **Script**, and **Help**. For more information, see the specific sections on these features.

## **General tab**

Use the General tab to set your first calendar day, default ACD, and other interface usage options.

This tab of the Options dialog box contains the following controls:

Name	Description
First Day of Week	This option affects only how the calendar displays. For example, if you browse for a date, the calendar starts the week based on the day that you choose. This action does not change the Start of Week day for weekly data collection that displays through the System Setup-Storage Intervals window.
Default ACD	Select the ACD that is used as the default ACD for operations and reports windows. Note that an ACD Group can also be set as the default.
Synchronize PC and CMS Time at Login	Select this check box to change the internal clock of the computer to match the current time on the CMS server. This option does not affect the time on the CMS server.
Use Sound	Select this check box to receive an audible alert when the <b>Exceptions Indicator</b> box is updated. The <b>Exceptions Indicator</b> box is located on the Controller status bar. The sound that you hear is the sound that you chose for the exclamation event in Windows. Threshold Highlighting does not use sound and uses color only as an indicator of a threshold being met.
Use Tooltips	Select this check box to make tooltips visible for the controls in the CMS Supervisor interface. For example, when you are working in the CMS Supervisor Controller window, you can put your mouse pointer over a toolbar button. The system displays a yellow box that provides a brief description of that button.
Use Taskbar Icon	Select this check box to have CMS Supervisor put an icon in the notification area.
Window Menu Sort Order	Use this option group to determine how items that are displayed in the menu for notification area icon are arranged:
	• <b>Start Order</b> : Select this option to display the items in the notification area icon menu where the last item used displays at the top of the menu.
	• <b>Alphabetical</b> : Select this option to display the items in the notification area icon menu in alphabetical order.

## Scripting tab

Use the Scripting tab to set the user ID used to run scripts, adjust the logging level, and set the file used for logging.

This tab of the Options dialog box contains the following controls:

Name	Description
User ID	The login ID for a CMS user.
Set User	Select this button to open the Save as Script - User Information dialog box.
Logging Level	This option group facilitates the following logging levels in configuring the amount of information that is recorded during scripting:
	• <b>Minimum</b> : The only activities that are logged are errors and messages from Supervisor that is displayed in the window. These messages are displayed as if the user performed the scripted activity manually.
	• <b>Normal</b> : All activities are logged, plus the start and stop time of each task in the script. This control also includes the script name.
	• <b>Maximum</b> : All activities are logged, plus more information that might be useful for debugging a script. Any message that displays as the script runs is logged.
Log File Path	Enter the path and the file name of the log file in this field. You might also use the Browse button to the right of this field to select a file on the PC.
Log File Size	This field determines how large the script log file can get before the log file begins replacing the oldest data. The field defaults to a value of 200KB.
View Log	Select this button to view the script log file.

### **Report Colors tab**

Use the Report Colors tab to set the colors in your graphical reports.

This tab of the **Options** dialog box contains the following controls:

Name	Description
Scheme	This field contains all available color schemes.
Save As	Selecting this button saves any changes made in the color bar window as a new scheme. See <u>Creating a new report color scheme</u> on page 38 for instructions on creating report color schemes.
Remove	Selecting this button deletes the displayed scheme.
Color window	This display of 16 bars lets you change the color and pattern of each bar by performing a right-click on that bar.

Table continues...

Name	Description
Background	The background color of reports provides two choices:
	<ul> <li>White : Select this option to display a white background for all reports.</li> </ul>
	<ul> <li>Automatic : Select this option to have the background of all reports use the color scheme configured through Windows.</li> </ul>

### Creating a new report color scheme

### Procedure

1. From the menu bar of the Controller window, select **Tools > Options**.

CMS Supervisor displays the Options window.

- 2. Select the Report Colors tab.
- 3. From the **Scheme** drop-down list, select the color scheme you want to use as a basis for the new color scheme.

CMS Supervisor displays the configuration of the scheme in the color bar window.

- 4. From the **Background** options, select **White** or **Automatic**.
- 5. Click the color bar (1 through 16) that you want to change.
- 6. If you want to change the color, select the **Change Color** button and select the color through the Change Color dialog box that the system displays .
- 7. If you want to change the pattern, select the **Change Pattern** button and select the pattern from the resulting list.
- 8. Repeat Step <u>5</u> on page 38 through Step <u>7</u> on page 38 until you have updated all color bars that you want to change.
- 9. When you finish modifying color bars, select the Scheme button.

### 😵 Note:

If you do not save the new color scheme using the **Save As** button, the changes that you make overwrites the default color scheme that you change.

CMS Supervisor displays the Save Scheme As window.

- 10. Enter a name for this new color scheme in the relevant field.
- 11. Select **OK** to save this scheme.

To view the changes that you made to a color scheme at any point, select the **Apply** button. The current color scheme is then applied to any reports that are running.

### **Threshold Colors tab**

Use the Threshold Colors tab to set the colors that are used in reports to notify you when exceptions thresholds are reached.

This tab of the	Options d	lialog contains	the following controls:
		5	5

Name	Description
Options	This drop-down list box contains all of the existing color schemes available.
Scheme	Selecting this button saves any changes made in the color bar window as a new scheme. See <u>Creating a new threshold color scheme</u> on page 39 for instructions on creating new color schemes.
Remove	Selecting this button deletes the currently displayed scheme.
View/set colors for report threshold indicators	This list box displays the states used for exception thresholds. A graphical representation of the selected state is displayed in the area to the right.
Color	Use the button to the right of this field to change the color for the selected exception threshold state.
Pattern	Use the button to the right of this field to change the graphical pattern applied for the selected exception threshold state.

### Creating a new threshold color scheme

### Procedure

1. From the menu bar of the Controller window, select **Tools > Options**.

CMS Supervisor displays the Options window.

- 2. Select the Threshold Colors tab.
- 3. From the **Scheme** drop-down list, select the color scheme you want to use as a basis for the new color scheme.

CMS Supervisor displays the view of the scheme.

4. In the **View/set colors for report threshold indicators** list, select the item you want to change.

Supervisor displays the current setting for the selected item in the area to the right of the list box. The **Color** and **Pattern/Background** fields display the respective settings for the current item.

5. If you want to change the color of the selected item, select the **Change Color** button at the right of the **Color** field.

CMS Supervisor displays the standard Color window from Windows allowing you to select the new color.

6. If you want to change the pattern/background color for the selected item, select the button at the right of the **Pattern/Background** field.

Depending on the item selected, Supervisor will display either the pattern list or the Color window which allows you to select a new pattern or background color.

- 7. Repeat Steps <u>4</u> on page 39 through <u>6</u> on page 40 until you have updated all of the threshold element colors that you want to modify.
- 8. When you are done modifying the threshold element colors, select the **Save As** button.

Supervisor displays the Save Scheme As window.

- 9. In the text box, enter a name for this new threshold color scheme you have just created.
- 10. Select the **OK** button to save this new color scheme.

To view the changes that you made to a color scheme at any point in the modification, select the **Apply** button.

The current color scheme is then applied to any reports that are running.

### Name Format tab

Use the Name Format tab to choose or create formats for how CMS entities, for example, splits/ skills, ACDs, VDNs, vectors, trunks, trunk groups, call work codes, and AUX codes, are displayed in CMS. Supervisor. The display can be set to any one or a combination of **{name}** for Dictionary Name, **{entity}** for entity type, and **{number}** for entity number.

Choose or create a name format using **{name}** for entity name, as entered in the Dictionary, **{entity}** for entity type, and **{number}** for entity number. These formats determine how items are displayed in reports. For example, if you select the name format of **{entity}{number}**, all entities that can be named in the Dictionary are displayed as the entity type and number instead of the name defined in the Dictionary. If you selected **{name}** as the name format, the names that are assigned to the entities in the Dictionary are displayed.

### **Defining entity formats**

### Procedure

- 1. From the **Entity** field, select the item for which you want to change the format.
- 2. In the **Format** field, use one of the following methods to select a format for the specified entity type:
  - Manually enter the format that you want using the three possible types: {name}, {entity}, and {number}. Using a separator character between formats is unnecessary unless you want the separator to appear in the report. For example, if you want to display agent names and extension numbers on reports, enter {name} {number} in the Format box.
  - Use the drop-down list to choose from a set of preformatted options.

The **Example** field provides an example of what the format resembles based on your current definition.

If you entered a nonstandard name format, this format not saved in the Format list.

3. Select **OK** to save your changes.

# Chapter 4: Administering Dictionary names for call center entities

# About using the Dictionary to name call center entities

This section provides information on procedures for using the Dictionary to administer names that are associated with call center entities. Dictionary only works on Communication Manager systems enabled with Expert Agent Selection (EAS).

# **About the Dictionary**

Use the Dictionary subsystem to assign synonyms or names to call center entities. The following is a list of entities that you can assign names in the Dictionary:

- ACDs
- Agent groups
- · Agent string values
- Announcements
- AUX reason codes
- · Call work codes
- · Generic string values
- Location IDs
- Login IDs
- Logout reason codes
- Splits/skills
- Split/Skill string values
- Tenants
- Trunk groups
- Trunk string values
- VDNs

Vectors

The Dictionary also allows users to work with items in the database such as:

- Viewing ACD groups
- Creating and administering custom calculations
- · Creating and administering constants
- Creating and administering custom database items
- · Viewing standard database items
- Viewing standard calculations

The names assigned through the Dictionary appear on reports to help users understand them better. The Dictionary also makes it possible for users to create agent groups, change agent splits/ skills, and change trunk string values for reporting purposes. The Dictionary also provides a global search function on the PC Client to find any item within the Dictionary.

# Before using the Dictionary

When using the PC Client, if you select an ACD Group as the current ACD in the Dictionary window, only those operations that are valid for the ACD Group displays in the **Operations** list.

### Note:

Changes to the Dictionary should occur during off hours when there are the fewest database updates. Otherwise, the CMS Supervisor users will need to constantly query the database to update the cache on the computer where CMS Supervisor is running. This causes the real-time reports to hang and users are denied access to CMS Supervisor.

### **Dictionary rules**

The following rules apply when assigning names in the Dictionary:

- Can have from 1 to 20 characters.
- First character must be A-Z or a-z.
- Remaining characters can be A-Z, a-z, 0-9, underscores (\_), periods (.), and commas (,).
- Spaces are allowed in all Dictionary names except:
  - Calculation names
  - Constant names
- Names must be unique within each section of the Dictionary for an ACD.

For example, you can name trunk group 1 as "sales", and skill 1 as "sales", but you cannot name skill 1 as "sales" and skill 2 as "sales" on the same ACD. Similarly, no two agents can have the same synonyms within the same ACD.

- Fields and entries made in the Dictionary are case-sensitive.
- The following rules apply to the descriptions assigned in the Dictionary:
  - Descriptions in the Dictionary can have from 0 to 50 characters.
  - Descriptions can include all printable characters except:
    - Semicolon (;)
    - Double quotes (")
    - Pipe symbol (|)

# About searching the Dictionary using the PC Client

The Dictionary, when using the PC Client, contains a global search feature that you can use to find a variety of information. Some examples of the types of information that you can search for in the dictionary are:

- A login ID or a group of login IDs
- A split, skill, or trunk group
- ACD names
- Database items
- Calculations
- Agent names
  - 😵 Note:

Remember the following before entering the search criteria:

- You can search on any pattern.
- You can include an asterisk (\*) or question mark (?) in your pattern.
- The search is case sensitive.

# Permissions required to search the Dictionary

To do a global search in the dictionary, you need the *write* permissions for the Dictionary subsystem.

# Searching the Dictionary

### Procedure

From the Controller window, select Commands > Dictionary.
 CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Global Search.
- 3. In the **Search for** field, enter the item name or pattern.
- 4. From the **Actions** menu, select **Run**.

CMS displays the Dictionary Global Search Results.

# **Dictionary global search results**

Field	Contents
Value matched	Displays the matches for your pattern.
Field matched	Displays the name of the field in the Dictionary that corresponds to value matched.
In submenu	The Dictionary submenu that contains your search pattern.
Name	The name that corresponds to the value matched.

# About administering ACD names in the Dictionary

This section provides information on administering ACD names in the Dictionary. You can use the Dictionary Operations window to assign names to real and pseudo ACDs. Generated reports contain the ACDs names, instead of the assigned ACD numbers.

### 😵 Note:

For tenant users, the Dictionary Operations window provides the user with the **Find one** and **List all** options. The tenant user can determine matching entries in the database for the ACD numbers and ACD names entered in the fields of the Dictionary ACDs window.

You can add, delete, or change an ACD name regardless of the ACD that you are logged in to. For example, you can be logged in to ACD 1 and change the name for ACD 3. This change does not appear on the changed window border of the ACD until you open a new window.

### Important:

The Dictionary naming rules apply to these procedures. See <u>Dictionary rules</u> on page 43 for more information.

### Permissions required to administer ACD names

Depending on the procedure that you want to perform, you need the following permissions:

- To add, delete, or change the name of an ACD, you need "write" permissions for the Dictionary subsystem and for the ACD.
- To view ACD names, you need "read" permissions for the Dictionary subsystem and for the ACD.

# Adding an ACD name using the Web Client

### Procedure

1. Navigate to **Administration > Dictionary > ACDs**.

CMS Supervisor displays the list of administered ACD names.

2. Click Add ACD.

CMS Supervisor displays the Add ACD window.

- 3. Administer the following options:
  - In the ACD Number field, enter a number from 1 to 26 to correspond with the new ACD name. Numbers 1 through 8 is reserved for real ACDs and 9 through 26 is reserved for pseudo-ACDs.
  - In the ACD Name field, enter the name of the ACD or ACD Group.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Modifying an ACD name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > ACDs.

CMS Supervisor displays the list of administered ACD names.

2. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 3. Administer the following options:
  - The ACD Number is a display-only field. You cannot modify this value.
  - In the ACD Name field, enter the name of the ACD or ACD Group.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Deleting an ACD name using the Web Client

### About this task

#### Important:

Deleting an ACD name from the Dictionary only removes the name of the ACD. The ACD is then displayed as unnamed\_acdn where n is the number of the ACD. No warnings are given during the process of deleting an ACD. This procedure should not be performed unless you are certain that you want to delete the ACD name.

#### Procedure

#### 1. Navigate to Administration > Dictionary > ACDs.

CMS Supervisor displays the list of administered ACD names.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

3. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

4. Click **OK**.

CMS Supervisor displays an updated list of items.

# Adding an ACD name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **ACDs**.
- 3. Click **OK**.

CMS Supervisor displays the Dictionary ACDs window.

4. In the **ACD Name** field, enter the name of the ACD or ACD Group that you want to add, delete, or change.

The name you assign to an ACD, pseudo ACD, or ACD Group in the Dictionary is displayed on all reports and window titles that are associated with that ACD.

- 5. In the **ACD Number** field, enter a number from 1 to 26 to correspond with the new ACD name. Numbers 1 through 8 is reserved for real ACDs and 9 through 26 is reserved for pseudo-ACDs.
- 6. To add your changes to the Dictionary, select **Actions > Add**.

# Modifying an ACD name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **ACDs**.
- 3. Click OK.

CMS Supervisor displays the Dictionary ACDs window.

- 4. In the **ACD Number** field, enter the number of the ACD, pseudo-ACD, or ACD Group that you want to change.
- 5. From the Actions menu, select Find one.
- 6. In the **ACD Name** field, enter the new name for the selected ACD.
- 7. To add your changes to the Dictionary, select Actions > Modify.

# Deleting an ACD name using the PC Client

### About this task

### Important:

Deleting an ACD name from the Dictionary only removes the name of the ACD. The ACD is then displayed as  $unnamed\_acdn$  where *n* is the number of the ACD. No warnings are given during the process of deleting an ACD. This procedure should not be performed unless you are certain that you want to delete the ACD.

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **ACDs**.
- 3. Click OK.

CMS Supervisor displays the Dictionary ACDs window.

- 4. In the **ACD Number** field, enter the number of the ACD, pseudo-ACD, or ACD Group for which you want to delete the name.
- 5. From the Actions menu, select Find one.

The name of the ACD is displayed in the ACD Name field.

6. Select Actions > Delete to remove the ACD from the Dictionary.

# About administering ACD Groups in the Dictionary

This section provides information for viewing ACD Groups in the Dictionary. ACD Groups and the corresponding members can only be viewed through the Dictionary Operations window. Administration of ACD Groups is done through the Call Center Administration subsystem. The capability of viewing ACD Groups through the Dictionary subsystem allows those individuals who only run reports in the call center to view which ACDs are defined within each ACD Group. This capability can assist these individuals in determining which ACD Groups should be used when running reports.

### 😵 Note:

You cannot select ACD Groups to display information through standard CMS reports. To run reports for ACD Groups, you must create custom reports through the CMS ASCII interface. You can also have the reports created for you by contacting the Avaya Professional Services Organization.

# Before using ACD groups

You must read and understand the following before working with ACD Groups in the Dictionary:

- If you add an ACD Group, you must log out of CMS Supervisor. Then, you must log back in to see this group as a choice in the appropriate dialog boxes.
- An ACD Group cannot serve as the CMS master ACD.
- Overlapping ACD Groups, which are groups having common member ACDs, might result in synonym conflict within the members of an ACD Group if poorly administered. Because of this capability, entity IDs in overlapping ACD Groups must be mutually exclusive.
- Entity synonyms must be unique for an ACD Group and across all ACDs that are members of the ACD Group.
- User permissions are administered separately for an ACD Group and the group's member ACDs.
- CMS real-time custom reports are only displayed if data collection is enabled and the ACD link status is 'up' for at least one member ACD in the specified ACD Group. An error message is displayed if these conditions are not met.
- Custom reports that you create with the Single ACD Only option enabled cannot be run for an ACD Group and vice versa.

# Permissions required for ACD groups

Depending on the procedure that you want to perform, you need the following permissions:

• To view, export, or print ACD groups, you need "read" permissions for the Dictionary subsystem and the ACD group.

😵 Note:

A tenant using the Web Client can only view the ACD groups to which they have been assigned.

Listing all ACD Groups using the Web Client

### Procedure

Navigate to Administration > Dictionary > ACD Groups.

CMS Supervisor displays the list of administered ACD Groups.

# Viewing the contents of an ACD Group using the Web Client Procedure

1. Navigate to Administration > Dictionary > ACD Groups.

CMS Supervisor displays the list of administered ACD Groups.

- Click the folder next to an ACD Group to display the contents of the group.
   CMS Supervisor displays the list of ACDs that are part of the administered ACD Group.
- 3. Click **Back to Group List** to display the list of administered ACD Groups.

# Listing all ACD Groups using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **ACD Groups**.
- 3. Select OK.

CMS Supervisor displays the Dictionary ACD Groups window.

4. From the menu bar, select **Actions > List all**.

CMS Supervisor displays the Dictionary ACD Groups List all window listing all ACD Groups defined on this CMS server.

# Viewing the contents of an ACD Group using the PC Client Procedure

- 1. From the Controller window, select **Commands > Dictionary**.
- 2. In the **Operations**list, highlight **ACD Groups**.
- 3. Select OK.

CMS Supervisor displays the Dictionary ACD Groups window.

- 4. In the ACD Group Name field, enter the name of the ACD Group that you want to view.
- 5. From the menu bar, select **Actions > Find one**.

CMS Supervisor retrieves the information for the specified ACD Group, if valid.

6. From the menu bar, select Actions > Get contents .

CMS Supervisor displays the Dictionary ACD Groups Get contents window which lists all ACDs assigned to this ACD Group.

# About administering agent groups in the Dictionary

This section provides procedures for creating and naming, copying, and deleting agent groups in the Dictionary using the Agent Groups window.

Agents can be grouped for reporting purposes, without regard to the split/skill assignment for the agent. For example, you can create a group for new employees or a group for employees with special skills.

### Permissions required to administer agent groups

Depending on the procedure that you want to perform, you need the following permissions:

- To add, delete, or change agent groups, you need "write" permissions for the Dictionary subsystem.
- To view agent groups, you need "read" permissions for the Dictionary subsystem.
- For more information about considerations on creating agent groups, see <u>Considerations</u> when sizing and reporting on agent groups on page 52.

### Considerations when sizing and reporting on agent groups

When creating agent groups, think about the following sizing and reporting recommendations:

• Limit the size of agent groups to approximately 99 agents. Avoid any agent groups larger than 99 agents because the system performance is adversely affected.

#### 😵 Note:

The new CMS systems have a customer administrable flag for limiting the historical and real time reporting on agent groups to groups of 99 or less. See <u>About administering</u> <u>report properties</u> on page 414 for more information about this topic.

- You can add or remove up to 32 agents at a time.
- When possible, report on consecutive Agent IDs in the same report.
- When possible, limit agent group reports and use skill-based reports.
- Tenant users must have permissions for the agent group they want to modify.

# Adding an agent group using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Agent Groups.

CMS Supervisor displays the list of agent groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to add an agent group.

CMS Supervisor displays the list of agent groups administered for the selected ACD.

3. Click Add Agent Group.

CMS Supervisor displays the Add Agent Group window.

4. In the Add Agent Group field, enter the name of the agent group.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Copying an agent group using the Web Client

### Procedure

1. Navigate to **Administration > Dictionary > Agent Groups**.

CMS Supervisor displays the list of agent groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to add an agent group.

CMS Supervisor displays the list of agent groups administered for the selected ACD.

3. Click **Copy** for one of the agent groups.

CMS Supervisor displays the Copy Agent Group window.

4. In the **To Agent Group Name** field, enter the name of the agent group.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting an agent group using the Web Client Procedure

1. Navigate to **Administration > Dictionary > Agent Groups**.

CMS Supervisor displays the list of agent groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to add an agent group.

CMS Supervisor displays the list of agent groups administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Listing agents in an agent group using the Web Client

### Procedure

1. Navigate to **Administration > Dictionary > Agent Groups**.

CMS Supervisor displays the list of agent groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to add an agent group.

CMS Supervisor displays the list of agent groups administered for the selected ACD.

3. Click Group Contents for one of the agent groups.

CMS Supervisor displays the list of agents administered for the agent group.

4. Click **Back to Group List** to get back to the list of agent groups administered for the current ACD.

# Adding agents to an agent group using the Web Client Procedure

1. Navigate to Administration > Dictionary > Agent Groups.

CMS Supervisor displays the list of agent groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to add agents to an agent group.

CMS Supervisor displays the list of agent groups administered for the selected ACD.

3. Click **Group Contents** for the agent group to add agents.

CMS Supervisor displays the list of agents administered for the agent group.

4. Click Add Agent(s).

CMS Supervisor displays the Agent Groups: Contents window.

- 5. Search for agent names or login IDs in the Add Agent(s) field.
- 6. Click the plus sign to move the agents you want to add to the agent group from the Search Results area to the Selected Agents area. Click the minus sign to move the agents from the Selected Agents area to the Search Results area. You can add up to 32 agents at a time.
- 7. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

8. Click **OK**.

CMS Supervisor displays an updated list of items.

9. Click **Back to Group List** to get back to the list of agent groups administered for the current ACD.

# Deleting agents from an agent group using the Web Client

### Procedure

1. Navigate to **Administration > Dictionary > Agent Groups**.

CMS Supervisor displays the list of agent groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to delete agents from an agent group.

CMS Supervisor displays the list of agent groups administered for the selected ACD.

3. Click Group Contents for the agent group to delete agents.

CMS Supervisor displays the list of agents administered for the agent group.

4. Click Remove Agent(s).

CMS Supervisor displays the Agent Groups: Contents window.

- 5. Search for agent names or login IDs in the Remove Agent(s) field.
- 6. Click the plus sign to move the agents you want to remove from the agent group from the **Search Results** area to the **Selected Agents** area. Click the minus sign to move the agents from the **Selected Agents** area to the **Search Results** area. You can delete up to 32 agents at a time.
- 7. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

8. Click OK.

CMS Supervisor displays an updated list of items.

9. Click **Back to Group List** to get back to the list of agent groups administered for the current ACD.

# Adding an agent group using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Agent Groups**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which the agent group exists.
- 4. Click OK.

CMS Supervisor displays the Dictionary Agent Groups window.

- 5. In the Agent group name field, enter the name of the new agent group.
- 6. To add the agent group to the Dictionary, select **Actions > Add**.
- To add the Login IDs for this agent group, select Actions > Get contents.
   CMS Supervisor displays the Agent Groups-Get Contents window.
- 8. Enter the Login IDs for the new group.
- 9. To add the Login IDs to the Dictionary for this agent group, select **Actions > Add**.

### Copying an agent group using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Agent Groups**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which the agent group exists.
- 4. Click OK.

CMS Supervisor displays the Dictionary Agent Groups window.

- 5. In the Agent group name field, enter the name of the new agent group.
- 6. From the **Actions** menu, select **Copy Group**.

CMS Supervisor displays the Dictionary Agent Groups window.

- 7. In the **Copy from** field, enter the name of the agent group that you want to copy.
- 8. From the Actions menu, select Copy Group.

The new agent group is automatically populated with all agents from the copied group.

# Deleting an agent group using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Agent Groups**.
- 3. In the ACD field, enter the ACD or ACD Group on which the agent group exists.
- 4. Click OK.

CMS Supervisor displays the Dictionary Agent Groups window.

- 5. In the Agent group name field, enter the name of the agent group to delete.
- 6. From the Actions menu, select Delete.

The selected agent group name is removed from the Dictionary.

### Listing agents in an agent group using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Agent Groups**.
- 3. In the ACD field, enter the ACD or ACD Group on which the agent group exists.
- 4. Click **OK**.

CMS Supervisor displays the Dictionary Agent Groups window.

- 5. In the **Agent group name** field, enter the name of the agent group.
- 6. From the Actions menu, select Get contents.

CMS Supervisor displays the Agent Groups-Get Contents window.

7. From the Actions menu, select List all.

CMS Supervisor displays the Dictionary Agent Groups-Get Contents-List All window listing the agents in the group.

# Adding agents to an agent group using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Agent Groups**.
- 3. In the ACD field, enter the ACD or ACD Group on which the agent group exists.
- 4. Click OK.

CMS Supervisor displays the Dictionary Agent Groups window.

- 5. In the **Agent group name** field, enter the name of the agent group to which you want to add agents.
- 6. From the Actions menu, select Get contents.

CMS Supervisor displays the Dictionary ACD Groups Get contents window.

- 7. Enter the Login IDs that you want to add to this group. You can add up to 32 agents at a time.
- 8. From the Actions menu, select Add.

# Deleting agents from an agent group using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Agent Groups**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which the agent group exists.
- 4. Click **OK**.

CMS Supervisor displays the Dictionary Agent Groups window.

- 5. In the **Agent group name** field, enter the name of the agent group from which you want to delete agents.
- 6. From the **Actions** menu, select **Get contents**.

CMS Supervisor displays the Agent Groups-Get Contents window.

- 7. Enter the Login IDs to delete from this group. You can delete up to 32 agents at a time.
- 8. From the **Actions** menu, select **Delete**.

# About administering agent string values in the Dictionary

Agent string values are the descriptive words in reports that correspond with agent states. These words, such as ACD, ACW, or AUX, describe the value of the data. Strings are changed to the values you administer when these strings are displayed as data in a report. The report heading is not affected.

# Permissions required to administer agent string values

Depending on the procedure that you want to perform, you need the following permissions:

- To change agent string values, you need "write" permissions for the Dictionary subsystem.
- To view agent string values, you need "read" permissions for the Dictionary subsystem.

# Modifying agent string value descriptions using the Web Client Procedure

1. Navigate to Administration > Dictionary > Agent String Values.

CMS Supervisor displays the list of agent string values administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to change agent string values.

CMS Supervisor displays the list of agent string values administered for the selected ACD.

3. Enter a new descriptive word in the fields that you want to change.

See Agent string value field descriptions on page 60 for field descriptions.

- 4. Do one of the following actions:
  - Click **Apply** to commit the change.
  - Click **Reset** to reset the values of the fields.

If you clicked **Apply**, CMS Supervisor displays a confirmation message. If you clicked **Reset**, the fields reset to the previous values.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Modifying agent string value descriptions using the PC Client Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Agent String Values**.
- 3. In the **ACD** field, select the ACD or ACD Group that you want to change.
- 4. Click OK.

CMS Supervisor displays the Dictionary Agent String Values window.

5. Enter a new descriptive word in the fields that you want to change.

See Agent string value field descriptions on page 60 for field descriptions.

6. Click Actions > Modify.

CMS Supervisor saves the changed agent string values.

# Agent string value field descriptions

Name	Description
Work Mode	ACD: The agent is on an ACD call.
	ACW: The agent is in the after-call work mode.
	AUX: The agent is in the auxiliary work mode.
	AVAIL: The agent is available to take an ACD call.
	DACD: The agent is on a direct agent ACD call.
	• <b>DACW</b> : The agent is in the after-call work mode for a direct agent ACD call.
	• <b>OTHER</b> : The agent has just logged in and CMS has not yet been notified of the agent's state, or the agent is dialing for an extension call while in auto-in/manual-in (AI/MI), or the agent is in AI/MI and has an extension call ringing, or the agent has put a call on hold and has taken no further call-related action.
	• <b>RINGING</b> : An ACD call is ringing at the agent's voice terminal and the agent is not doing anything else.
	UNKNOWN: CMS does not recognize the current state.
	• UNSTAFF: The agent is not logged in, or is not staffed yet.

Table continues...

Name	Description	
Agent Trace Work	LOGON: An agent is logged in.	
Mode	• LOGOFF: An agent is logged out and is not available to take ACD calls.	
Call Direction	• IN: The agent is on an incoming call.	
	OUT: The agent is on an outbound call.	
Call Origination	• <b>PHONE</b> : The agent dialed an outbound call using the voice terminal dial pad.	
	• <b>KEYBOARD</b> : The agent dialed an outbound call using the computer keyboard.	
Call Destination	PBX: Internal to the switch.	
	Off: External to the switch.	
Reserve Level	• <b>Rsv1</b> : The agent begins answering calls when the skill's first threshold is crossed.	
	<ul> <li>Rsv2: The agent begins answering calls when the skill's second threshold is crossed.</li> </ul>	
Call Handling	LEVEL: The agent's call-handling preference is by skill level.	
Preference	<ul> <li>NEED: The agent's call-handling preference is by greatest need.</li> </ul>	
	<ul> <li>PERCENT: The agent's call-handling preference is based on an assigned percentage of time allocated to each skill.</li> </ul>	
Agent Role	• <b>TOP</b> : The agent can be counted on to answer the skill's calls, unless an agent's other skills go into overload.	
	ALLOCATED: The agent has time allocated to answering the skill's calls.	
	<ul> <li>BACKUP: The agent helps answer the skill's calls when his/her top skill is not busy.</li> </ul>	
	• <b>ROVING</b> : The agent answers a skill's calls when this skill has the greatest need.	
	<ul> <li>RESERVE: The agent helps answer the skill's calls when the skill is over threshold. These roles vary according to call-handling preference.</li> </ul>	
Interrupt Type	• <b>NA</b> : Not interruptible when the agent is in AUX.	
	AUTO-IN: Auto in interrupt.	
	MANUAL-IN: Manual in interrupt.	
	<ul> <li>NOTIFY: Agent is notified of the interrupt and can choose whether to accept of reject the interrupt.</li> </ul>	
Interrupt Status	NA: The agent is not in the interruptible AUX state.	
	<ul> <li>NOTIFYING: The agent is being notified of an interrupt while in the interruptible AUX state.</li> </ul>	
	<ul> <li>INTRRPTED: The agent is interrupted in the interruptible AUX state and is handling a call.</li> </ul>	
	• <b>INTRRPTBLE</b> : The agent is in the interruptible AUX state.	

# About administering announcement names in the Dictionary

This section provides information on working with announcement names in the Dictionary. Announcements are recorded messages that are played for callers. Announcement names are synonyms assigned to these recorded messages in the Dictionary.

# Permissions required to administer announcement names

Depending on the procedure that you want to perform, you need the following permissions:

- To view announcement names, you need "read" permissions for the Dictionary subsystem.
- To add, delete, or change announcement names, you need "write" permissions for the Dictionary subsystem.

### Before administering announcement names

Read and understand the following items before administering announcement names in the Dictionary:

- Use unique announcement names.
- Do not use multiple values for announcement names or numbers.

# Viewing an announcement name using the Web Client Procedure

1. Navigate to Administration > Dictionary > Announcements.

CMS Supervisor displays the list of announcement names administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to view announcement names.

CMS Supervisor displays the list of announcement names administered for the selected ACD.

### Adding an announcement name using the Web Client Procedure

#### 1. Navigate to Administration > Dictionary > Announcements.

CMS Supervisor displays the list of announcement names administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer announcement names.

CMS Supervisor displays the list of announcement names administered for the selected ACD.

3. Click Add Announcement.

CMS Supervisor displays the Add Announcement window.

- 4. Administer the following options:
  - In the Announcement Extension field, enter a 3-7 digit extension number.
  - In the **Announcement Name** field, enter the name of the announcement. The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.
  - In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

### Modifying an announcement name using the Web Client Procedure

1. Navigate to Administration > Dictionary > Announcements.

CMS Supervisor displays the list of announcement names administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer announcement names.

CMS Supervisor displays the list of announcement names administered for the selected ACD.

3. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The **Announcement Extension** field is a display-only field. You cannot change the extension number.

- In the **Announcement Name** field, enter the name of the announcement. The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.
- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

### Deleting an announcement name using the Web Client Procedure

1. Navigate to Administration > Dictionary > Announcements.

CMS Supervisor displays the list of announcement names administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer announcement names.

CMS Supervisor displays the list of announcement names administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

### Viewing an announcement name using the PC Client Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Announcements**.
- 3. In the **ACD** field, enter the ACD on which the announcement resides.

#### 4. Click OK.

CMS Supervisor displays the Dictionary Announcements window.

- 5. To find an announcement name to view, only one of the fields requires that you specify an announcement. Perform one of the following actions to specify an announcement in the Dictionary:
  - In the Announcement Name field, enter the synonym name of the announcement.
  - In the Announcement Number field, enter the number of the announcement.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the data for the specified announcement, if valid.

# Listing all announcement names for an ACD using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Announcements**.
- 3. In the **ACD** field, enter the ACD on which the announcement resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Announcements window.

5. From the **Actions** menu, select **List all**.

### Adding an announcement name using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Announcements**.
- 3. In the ACD field, enter the ACD on which the announcement resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Announcements window.

- 5. In the **Announcement Name** field, enter the name that you want to assign to the announcement.
- 6. In the **Announcement Number** field, enter a number that corresponds with the announcement name.

You can enter any other information about the announcement in the **Description** field. You can enter only 50 or fewer characters in this field.

7. From the Actions menu, select Add.

# Modifying an announcement name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Announcements.
- 3. In the **ACD** field, enter the ACD on which the announcement resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Announcements window.

- 5. To find an announcement name to change , you must specify an announcement in only one of the fields. Perform one of the following actions to specify an announcement in the Dictionary:
  - In the Announcement Name field, enter the name of the announcement.
  - In the Announcement Number field, enter the number of the announcement.
- 6. From the Actions menu, select Find one.

Supervisor retrieves and displays the data for the specified announcement, if valid.

- 7. In the Announcement Name field, enter the new announcement name.
- 8. From the Actions menu, select Modify.

### Deleting an announcement name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Announcements**.
- 3. In the **ACD** field, enter the ACD on which the announcement resides.
- 4. Click **OK**.

CMS Supervisor displays the Dictionary Announcements window.

- 5. To find an announcement name to delete, you must specify an announcement in only one of the fields. Perform one of the following actions to specify an announcement in the Dictionary:
  - In the Announcement Name field, enter the name of the announcement.
  - In the Announcement Number field, enter the number of the announcement.
- 6. From the Actions menu, select Find one.

Supervisor retrieves and displays the data for the specified announcement, if valid.

7. From the **Actions** menu, select **Delete**.

# About administering AUX reason code names in the Dictionary

This section provides information on working with AUX reason code names in the Dictionary. AUX reason codes help a call center to track an agent's time more precisely when the agent is in the AUX work mode. The agent can specify exactly why the AUX state is used, such as for lunch or meetings. You can view, add, delete, or change AUX reason code names by selecting **AUX Reason Codes** from the **Dictionary** menu.

Complete the AUX Reason Codes window if you want the names that are associated with your AUX reason codes to appear in the AUX Reasons Code standard real-time and historical reports.

# Permissions required to administer AUX reason code names

Depending on the procedure that you want to perform, you need the following permissions:

- To view AUX reason codes, you need "read" permissions for the Dictionary subsystem.
- To add, delete, or change AUX reason codes, you need "write" permissions for the Dictionary subsystem.

### Before administering AUX reason code names

Read and understand the following items before administering AUX reason code names in the Dictionary:

- To use AUX reason codes, your switch must have EAS.
- AUX reason codes are digits 0 through 99.
- AUX reason code names can be up to 20 characters long.
- AUX reason code 0 is used for cases in which the switch automatically puts an agent into AUX work mode. You can change this name.

- Names must be unique within an ACD. No two AUX reason codes in the same ACD can have the same name.
- If you make changes to the AUX reason code names, you must restart any report that uses AUX reason codes to see the changes.

# Viewing an AUX reason code name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > AUX Reason Codes.

CMS Supervisor displays the list of AUX reason code names administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer AUX reason code names.

CMS Supervisor displays the list of AUX reason code names administered for the selected ACD.

# Adding an AUX reason code name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > AUX Reason Codes.

CMS Supervisor displays the list of AUX reason code names administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer AUX reason code names.

CMS Supervisor displays the list of AUX reason code names administered for the selected ACD.

3. Click Add AUX Reason Code.

CMS Supervisor displays the Add AUX Reason Code window.

- 4. Administer the following options:
  - In the AUX Reason Code field, enter a value between 0-99.
  - In the **AUX Reason Code Name** field, enter the name of the AUX reason code. The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.
  - In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying an AUX reason code name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > AUX Reason Codes.

CMS Supervisor displays the list of AUX reason code names administered for the current ACD.

 In the Current ACD drop-down list, select the active ACD for which you want to administer AUX reason code names.

CMS Supervisor displays the list of AUX reason code names administered for the selected ACD.

3. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The AUX Reason Code field is a display-only field.
  - In the **AUX Reason Code Name** field, enter the name of the AUX reason code. The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.
  - In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

### Deleting an AUX reason code name using the Web Client Procedure

### 1. Navigate to Administration > Dictionary > AUX Reason Codes.

CMS Supervisor displays the list of AUX reason code names administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer AUX reason code names.

CMS Supervisor displays the list of AUX reason code names administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing an AUX reason code name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **AUX Reason Codes**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which the AUX Reason Codes reside.
- 4. Click OK.

CMS Supervisor displays the Dictionary AUX Reason Codes window.

- 5. To find an AUX reason code name to view, only one of the fields requires that you specify an AUX reason code . Perform one of the following actions to specify an AUX reason code in the Dictionary:
  - In the AUX Reason Code Name field, enter the name for the AUX reason code.
  - In the AUX Reason Code field, enter an AUX reason code number from 0 to 99.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified AUX reason code, if valid.

# Listing all AUX reason code names using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight AUX Reason Codes.
- 3. In the ACD field, enter the ACD or ACD Group on which the AUX Reason Codes reside.
- 4. Click **OK**.

CMS Supervisor displays the Dictionary AUX Reason Codes window.

5. From the **Actions** menu, select **List all**.

CMS Supervisor displays the Dictionary AUX Reason Codes — List All window.

# Adding an AUX reason code name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **AUX Reason Codes**.
- 3. In the ACD field, enter the ACD or ACD Group on which the AUX Reason Codes reside.
- 4. Click OK.

CMS Supervisor displays the Dictionary AUX Reason Codes window.

- 5. In the AUX Reason Code Name field, enter the name for the AUX reason code.
- 6. In the AUX Reason Code field, enter an AUX reason code number from 0 to 99.

You can enter any other information about the AUX reason code in the **Description** field. You can enter only 50 or fewer characters in this field.

7. From the Actions menu, select Add

# Modifying an AUX reason code name using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **AUX Reason Codes**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which the AUX Reason Codes reside.
- 4. Click OK.

CMS Supervisor displays the Dictionary AUX Reason Codes window.

- 5. To find an AUX reason code name to modify, only one of the fields requires an AUX reason code name to be specified. Perform one of the following actions to specify an existing AUX reason code name in the Dictionary:
  - In the AUX Reason Code Name field, enter the name for the AUX reason code.
  - In the AUX Reason Code field, enter an AUX reason code number from 0 to 99.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified AUX reason code, if valid.

- 7. In the AUX Reason Code Name field, enter the new name for the AUX reason code.
- 8. From the Actions menu, select Modify.

CMS Supervisor updates the name for the AUX reason code in the database.

# Deleting an AUX reason code name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **AUX Reason Codes**.
- 3. In the ACD field, enter the ACD or ACD Group on which the AUX Reason Codes reside.
- 4. Click OK.

CMS Supervisor displays the Dictionary AUX Reason Codes window.

- 5. To find an AUX reason code name to delete, you must specify an AUX reason code in only one of the fields. Perform one of the following actions to specify an AUX reason code in the Dictionary:
  - In the AUX Reason Code Name field, enter the name for the AUX reason code.
  - In the AUX Reason Code field, enter an AUX reason code number from 0 to 99.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified AUX reason code, if valid.

7. From the Actions menu, select Delete.

CMS Supervisor removes the specified AUX reason code from the Dictionary.

# About administering calculations in the Dictionary

Calculation names are abbreviated names for the calculations in the database that are used to create reports. You can view standard calculations or create your own custom calculations to use in custom reports. The names for calculations used in standard reports already exist in the Dictionary.

# Permissions required to administer calculations

Depending on the procedure that you want to perform, you need the following permissions:

- To view calculation names, you need "read" permissions for the Dictionary subsystem.
- To create, delete or change a custom calculation name, you need "write" permissions for the Dictionary subsystem.

# Before administering calculations

Read and understand the following items before changing calculation names in the Dictionary:

- Calculation names must be one word with no blanks.
- Reports do not run if you embed calculations more than three levels deep.
- You cannot delete standard calculation names.

The standard CMS calculation names are listed in the following documents:

- Avaya Call Management System Database Items and Calculations
- Avaya CMS Supervisor Report Designer
- Avaya CMS Supervisor Reports
- Avaya Call Management System Custom Reports
- Avaya recommends that you identify your own calculation names in all lowercase letters to distinguish those calculation names from the standard CMS Supervisor calculation names. The standard calculation names are in all uppercase letters.
- If you delete a custom calculation from the Dictionary, any reports that the calculation appeared in does not run.
- You can adversely affect standard reports if you change a standard CMS Supervisor calculation. Reports might run, but the results might be different than expected.
- Reports do not run if you create calculations that reference each other in a circular way. For example, assume that CALC\_1 uses CALC\_2 in processing. If CALC\_2 then uses CALC\_1 in processing, this creates a circular pattern where the processing cannot be completed.

## Viewing calculations using the Web Client Procedure

### Navigate to Administration > Dictionary > Calculations.

CMS Supervisor displays the list of calculation names administered for the system.

## Adding a custom calculation using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Calculations.

CMS Supervisor displays the list of calculations administered for the system.

2. Click Add Calculation.

CMS Supervisor displays the Add Calculation window.

- 3. Administer the following options:
  - In the **Calculation Name** field, enter a name for the new custom calculation. Use lowercase letters in the name to distinguish this custom calculations from a standard CMS calculation.
  - In the Calculations field, enter the formula for the calculation. Formulas can include:
    - Database items
    - Constants
    - Calculations. The maximum nesting level is 3.
    - The following arithmetic operators:
      - + (add)
      - - (subtract)
      - \* (multiply)
      - / (divide)
      - () (do first, as in standard mathematical operations)

### Important:

Calculations that refer to another calculation should enclose the referenced calculation within parentheses. For example, if calculation 1 (C1) is A + B + C, and calculation 2 (C2) is C1/D, you must enter calculation 2 as (C1)/D.

You can enter up to 70 characters in this field.

• In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).

4. Click OK to commit the operation. Click Cancel to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying a custom calculation using the Web Client

## About this task

## ▲ Caution:

Only modify custom calculations that you have created. Do not modify standard CMS calculations. If you change a standard CMS calculation, the meaning of that calculation changes in every report in which the calculation displays.

### Procedure

1. Navigate to Administration > Dictionary > Calculations.

CMS Supervisor displays the list of calculations administered for the system.

2. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 3. Administer the following options:
  - The Calculation Name field is a display-only field.
  - In the Calculations field, enter the formula for the calculation. Formulas can include:
    - Database items
    - Constants
    - Calculations. The maximum nesting level is 3.
    - The following arithmetic operators:
      - + (add)
      - - (subtract)
      - \* (multiply)
      - / (divide)
      - () (do first, as in standard mathematical operations)

## Important:

Calculations that refer to another calculation should enclose the referenced calculation within parentheses. For example, if calculation 1 (C1) is A + B + C, and calculation 2 (C2) is C1/D, you must enter calculation 2 as (C1)/D.

You can enter up to 70 characters in this field.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Deleting a custom calculation using the Web Client

## About this task

## ▲ Caution:

Only delete custom calculations that you have created. Do not delete standard CMS calculations. If you delete a standard CMS calculation, every report in which the calculation is used will be invalid.

## Procedure

1. Navigate to Administration > Dictionary > Calculations.

CMS Supervisor displays the list of calculations administered for the system.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

3. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

4. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing calculations using the PC Client

### Procedure

- From the Controller window, select Commands > Dictionary. CMS Supervisor displays the Dictionary window.
- 2. In the Operations list, highlight Calculations.
- 3. Click OK.

CMS Supervisor displays the Dictionary Calculations window.

- 4. To find a calculation to view, only one of the fields requires that you specify a calculation. Perform one of the following actions to specify an existing database calculation in the Dictionary:
  - If you know the name of the calculation, enter the calculation in the **Calculation Name** field.
  - If you do not know the name of the calculation, Leave all the fields in the Dictionary Calculations window blank, and from the **Actions** menu, select **Find one**. Use the **Next** or **Previous** buttons to move through the list of calculations.

# Listing all calculations using the PC Client Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Calculations**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Calculations window.

4. From the Actions menu, select List all.

# Adding a custom calculation using the PC Client

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Calculations**.
- 3. Click **OK**.

CMS Supervisor displays the Dictionary Calculations window.

4. Enter the name of the calculation in the **Calculation Name** field.



Use lowercase letters in the name to distinguish this custom calculations from a standard CMS calculation.

5. In the **Calculations** field, enter the formula for the calculation.

Formulas can include:

- Database items
- Constants

- Calculations. The maximum nesting level is 3.
- The following arithmetic operators:
  - + (add)
  - - (subtract)
  - \* (multiply)
  - / (divide)
  - () (do first, as in standard mathematical operations)

### Important:

Calculations that refer to another calculation should enclose the referenced calculation within parentheses. For example, if calculation 1 (C1) is A + B + C, and calculation 2 (C2) is C1/D, you must enter calculation 2 as (C1)/D.

You can add any other information about the calculation in the **Description** field. You can enter only 50 or fewer characters in this field.

6. From the Actions menu, select Add.

The custom calculation is added to the Dictionary.

## Modifying a custom calculation using the PC Client

#### About this task

### ▲ Caution:

Only modify custom calculations that you have created. Do not modify standard CMS calculations. If you change a standard CMS calculation, the meaning of that calculation changes in every report in which the calculation displays.

#### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Calculations.
- 3. Click OK.

CMS Supervisor displays the Dictionary Calculations window.

- 4. Enter the name of the custom calculation in the Calculation Name field.
- 5. From the Actions menu, select Find one.
- 6. In the **Calculation** field, enter the new formula.

Enter any changes to the descriptive information in the **Description** field.

7. From the Actions menu, select Modify.

# **Deleting a custom calculation using the PC Client**

## About this task

## ▲ Caution:

Only delete custom calculations that you have created. Do not delete standard CMS calculations. If you delete a standard CMS calculation, every report in which the calculation is used will be invalid.

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Calculations**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Calculations window.

- 4. Enter the name of the custom calculation in the Calculation Name field.
- 5. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified calculation, if valid.

6. From the **Actions** menu, select **Delete**.

The specified calculation is removed from the Dictionary.

# About administering call work codes in the Dictionary

Call work codes are numeric sequences that agents enter to categorize the call that the agents have received or are handling. By entering call work codes, agents can assign one of many defined categories to the calls which can be later viewed in detail through reports. The call work codes are defined in the Dictionary and can represent any type of call that are tracked. These calls include complaints, special sales, and promotional events, . You can assign up to five call work codes to each call. You can view, add, delete, or change call work codes and the names from the Call Work Codes window. These names then appear in the standard Call Work Code historical report.

## Permissions required to administer call work codes

Depending on the procedure that you want to perform, you need the following permissions:

• To view call work code names, you need "read" permissions for the Dictionary subsystem.

• To add, delete or change call work code names, you need "write" permissions for the Dictionary subsystem.

# Before using call work codes

Read and understand the following items before changing call work codes in the Dictionary:

- Call work codes must be activated on the ACD before the administration and naming of the codes can be performed.
- Call work codes require storage space on the CMS file system. You must configure the number of call work codes available on a system through the Data Storage Allocation window. See <u>Chapter 11: Configuring CMS system settings</u> on page 320 for more information.
- Call Work Code 0 is reserved for unadministered work codes so that summary data can be collected. The default name for Call Work Code 0 is Unadministered codes, but this name can be changed.
- Even if call work codes can be up to 16 digits long, a Dictionary name can only be assigned to a call work code that is 9 digits long.
- Tenant users must have permissions for the Call Work Codes they wish to add/delete/modify.

# Viewing a call work code name using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Call Work Code.

CMS Supervisor displays the list of call work codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer call work codes.

CMS Supervisor displays the list of call work codes administered for the selected ACD.

# Adding a name to a call work code using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Call Work Code.

CMS Supervisor displays the list of call work codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer call work codes.

CMS Supervisor displays the list of call work codes administered for the selected ACD.

3. Click Add Call Work Code.

CMS Supervisor displays the Add Call Work Code window.

- 4. Administer the following options:
  - In the Call Work Code field, enter a 1-16 digit number.
  - In the **Call Work Code Name** field, enter the name you want to use to represent the call work code.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

# Modifying a call work code name using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Call Work Code.

CMS Supervisor displays the list of call work codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer call work codes.

CMS Supervisor displays the list of call work codes administered for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The Call Work Code field is a display-only field.
  - In the **Call Work Code Name** field, enter the name you want to use to represent the call work code.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting a call work code name using the Web Client Procedure

1. Navigate to Administration > Dictionary > Call Work Code.

CMS Supervisor displays the list of call work codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer call work codes.

CMS Supervisor displays the list of call work codes administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Viewing a call work code name using the PC Client

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Call Work Code**.
- 3. In the **ACD** field, enter the ACD on which the call work code resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Call Work Codes window.

- 5. To find a call work code name to view, only one of the fields requires that you specify a call work code. Perform one of the following actions to specify a call work code in the Dictionary:
  - In the Call Work Code Name field, enter the name of the call work code.
  - In the Call work code field, enter the number of the of the call work code.
- 6. From the Call Work Code Name menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified call work code, if valid.

# Listing all call work code names using the PC Client

## Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Call Work Code**.
- 3. In the **ACD** field, enter the ACD on which the call work code resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Call Work Codes window.

5. From the **Actions** menu, select **List all**.

# Adding a name to a call work code using the PC Client Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Call Work Code**.
- 3. In the **ACD** field, enter the ACD on which the call work code resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Call Work Codes window.

- 5. In the Call Work Code Name field, enter the name of the of the new call work code.
- 6. In the **Call work code** field, enter the number of the of the new call work code.
- 7. From the Actions menu, select Add.

The specified call work code and the associated name is added to the Dictionary.

# Modifying a call work code name using the PC Client

## Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Call Work Code**.

- 3. In the **ACD** field, enter the ACD on which the call work code resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Call Work Codes window.

- 5. To find a call work code name to change , only one of the fields requires that you specify a call work code. Perform one of the following actions to specify a call work code in the Dictionary:
  - In the Call Work Code Name field, enter the name of the call work code.
  - In the Call work code field, enter the number of the of the call work code.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified call work code, if valid.

- 7. In the Call Work Code Name field, enter the new name of the call work code.
- 8. From the **Actions** menu, select **Modify**.

The specified call work code entry is changed in the Dictionary.

## Deleting a call work code name using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Call Work Code.
- 3. In the **ACD** field, enter the ACD on which the call work code resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Call Work Codes window.

- 5. To find a call work code name to delete, only one of the fields requires that you specify a call work code. Perform one of the following actions to specify a call work code in the Dictionary:
  - In the Call Work Code Name field, enter the name of the of the call work code.
  - In the Call work code field, enter the number of the of the call work code.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified call work code, if valid.

7. From the Actions menu, select Delete.

The specified call work code is removed from the Dictionary.

# About administering constants in the Dictionary

Constants are items with fixed numeric values that you can enter into the Dictionary for use only in custom and designer reports. Constants do not exist in CMS when CMS is installed.

# Permissions required to administer constants

Depending on the procedure that you want to perform, you need the following permissions:

- To view a constant, you need "read" permissions for the Dictionary subsystem.
- To add, delete or change a constant, you need "write" permissions for the Dictionary subsystem.

# Viewing a constant using the Web Client

## Procedure

Navigate to Administration > Dictionary > Constants.

CMS Supervisor displays the list of constants administered for the system.

# Adding a constant using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Constants.

CMS Supervisor displays the list of constants administered for the system.

2. Click Add Constant.

CMS Supervisor displays the Add Constant window.

- 3. Administer the following options:
  - In the **Constant Name** field, enter the name of the constant.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Value** field, enter the value for the constant. The value can range from -99999 to 999999.
- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying a constant using the Web Client

## Procedure

1. Navigate to **Administration > Dictionary > Constants**.

CMS Supervisor displays the list of constants administered for the system.

2. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 3. Administer the following options:
  - The Constant Name field is a display-only field.
  - In the **Value** field, enter the value for the constant. The value can range from -99999 to 999999.
  - In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Deleting a constant using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Constants.

CMS Supervisor displays the list of constants administered for the system.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

3. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

4. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing a constant using the PC Client

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Constants**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Constants window.

- 4. To find a constant to view, only one of the fields requires that you specify an entry. Perform one of the following actions to specify a constant in the Dictionary:
  - In the Constant Name field, enter the name of the constant.
  - In the Value field, enter the numeric value of the constant.
- 5. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified constant, if valid.

# Listing all constants using the PC Client

## Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Constants**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Constants window.

4. From the Actions menu, select List all.

# Adding a constant using the PC Client

## Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Constants**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Constants window.

- 4. In the **Constant Name** field, enter the name of the new constant.
- 5. In the **Value** field, enter the numeric value of the constant. The value can range from -99999 to 999999.

You can enter any other information about the constant in the **Description** field. You can enter only 50 or fewer characters in this field.

6. From the **Actions** menu, select **Add**.

# Modifying a constant using the PC Client

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Constants**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Constants window.

- 4. To find a constant to change, only one of the fields requires that you specify an entry. Perform one of the following actions to specify a constant in the Dictionary:
  - In the Constant Name field, enter the name of the constant.
  - In the Value field, enter the numeric value of the constant.
- 5. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified constant, if valid.

6. In the Value field, enter the new numeric value for the constant.

#### 😵 Note:

You cannot change the name of the new constant. If you want to change the name, you must delete the old constant and add a new one.

7. From the Actions menu, select Modify.

## Deleting a constant using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Constants**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Constants window.

- 4. To find a constant to delete, only one of the fields requires that you specify an entry. Perform one of the following actions to specify a constant in the Dictionary:
  - In the Constant Name field, enter the name of the constant.
  - In the Value field, enter the numeric value of the constant.
- 5. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified constant, if valid.

6. From the **Actions** menu, select **Delete**.

The specified constant is removed from the Dictionary.

# About administering custom database items in the Dictionary

You can define your own custom database items, which are stored in the CMS database. You can enter the custom database items from the Custom Items or Dictionary Custom Items window. These items allow you to combine your own data with the CMS data on custom or designer reports. You can also change or delete custom database items.

# Permissions required to administer custom database items

Depending on the procedure that you want to perform, you need the following permissions:

- To view a custom database item, you need "read" permissions for the Dictionary subsystem.
- To add, delete, or change a custom database item, you need "write" permissions for the Dictionary subsystem.

## Before using custom database items

Read and understand the following items before working with custom database items in the Dictionary:

• You must first create the table in the database before you create a custom database item.

# Viewing a custom database item using the Web Client Procedure

Navigate to Administration > Dictionary > Custom Items.

CMS Supervisor displays the list of custom database items administered for the system.

# Adding a custom database item using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Custom Items.

CMS Supervisor displays the list of custom database items administered for the system.

2. Click Add Custom Database Item.

CMS Supervisor displays the Add Custom Database Item window.

- 3. Administer the following options:
  - In the **Database Item** field, enter the name of the database item. You can enter up to 18 characters in this field.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Table** field, enter the name of the table that contains the new custom database item. You can enter up to 18 characters in this field.
- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying a custom database item using the Web Client Procedure

1. Navigate to Administration > Dictionary > Custom Items.

CMS Supervisor displays the list of custom database items administered for the system.

2. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 3. Administer the following options:
  - The **Database Item** field is a display-only field.

## 😵 Note:

You cannot change the name of a custom database item. You must delete the old item and add the new item if you want a different name.

- In the **Table** field, enter the name of the table that contains the new custom database item. You can enter up to 18 characters in this field.
- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Deleting a custom database item using the Web Client Procedure

1. Navigate to Administration > Dictionary > Custom Items.

CMS Supervisor displays the list of custom database items administered for the system.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

3. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

4. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing a custom database item using the PC Client

## Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Custom Items**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Custom Items window.

4. In the **Database Item** field, enter the name of the custom database item.

5. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified custom database item, if valid.

Listing all custom database items using the PC Client

## Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Custom Items**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Custom Items window.

- 4. In the **Database Item** field, enter the name of the custom database item.
- 5. From the **Actions** menu, select **List all**.

# Adding a custom database item using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Custom Items**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Custom Items window.

4. In the Database Item field, enter the name of the new database item.

You can enter any other information about the custom database item in the **Description** field. Only 50 or fewer characters can be entered in this field.

- 5. In the Table field, enter the name of the table that contains the new custom database item.
- 6. From the **Actions** menu, select **Add**.

# Modifying a custom database item using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Custom Items**.
- 3. Click **OK**.

CMS Supervisor displays the Dictionary Custom Items window.

- 4. In the **Database Item** field, enter the new name for the custom database item.
- 5. In the **Table** and **Description** fields, enter the new information for the custom database item.

You can enter only 50 or fewer characters in the **Description** field.

😵 Note:

You cannot change the name of a custom database item. You must delete the old item and add the new item if you want a different name.

6. From the Actions menu, select Modify.

The specified custom database item and the changes are saved to the Dictionary.

# Deleting a custom database item using the PC Client

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Custom Items**.
- 3. Click OK.

CMS Supervisor displays the Dictionary Custom Items window.

- 4. In the **Database Item** field, enter the name of the database item to delete.
- 5. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified custom database item, if valid.

6. From the Actions menu, select Delete.

The specified custom database item is removed from the Dictionary.

# About administering generic string value synonyms in the Dictionary

Changing generic string values enables you to enter a replacement string for the default  $_{\rm Y}$  for YES and n for NO values. The string values can be up to six characters long. These modified string values appear in custom or designer reports that use the YES or NO synonyms.

# Permissions required to administer generic string value synonyms

Depending on the procedure that you want to perform, you need the following permissions:

- To view generic string values, you need "read" permissions for the Dictionary subsystem.
- To change generic string values, you need "write" permissions for the Dictionary subsystem.

# Viewing generic string values using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Generic String Values.

CMS Supervisor displays the list of generic string values administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer generic string values.

CMS Supervisor displays the list of generic string values administered for the selected ACD.

# Modifying generic string values using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Generic String Values.

CMS Supervisor displays the list of generic string values administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer generic string values.

CMS Supervisor displays the list of generic string values administered for the selected ACD.

3. Administer new string values for the YES and NO synonyms.

- 4. Do one of the following actions:
  - Click **Apply** to commit the change.
  - Click **Reset** to reset the values of the fields.

If you clicked **Apply**, CMS Supervisor displays a confirmation message. If you clicked **Reset**, the fields reset to the previous values.

5. Click OK.

CMS Supervisor displays an updated list of items.

## Viewing generic string values using the PC Client Procedure

1. From the Controller window, select **Commands> Dictionary**.

CMS Supervisor displays the Dictionarywindow.

- 2. In the **Operations** list, highlight **Generic String Values**.
- 3. In the ACD field, enter the ACD or ACD Group on which the generic string values reside.
- 4. Select OK.

CMS Supervisor displays the Dictionary Generic String Valueswindow.

# Modifying generic string values using the PC Client

### Procedure

1. From the Controller window, select **Commands**> **Dictionary**.

CMS Supervisor displays the Dictionarywindow.

- 2. In the **Operations** list, highlight **Generic String Values**.
- 3. In the ACD field, enter the ACD or ACD Group on which the generic string values reside.
- 4. Select OK.

CMS Supervisor displays the Dictionary Generic String Valueswindow.

- 5. In the **YES** field, enter up to six characters.
- 6. In the **NO** field, enter up to six characters.

The characters entered in the **YES** and **NO** fields displays in reports that use YES and NO fields.

7. From the **Actions** menu, select **Modify**.

# About administering location IDs in the Dictionary

Location IDs represent the location or site where an agent sits or the port network to which a trunk is assigned. You can name location IDs for ease of identification in reporting for multisite environments. The same location IDs and the synonyms are used for both agents and trunks.

# Permissions required to administer location IDs

Depending on the procedure that you want to perform, you need the following permissions:

- To view the name of a location ID, you need "read" permissions for the Dictionary subsystem.
- To add, delete, or change the name of a location ID, you need "write" permissions for the Dictionary subsystem.

# Viewing a location ID using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Location IDs.

CMS Supervisor displays the list of location IDs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer location IDs.

CMS Supervisor displays the list of location IDs administered for the selected ACD.

# Adding a location ID using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Location IDs.

CMS Supervisor displays the list of custom database items administered for the current ACD.

 In the Current ACD drop-down list, select the active ACD for which you want to administer location IDs.

CMS Supervisor displays the list of location IDs administered for the selected ACD.

3. Click Add Location ID.

CMS Supervisor displays the Add Location ID window.

- 4. Administer the following options:
  - In the Location ID field, enter a number from 1-250.
  - In the Location Name field, enter the name you want to use to represent the location.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying a location ID using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Location IDs.

CMS Supervisor displays the list of custom database items administered for the current ACD.

 In the Current ACD drop-down list, select the active ACD for which you want to administer location IDs.

CMS Supervisor displays the list of location IDs administered for the selected ACD.

3. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The Location ID field is a display-only field.
  - In the **Location Name** field, enter the name you want to use to represent the location. The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.
  - In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting a location ID using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Location IDs.

CMS Supervisor displays the list of custom database items administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer location IDs.

CMS Supervisor displays the list of location IDs administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Viewing a location ID using the PC Client

## Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Location IDs**.
- 3. In the **ACD** field, enter the ACD on which the location ID resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Location IDs window.

- 5. To find a location ID to view, only one of the fields requires that you specify a value. Perform one of the following actions to specify a location ID in the Dictionary:
  - In the Location Name field, enter the name of the location.
  - In the Location ID field, enter the number of the location.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified location ID, if valid.

## Listing all location IDs using the PC Client Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Location IDs**.
- 3. In the **ACD** field, enter the ACD on which the location ID resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Location IDs window.

5. From the Actions menu, select List all.

# Adding a location ID using the PC Client

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Location IDs**.
- 3. In the **ACD**field, enter the ACD on which you want to add the location ID.
- 4. Click OK.

CMS Supervisor displays the Dictionary Location IDs window.

- 5. In the Location Name field, enter the name of the new location.
- 6. In the Location ID field, enter the number from 1-250 for the new location.

You can enter any other information about the location ID in the **Description**field. You can enter only 50 or fewer characters in this field.

7. From the Actions menu, select Add.

# Modifying a location ID using the PC Client

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Location IDs**.
- 3. In the **ACD** field, enter the ACD on which the location ID resides.

4. Click OK.

CMS Supervisor displays the Dictionary Location IDs window.

- 5. To find a location ID to change, only one of the fields requires that you specify a value. Perform one of the following actions to specify a location ID in the Dictionary:
  - In the Location Name field, enter the name of the location.
  - In the Location ID field, enter the number of the location.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified location ID, if valid.

- 7. In the Location Name field, enter the new name for the location.
- 8. From the Actions menu, select Add.

# **Deleting a location ID using the PC Client**

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Location IDs**.
- 3. In the **ACD** field, enter the ACD on which the location ID resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Location IDs window.

- 5. To find a location ID to delete, only one of the fields requires a value to be specified. Perform one of the following actions to specify a location ID in the Dictionary:
  - In the Location Name field, enter the name of the location.
  - In the Location ID field, enter the number of the location.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified location ID.

7. From the Actions menu, select Delete.

The specified location ID is removed from the Dictionary.

# About administering login ID names in the Dictionary

CMS uses agent login IDs to identify measured ACD agents. After an agent's name is assigned to a login ID, CMS windows and reports show the agent's login ID name instead of the login ID number.

You do not have to include agent names in the Dictionary, but CMS administration windows and reports are easier to understand with agent names instead of login IDs. Depending on the amount of space in the report, agent names can be truncated.

# Permissions required to administer login ID names

Depending on the procedure that you want to perform, you need the following permissions:

- To view login IDs, you need "read" permissions for the Dictionary subsystem.
- To add, delete, or change login IDs, you need "write" permissions for the Dictionary subsystem.

# Before using login ID names

The following items should be read and understood before working with login ID names in the Dictionary:

- Login ID names are sorted alphabetically in the Dictionary based on the first character that you input in the Agent Name field. For example, if the agent is listed as "Jane Brown", CMS sorts on the "J" for Jane. If the agent is listed as "Brown, Jane" sorts on the "B" in Brown. CMS Supervisor reports do not automatically sort by agent name, but the user can request the report to do so.
- You can assign no more than one agent name to the same login ID.
- You cannot assign the same agent name to multiple login IDs.
- You can use only numbers in login IDs.
- If you are viewing a real-time report when a change is made to a login ID that appears on that report, you must exit the report and rerun it to see the change.
- Tenant users must have permissions for the agent LOGID which they want to add/delete/ modify.

# Viewing a login ID name using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Login IDs.

CMS Supervisor displays the list of login IDs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer login IDs.

CMS Supervisor displays the list of login IDs administered for the selected ACD.

# Adding a name to a login ID using the Web Client Procedure

1. Navigate to Administration > Dictionary > Login IDs.

CMS Supervisor displays the list of login IDs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer login IDs.

CMS Supervisor displays the list of login IDs administered for the selected ACD.

3. Click Add Login ID.

CMS Supervisor displays the Add Login ID window.

- 4. Administer the following options:
  - In the Login ID field, enter a 3-13 digit numeric ID for the new agent name.
  - In the Agent Name field, enter an 8-20 character agent name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

## Modifying a login ID name using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Login IDs.

CMS Supervisor displays the list of login IDs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer login IDs.

CMS Supervisor displays the list of login IDs administered for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The Login ID field is a display-only field.
  - In the Agent Name field, enter an 8-20 character agent name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting a login ID name using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Login IDs.

CMS Supervisor displays the list of login IDs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer login IDs.

CMS Supervisor displays the list of login IDs administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Adding a name to a login ID using the PC Client

## Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Login identification**.

- 3. In the **ACD** field, enter the ACD or ACD Group on which you want to view a login ID name.
- 4. Click OK.

CMS Supervisor displays the Dictionary Login Identifications window.

- 5. To find a login ID to view, only one of the fields requires that you specify a value. Perform one of the following actions to specify a login ID in the Dictionary:
  - In the Login ID field, enter the number of the login ID.
  - In the Agent Name field, enter the name of the agent.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified login ID name, if valid.

# Listing all login ID names using the PC Client

### Procedure

- From the Controller window, select Commands > Dictionary. CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Login identification**.
- 3. In the ACD field, enter the ACD or ACD Group in which you want to list all login ID names.
- 4. Click OK.

CMS Supervisor displays the Dictionary Login Identifications window.

5. From the Actions menu, select List all.

# Adding a name to a login ID using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Login identification**.
- 3. In the **ACD**field, enter the ACD or ACD Group to which you want to assign a name to a login ID.
- 4. Click OK.

CMS Supervisor displays the Dictionary Login Identifications window.

5. In the **Login ID** field, enter the number of the login ID to which you want to assign a new name.

- 6. In the **Agent Name** field, enter the name of the agent that you want to associate with the Login ID number.
- 7. From the **Actions** menu, select **Add**.

# Modifying a login ID name using the PC Client

## Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Login identification**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which you want to modify a login ID name.
- 4. Click OK.

CMS Supervisor displays the Dictionary Login Identifications window.

- 5. To find a login ID to change, only one of the fields requires you to specify a value. Perform one of the following actions to specify a login ID in the Dictionary:
  - In the Login ID field, enter the number of the login ID.
  - In the Agent Name field, enter the name of the agent.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information that is associated with the specified login ID name, if valid.

- 7. In the **Agent Name** field, enter the modified name of the agent.
- 8. From the Actions menu, select Modify.

The specified login ID name and the changes are saved in the Dictionary.

# Deleting a login ID name using the PC Client

## Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Login identification**.
- 3. In the ACD field, enter the ACD or ACD Group in which the login ID name to delete resides.
- 4. Click **OK**.

CMS Supervisor displays the Dictionary Login Identifications window.

- 5. To find a login ID to delete, only one of the fields requires that you specify a value. Perform one of the following actions to specify a login ID in the Dictionary:
  - In the Login ID field, enter the number of the login ID.
  - In the Agent Name field, enter the name of the agent.
- 6. From the **Actions** menu, select **Find one**.

CMS Supervisor retrieves and displays the information for the specified login ID name, if valid.

7. From the Actions menu, select Delete.

# About administering logout reason code names in the Dictionary

An agent can use Logout reason codes to give the reason for logging out, such as attending training or the end of a shift. You can add, delete, change, and view logout reason codes from the Logout Reason Codes window. The names that you assign to the logout reason codes are displayed in the standard agent login/logout and agent trace historical reports.

## Permissions required to administer logout reason code names

Depending on the procedure that you want to perform, you need the following permissions:

- To view logout reason codes, you need "read" permissions for the Dictionary subsystem.
- To add, delete, or change logout reason code, you need "write" permissions for the Dictionary subsystem.

## Before using logout reason code names

- Logout reason codes are single digits from 0 to 9. A zero is used when the system logs an agent out or if the agent does not specify a code.
- Logout reason code names can be up to 20 characters long.
- To use logout reason codes, your switch must have the Expert Agent Selection (EAS) feature.

# Viewing a logout reason code name using the Web Client Procedure

1. Navigate to Administration > Dictionary > Logout Reason Codes.

CMS Supervisor displays the list of logout reason codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer logout reason codes.

CMS Supervisor displays the list of logout reason codes administered for the selected ACD.

# Adding a logout reason code name using the Web Client

## Procedure

1. Navigate to Administration > Dictionary > Logout Reason Codes.

CMS Supervisor displays the list of logout reason codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer logout reason codes.

CMS Supervisor displays the list of logout reason codes administered for the selected ACD.

3. Click Add Logout Reason Code.

CMS Supervisor displays the Add Logout Reason Code window.

- 4. Administer the following options:
  - In the Logout Reason Code field, enter a single digit numeric logout reason code.
  - In the **Logout Reason Code Name** field, enter a logout reason code name. The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma. You can enter up to 20 characters in this field.
  - In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

# Modifying a logout reason code name using the Web Client Procedure

1. Navigate to Administration > Dictionary > Logout Reason Codes.

CMS Supervisor displays the list of logout reason codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer logout reason codes.

CMS Supervisor displays the list of logout reason codes administered for the selected ACD.

3. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The Logout Reason Code field is a display-only field.
  - In the **Logout Reason Code Name** field, enter a logout reason code name. The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma. You can enter up to 20 characters in this field.
  - In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

# Deleting a logout reason code name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Logout Reason Codes.

CMS Supervisor displays the list of logout reason codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer logout reason codes.

CMS Supervisor displays the list of logout reason codes administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Viewing a logout reason code name using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Logout Reason Codes**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which you want to view a logout reason code name.
- 4. Click OK.

CMS Supervisor displays the Dictionary Logout Reason Codes window.

- 5. To find a logout reason code to view, only one of the fields requires that you specify a value. Perform one of the following actions to specify a logout reason code in the Dictionary:
  - In the Logout Reason Code Name field, enter the name of the logout reason code.
  - In the **Logout Reason Code** field, enter a number from 0 to 9 that is associated with the logout reason code.
- 6. From the Actions menu, select Find one.

CMS Supervisor displays the Dictionary window retrieves and displays the information for the specified logout reason code name, if valid.

# Listing all logout reason code names using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Logout Reason Codes**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which you want to view all logout reason code names.
- 4. Click **OK**.

CMS Supervisor displays the Dictionary Logout Reason Codes window.

5. From the **Actions** menu, select **List all**.

CMS Supervisor displays the Dictionary Logout Reason Codes - List All window.

# Adding a logout reason code name using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Logout Reason Codes**.
- 3. In the **ACD** field, enter the ACD or ACD Group in which you want to add a logout reason code.
- 4. Click OK.

CMS Supervisor displays the Dictionary Logout Reason Codes window.

- 5. In the Logout Reason Code Name field, enter the name of the new logout reason code.
- 6. In the **Logout Reason Code** field, enter a number from 0 to 9 to be associated with the logout reason code name.

You can enter any other information about the logout reason code in the **Description** field. You can enter only 50 or fewer characters in this field.

7. From the Actions menu, select Add.

# Modifying a logout reason code name using the PC Client Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Logout Reason Codes**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which you want to modify a logout reason code name.
- 4. Click OK.

CMS Supervisor displays the Dictionary Logout Reason Codes window.

- 5. To find a logout reason code to change, only one of the fields requires that you specify a value. Perform one of the following actions to specify a logout reason code in the Dictionary:
  - In the Logout Reason Code Name field, enter the name of the logout reason code.

- In the **Logout Reason Code** field, enter the number from 0 to 9 that is associated with the logout reason code.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified logout reason code name, if valid.

- 7. In the Logout Reason Code Name field, enter the new name for the logout reason code.
- 8. From the **Actions** menu, select **Modify**.

The specified logout reason code name and the changes are saved to the Dictionary.

# Deleting a logout reason code name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Logout Reason Codes**.
- 3. In the **ACD** field, enter the ACD or ACD Group on which the logout reason code name to delete resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Logout Reason Codes window.

- 5. To find a logout reason code to delete, only one of the fields requires that you specify a value. Perform one of the following actions to specify a logout reason code in the Dictionary:
  - In the Logout Reason Code Name field, enter the name of the logout reason code.
  - In the **Logout Reason Code** field, enter the number from 0 to 9 that is associated with the logout reason code.
- 6. From the Actions menu, select Find one.

Supervisor retrieves and displays the information for the specified logout reason code name, if valid.

7. From the Actions menu, select Delete.

The specified logout reason code name is removed from the Dictionary.

# About administering split or skill names in the Dictionary

You can assign names to your ACD splits or skills. These split or skill names appear on the split/ skill reports, making your reports easier to identify and read. The names you assign should reflect the configuration of your splits or skills and ACDs.

For example, if you want skills in your system to be divided according to Sales, Customer Service, and Wholesale, assign those names to the skills that handle those areas of the business. If you want skills in your system to be divided by language such as French, Spanish, and German, assign those names to the skills that handle calls in those languages.

### 😵 Note:

The Web Client does not support administration of any splits in a non-EAS environment even though the server will support upgraded non-EAS ACDs.

# Permissions required to administer split or skill names

Depending on the procedure that you want to perform, you need the following permissions:

- To view the name assigned to a split or skill, you need "read" permissions for the Dictionary subsystem and for the split or skill.
- To add, delete or modify the name assigned to a split or skill, you need "write" permissions for the Dictionary subsystem and for the split or skill.

# Before using split or skill names

The following items should be read and understood before working with split or skill names in the Dictionary:

- It is advised that you be consistent with the names given by your switch administrator.
- If you assign a name, the split or skill number no longer appears in split or skill reports or windows. The split or skill name appears instead.
- If you make changes to split or skill names when viewing a report that includes those splits or skills, you must exit the report and rerun it to see the changes.

# Viewing a skill name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Splits/Skills.

CMS Supervisor displays the list of skills administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer skills.

CMS Supervisor displays the list of skills administered for the selected ACD.

# Adding a skill name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Splits/Skills.

CMS Supervisor displays the list of skills administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer skills.

CMS Supervisor displays the list of skills administered for the selected ACD.

3. Click Add Skill.

CMS Supervisor displays the Add Skill window.

- 4. Administer the following options:
  - In the **Split/Skill Number** field, enter a value between 1-8000.
  - In the Split/Skill Name field, enter a skill name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying a skill name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Splits/Skills.

CMS Supervisor displays the list of skills administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer skills.

CMS Supervisor displays the list of skills administered for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The Split/Skill Number field is a display-only field.
  - In the Split/Skill Name field, enter a skill name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting a skill name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Splits/Skills.

CMS Supervisor displays the list of skills administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer skills.

CMS Supervisor displays the list of skills administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing a split or skill name using the PC Client

### Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Split/Skill**.

- 3. In the ACD field, enter the ACD or ACD Group on which you want to view a split/skill.
- 4. Click OK.

CMS Supervisor displays the Dictionary Splits/Skills window.

- 5. To find a split/skill to view, only one of the fields requires a split/skill to be specified. Perform one of the following actions to specify an existing split/skill in the Dictionary:
  - In the Split/Skill Name field, enter the name of the split/skill.
  - In the Split/Skill Number field, enter the number of the split/skill.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified split/skill name, if valid.

# Listing all split or skill names using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Split/Skill.
- 3. Click OK.

CMS Supervisor displays the Dictionary Splits/Skills window.

- 4. In the **ACD** field, enter the ACD or ACD Group on which you want to view all split/skill names.
- 5. From the Actions menu, select List all.

### Adding a split or skill name using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Split/Skill.
- 3. In the ACD field, enter the ACD or ACD Group on which you want to name a split/skill.
- 4. Click OK.

CMS Supervisor displays the Dictionary Splits/Skills window.

- 5. In the Split/Skill Name field, enter the name of the split/skill.
- 6. In the Split/Skill Number field, enter the number of the split/skill.

Any additional information about the split/skill can be entered in the **Description** field. Only 50 or fewer characters can be entered in this field.

7. From the Actions menu, select Add.

# Modifying a split or skill name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Split/Skill.
- 3. In the **ACD** field, enter the ACD or ACD Group on which you want to modify the split/skill name.
- 4. Click OK.

CMS Supervisor displays the Dictionary Splits/Skills window.

- 5. To find a split/skill to modify, only one of the fields requires a split/skill to be specified. Perform one of the following actions to specify an existing split/skill in the Dictionary:
  - In the Split/Skill Name field, enter the name of the split/skill.
  - In the Split/Skill Number field, enter the number of the split/skill.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified split/skill name, if valid.

- 7. In the Split/Skill Name field, enter the new name of the split/skill.
- 8. From the Actions menu, select Modify.

The split/skill name and its changes are saved to the Dictionary.

# Deleting a split or skill name using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Split/Skill.
- 3. In the **ACD** field, enter the ACD or ACD Group on which the split/skill name to delete resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Splits/Skills window.

- 5. To find a split/skill to delete, only one of the fields requires a split/skill to be specified. Perform one of the following actions to specify an existing split/skill in the Dictionary:
  - In the Split/Skill Name field, enter the name of the split/skill.
  - In the Split/Skill Number field, enter the number of the split/skill.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified split/skill name, if valid.

7. From the **Actions** menu, select **Delete**.

The split/skill name is removed from the Dictionary.

# About administering split or skill string values in the Dictionary

Split or skill string values are the descriptive words used in the split or skill call profile reports instead of the split or skill numeric values. From the Split/Skill String Values window, you can change the default string values to correspond to your own requirements.

# Permissions required to administer split or skill string values

Depending on the procedure that you want to perform, you need the following permissions:

- To view split or skill string values, you need "read" permissions for the Dictionary subsystem.
- To change split or skill string values, you need "write" permissions for the Dictionary subsystem.

# Before using split or skill string values

- If you assign values that are longer than the field lengths permitted on standard reports, those values are truncated to fit on the reports. You can create similar custom reports to accommodate the longer string values.
- If you do not assign different values to the split or skill string values, the default values are used in the reports.

## Viewing skill string values using the Web Client Procedure

1. Navigate to Administration > Dictionary > Split/Skill String Values.

CMS Supervisor displays the list of skill string values administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer skill string values.

CMS Supervisor displays the list of skill string values administered for the selected ACD.

# Modifying skill string values using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Split/Skill String Values.

CMS Supervisor displays the list of skill string values administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer skill string values.

CMS Supervisor displays the list of skill string values administered for the selected ACD.

3. Enter a new string value in each field that you want to modify.

See <u>Split or skill string value field descriptions</u> on page 119 for field descriptions.

- 4. Do one of the following actions:
  - Click **Apply** to commit the change.
  - Click **Reset** to reset the values of the fields.

If you clicked **Apply**, CMS Supervisor displays a confirmation message. If you clicked **Reset**, the fields reset to the previous values.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Viewing split or skill string values using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

2. In the **Operations** list, highlight **Split/Skill String Values**.

- 3. In the **ACD** field, enter the ACD or ACD Group on which you want to view the split/skill string values.
- 4. Select OK.

CMS Supervisor displays the Dictionary Split/Skill String Values window.

# Modifying split or skill string values using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Operations list, highlight Split/Skill String Values.
- 3. In the **ACD** field, enter the ACD or ACD Group on which you want to modify the split/skill string values.
- 4. Select OK.

CMS Supervisor displays the Dictionary Split/Skill String Values window.

5. Enter a new string value in each field that you want to modify.

See <u>Split or skill string value field descriptions</u> on page 119 for field descriptions.

6. From the Actions menu, select Modify.

The split/skill string values and the changes are saved to the Dictionary.

# Split or skill string value field descriptions

Name	Description
Service Level Changed	The service level is the time limit in seconds for calls to wait in queue before being answered. The Split/Skill Call Profile reports can be used to see how many calls were either answered or abandoned within each service level increment.
	The string values in the following fields are displayed on the Split/Skill Call Profile Report:
	• <b>YES</b> : The string value in this field displays on the Split/Skill Call Profile Report if the service level in the split/skill call profile has changed.
	• <b>NO</b> : The string value in this field displays on the Split/Skill Call Profile Report if the service level in the split/skill call profile has not changed.

Table continues...

Name	Description
Period Changed	There are ten time increments of administrable length in the real-time and historical Split/Skill Call Profile Reports.
	The string values in the following fields are displayed on the Split/Skill Call Profile Report:
	• <b>YES</b> : The string value in this field displays on the Split/Skill Call Profile if the time in the split/skill call profile has changed.
	• <b>NO</b> : The string value in this field displays on the Split/Skill Call Profile if the time in the split/skill call profile has not changed.
Skill State	Skill states are used to specify states for the different skills.
	The string values in the following fields represent the following skill states:
	• UNKNOWN: Leave the default value. The default value is UNKN.
	• <b>Normal</b> : Enter the descriptive word for the state of a skill using the Service Level Supervisor feature when the skill is less than all overload thresholds. The default value is NORMAL.
	• <b>Overload1</b> : Enter the descriptive word for the state of a skill using the Service Level Supervisor feature when the skill exceeds the first overload threshold. The default value is OVRLD1.
	• <b>Overload2</b> : Enter the descriptive word for the state of a skill using the Service Level Supervisor feature when the skill exceeds both the first and second thresholds. The default value is OVRLD2.
	• <b>BEHIND</b> : This string indicates that a split or skill is either close to or failing to meet the administered target service level, and agents are not being autoreserved to compensate for this situation. The default value for this string is BEHIND.
	• <b>AUTORSV</b> : This string indicates that a split or skill is either close to or failing to meet the administered target service level, and agents are being autoreserved to achieve the necessary level. The default value for this string is AUTORSV.

# About viewing standard CMS database items in the Dictionary

Standard database items store ACD data and are used by CMS in its default reports.

You cannot change or delete standard database items because this is a read-only section of the Dictionary. You can view the standard information about each database item, the description for that item, and the tables in which the item appears.

The following example shows a current real-time agent table with standard CMS database item column headings:

Extension	Split	Logid	Logon start	Work mode	Started	Direction	Changed	>*
1000	1	4000	8:00	AVAIL	8:00	NULL	8:00	>
1001	1	5966	7:58	ACD	8:04	IN	8:04	>
1002	1	2200	7:59	ACD	8:03	IN	8:03	>
		•		•	•	•	•	>

### 😵 Note:

" >\*" indicates that more database item column headings follow. A dot (".") indicates that more data follows down the table.

# Permissions required to view standard CMS database items

To view the standard CMS database items, you need "read" permissions for the Dictionary subsystem.

# Viewing standard CMS database items using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Standard CMS Items.

CMS Supervisor displays the list of standard CMS database items for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to view standard CMS database items.

CMS Supervisor displays the list of standard CMS database items for the selected ACD.

# Viewing a standard CMS database item using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Standard CMS Items**.
- 3. Select OK.

CMS Supervisor displays the Dictionary Standard CMS Items window.

4. In the **Database Item** field, enter the name of the database item entirely in uppercase letters.

### Important:

If you do not know the entire database item name, enter part of the database item name along with an asterisk (\*) to find the item. You can use pattern searching in any field in the window.

You can also enter information in the **Table** field to limit the search of a database item to a single table.

5. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified standard database item, if valid.

😒 Note:

If you used pattern matching in your search for a standard database item, it is possible that more than one match was found. To view the next database item that matches the search parameter, select **Next** from the **Actions** menu. Continue to select **Next** until the appropriate database item is found.

# Viewing all standard CMS database items alphabetically using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Standard CMS Items**.
- 3. Select OK.

CMS Supervisor displays the Dictionary Standard CMS Items window.

4. From the Actions menu, select List all.

# About administering tenant names in the Dictionary

The Tenants window is used to assign tenant names, numbers, and description. The tenant names appear in reports making the reports easier to understand.

# Permissions required to administer tenant names

Depending on the procedure that you want to perform, you need the following permissions:

- To view the name that is assigned to a tenant, you need read permissions for the Dictionary subsystem and for the tenant partition.
- Tenant users cannot add, delete, or modify tenant names.

# Before using tenant names

You must install the tenancy feature package first. The administrator must already have planned out the division of the following resources on the given ACD: trunk groups, splits/skills, agent logids, Call work codes, and VDNs.

# Viewing a tenant name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Tenants.

CMS Supervisor displays the list of tenants administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer tenants.

CMS Supervisor displays the list of tenants administered for the selected ACD.

# Adding a tenant name using the Web Client

### Procedure

1. Navigate to **Administration > Dictionary > Tenants**.

CMS Supervisor displays the list of tenants administered for the current ACD.

In the Current ACD drop-down list, select the active ACD for which you want to administer tenants.

CMS Supervisor displays the list of tenants administered for the selected ACD.

3. Click Add Tenant.

CMS Supervisor displays the Add Tenant window.

- 4. Administer the following options:
  - In the **Tenant Number** field, enter a value between 0-250.

• In the Tenant Name field, enter a tenant name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

## Modifying a tenant name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Tenants.

CMS Supervisor displays the list of tenants administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer tenants.

CMS Supervisor displays the list of tenants administered for the selected ACD.

3. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The **Tenant Number** field is a display-only field.
  - In the Tenant Name field, enter a tenant name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting a tenant name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Tenants.

CMS Supervisor displays the list of tenants administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer tenants.

CMS Supervisor displays the list of tenants administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Viewing a tenant name using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Tenants**.
- 3. In the **ACD** field, enter the ACD for which you want to view a tenant.
- 4. Click OK.

CMS Supervisor displays the Dictionary Tenants window.

- 5. To find a tenant partition to view, only one of the fields requires a tenant partition to be specified. Perform one of the following actions to specify an existing tenant in the Dictionary:
  - a. In the Tenant Name field, enter the name of the tenant partition.
  - b. In the **Tenant Number** field, enter the number of the tenant partition.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified tenant, if valid.

# Listing all tenant names using the PC Client Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Tenants**.
- In the ACD field, enter the ACD for which you want to list all tenants and click OK.
   CMS Supervisor displays the Dictionary Tenants window.
- 4. From the Actions menu, select List all.

# Adding a tenant name using the PC Client

### Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Tenants**.
- 3. In the **ACD** field, enter the ACD for which you want to add a tenant.
- 4. Click OK.

CMS Supervisor displays the Dictionary Tenants window.

- 5. In the **Tenant Name** field, enter the name of the tenant partition.
- 6. In the **Tenant Number** field, enter the number of the tenant partition.

### Note:

The tenant partition must be assigned a number from 1 to 250.

7. From the Actions menu, select Add.

# Modifying a tenant name using the PC Client

### Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Tenants**.
- In the ACD field, enter the ACD for which you want to modify a tenant and click OK.
   CMS Supervisor displays the Dictionary Tenants window.

- 4. Perform one of the following actions to specify an existing tenant in the Dictionary:
  - a. In the **Tenant Name** field, enter the name of the tenant partition.
  - b. In the **Tenant Number** field, enter the number of the tenant partition.
- 5. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified tenant, if valid.

- 6. In the **Tenant Name** or **Description** field, make the necessary changes for the tenant partition.
- 7. From the **Actions** menu, select **Modify**.

### Deleting a tenant name using the PC Client

### Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **Tenants**.
- In the ACD field, enter the ACD for which you want to delete a tenant and click OK.
   CMS Supervisor displays the Dictionary Tenants window.
- 4. Perform one of the following actions to specify an existing tenant in the Dictionary:
  - a. In the Tenant Name field, enter the name of the tenant partition.
  - b. In the **Tenant Number** field, enter the number of the tenant partition.
- 5. From the **Actions** menu, select **Delete**.

The selected tenant name is removed from the Dictionary.

# About administering trunk group names in the Dictionary

The Trunk Groups window is used to assign names to ACD trunk groups. The trunk groups names appear in reports making the reports easier to understand.

### Permissions required to administer trunk group names

Depending on the procedure that you want to perform, you need the following permissions:

• To view the name that is assigned to a trunk group, you need "read" permissions for the Dictionary subsystem and for the trunk group.

• To add, delete, or modify the name assigned to a trunk group, you need "write" permissions for the Dictionary subsystem and for the trunk group.

# Before using trunk group names

The following items should be read and understood before working with trunk groups names in the Dictionary:

- When naming trunk groups, you may want to be consistent with the names given to trunk groups and splits/skills by your switch administrator.
- If you assign a trunk group name, the name is displayed on trunk group reports or windows instead of the trunk group number.
- If you make changes to trunk group names while viewing a report that includes those trunk groups, you must exit the report and rerun it to see the changes.

# Viewing a trunk group name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Trunk Groups.

CMS Supervisor displays the list of trunk groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk groups.

CMS Supervisor displays the list of trunk groups administered for the selected ACD.

# Adding a trunk group name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Trunk Groups.

CMS Supervisor displays the list of trunk groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk groups.

CMS Supervisor displays the list of trunk groups administered for the selected ACD.

3. Click Add Trunk Group(s).

CMS Supervisor displays the Add Trunk Group(s) window.

- 4. Administer the following options:
  - In the Trunk Group Number field, enter a value between 1-2000.
  - In the Trunk Group Name field, enter a trunk group name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

## Modifying a trunk group name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Trunk Groups.

CMS Supervisor displays the list of trunk groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk groups.

CMS Supervisor displays the list of trunk groups administered for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The Trunk Group Number field is a display-only field.
  - In the Trunk Group Name field, enter a trunk group name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting a trunk group name using the Web Client Procedure

1. Navigate to Administration > Dictionary > Trunk Groups.

CMS Supervisor displays the list of trunk groups administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk groups.

CMS Supervisor displays the list of trunk groups administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

- Click **OK** to commit the operation. Click **Cancel** to cancel the operation. CMS Supervisor displays a confirmation message.
- 5. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing a trunk group name using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Trunk Groups**.
- 3. In the **ACD** field, enter the ACD on which you want to view a trunk group name.
- 4. Click OK.

CMS Supervisor displays The Dictionary Trunk Groups window.

- 5. To find a trunk group to view, only one of the fields requires a trunk group to be specified. Perform one of the following actions to specify an existing trunk group in the Dictionary:
  - In the Trunk Group Name field, enter the name of the trunk group.
  - In the Trunk Group Number field, enter the number of the trunk group.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified trunk group, if valid.

# Listing all trunk group names using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Trunk Groups**.
- 3. In the **ACD** field, enter the ACD on which you want to list all trunk group names.
- 4. Click OK.

CMS Supervisor displays The Dictionary Trunk Groups window.

5. From the Actions menu, select List all.

# Adding a trunk group name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Trunk Groups**.
- 3. In the **ACD** field, enter the ACD on which you want to name a trunk group.
- 4. Click OK.

CMS Supervisor displays The Dictionary Trunk Groups window.

- 5. In the Trunk Group Name field, enter the name of the trunk group.
- 6. In the **Trunk Group Number** field, enter the number of the trunk group.

Any additional information about the trunk group can be entered in the **Description** field. Only 50 or fewer characters can be entered in this field.

7. From the **Actions** menu, select **Add**.

# Modifying a trunk group name using the PC Client Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Trunk Groups**.
- 3. In the **ACD** field, enter the ACD on which you want to modify a trunk group name.

4. Click OK.

CMS Supervisor displays The Dictionary Trunk Groups window.

- 5. To find a trunk group to modify, only one of the fields requires a trunk group to be specified. Perform one of the following actions to specify an existing trunk group in the Dictionary:
  - In the Trunk Group Name field, enter the name of the trunk group.
  - In the Trunk Group Number field, enter the number of the trunk group.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified trunk group, if valid.

- 7. In the **Trunk Group Name** or **Description** field, make the necessary changes for the trunk group.
- 8. From the Actions menu, select Modify.

# Deleting a trunk group name using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the Trunk Group Name list, highlight Trunk Groups.
- 3. In the **Trunk Group Number** field, enter the ACD on which the trunk group to delete resides.
- 4. Click OK.

CMS Supervisor displays The Dictionary Trunk Groups window.

- 5. To find a trunk group to delete, only one of the fields requires a trunk group to be specified. Perform one of the following actions to specify an existing trunk group in the Dictionary:
  - In the Trunk Group Name field, enter the name of the trunk group.
  - In the Trunk Group Number field, enter the number of the trunk group.
- 6. From the Actions menu, select Delete.

The selected trunk group name is removed from the Dictionary.

# About administering trunk string values in the Dictionary

Trunk string values are the descriptive words such as IDLE, HOLD, or QUEUED on trunk reports. These words are displayed in the data fields of the report. They are not displayed as headings. From the Trunk String Values window, the default values can be changed to any values that meet the needs of your call center. If you do not assign different trunk string values, the default values are used. Any changes that you make to the trunk string values affect what you see in the corresponding fields on trunk reports.

# Permissions required to administer trunk string values

Depending on the procedure that you want to perform, you need the following permissions:

- To view the trunk string values, you need "read" permissions for the Dictionary subsystem.
- To modify a trunk string value, you need "write" permissions for the Dictionary subsystem.

# Administering trunk string values using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Trunk String Values.

CMS Supervisor displays the list of trunk string values administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk string values.

CMS Supervisor displays the list of trunk string values administered for the selected ACD.

3. Enter a new string value in each field that you want to modify.

See <u>Trunk string values field descriptions</u> on page 134 for the field definitions.

- 4. Do one of the following actions:
  - Click **Apply** to commit the change.
  - Click **Reset** to reset the values of the fields.

If you clicked **Apply**, CMS Supervisor displays a confirmation message. If you clicked **Reset**, the fields reset to the previous values.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

# Administering trunk string values using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor retrieves and displays the information for the specified trunk group, if valid.

2. In the **Operations** list, highlight **Trunk String Values**.

3. Select OK.

CMS Supervisor displays the Dictionary Trunk String Values window.

4. To change any of the default names, enter the new descriptive word in the text box that is next to the name that you want to change.

See Trunk string values field descriptions on page 134 for the field definitions.

5. From the **Actions** menu, select **Modify** when the necessary changes have been completed.

# Trunk string values field descriptions

The following table describes the trunk string value fields.

Name	Description
Trunk State	To change any of the trunk state default names, enter the new descriptive word next to any of the following:
	• IDLE - The trunk is waiting for a call.
	• SEIZED - A call is holding the trunk, either incoming or outgoing.
	<ul> <li>QUEUED - An ACD call has seized the trunk, is queued to a split/skill, and is waiting for an agent to become available.</li> </ul>
	• CONN - The caller and an agent are connected on a call.
	DABN - The caller has abandoned the call.
	• FBUSY - The caller receives a forced busy signal.
	FDISC - The caller receives a forced disconnect.
	<ul> <li>HOLD - The agent has put the caller on hold.</li> </ul>
	MBUSY - The trunk is out of service for maintenance purposes.
	• <b>RINGING</b> - The call is ringing at an agent's voice terminal.
	UNKNOWN - CMS does not recognize the trunk state.
Queue Type	To change the queue type default names, enter the new descriptive name next to <b>MAIN</b> or <b>BACKUP</b> . The name entered here is displayed instead of the default value in real-time reports containing the trunk <b>QUETYPE</b> database item. (Standard reports do not contain this item).
	• MAIN - The call is queued to a split/skill as a result of a queue to main split/skill vector command.
	• BACKUP - The call is queued to a split/skill as a result of a vector command other than queue to main split/skill.

Table continues...

Name	Description				
Call Priority (Non-Vectoring)	To change the call priority (non-vectoring) default names, enter the new descriptive name next to <b>YES</b> or <b>NO</b> . The name entered here is displayed instead of the default name in real-time reports containing the trunk <b>PRIORITY</b> database item. (Standard reports do not contain this item.)				
	• YES - The call occupying the trunk has priority entering the trunk.				
	<ul> <li>NO - The call occupying the trunk does not have priority entering the split.</li> </ul>				
Call Priority (Vectoring)	To change the call priority (vectoring) default names, enter the new descriptive name next to LOW, MED, HIGH, or TOP. The priority level at which calls on a trunk queue to a split/skill is specified using either the queue to split/skill or check split/skill command in the vector that is processing the call. The name entered here is displayed instead of the default name in real-time reports containing the trunk <b>PRIORITY</b> database item. (Standard reports do not contain this item).				
	<ul> <li>LOW - The call occupying the trunk is queued to a split or skill at the lowest priority level.</li> </ul>				
	• <b>MED</b> - The call occupying the trunk is queued to a split or skill at the second lowest priority level.				
	<ul> <li>HIGH - The call occupying the trunk is queued to a split or skill at the second highest priority level.</li> </ul>				
	<ul> <li>TOP - The call occupying the trunk is queued to a split or skill at the highest priority level.</li> </ul>				
Call Direction	To change the call-direction default names, enter the new descriptive word next to <b>IN</b> or <b>OUT</b> .				
	• IN - The trunk is on an incoming call.				
	• <b>OUT</b> - The trunk is on an outbound call.				
All Trunks Busy	To change the all trunks busy default names, enter the new descriptive word next to <b>YES</b> or <b>NO</b> .				
	• <b>YES</b> - All trunks in the trunk group are busy (in use or maintenance).				
	• NO - Not all trunks in the trunk group are busy.				

# About administering VDN names in the Dictionary

From the VDNs window, you can assign names to VDNs so that names instead of numbers appear on VDN reports and VDN administration windows. VDN names should reflect the configuration of your ACD and convey one or more of the following:

- The VDN's purpose; for example, sales or customer service.
- The VDN destination vector; for example, FBusy-Nat.Accts.

• The trunk groups assigned to the VDN; for example, WATS 800-331-1111.

## Permissions required to administer VDN names

Depending on the procedure that you want to perform, you need the following permissions:

- To view the name that is assigned to a VDN, you need "read" permissions for the Dictionary subsystem and for the VDN.
- To add, delete, or modify the name that is assigned to a VDN, you need "write" permissions for the Dictionary subsystem and for the VDN.

# **Before using VDN names**

The following items should be read and understood before working with VDN names in the Dictionary:

- The VDNs window is available only if the Call Vectoring feature is installed and activated on your switch.
- VDNs must be created on the switch and assigned for measurement via CMS.
- To get a list of VDNs that can be named, run the vector configuration report. While all VDNs can be named, it is recommended that only those VDNs that are used are then named instead of all of the VDNs. This will conserve system resources.
- If you make changes to the VDN names when a report that includes those VDNs is running, you must exit the report and rerun it to see the changes.
- When naming VDNs, you may want to be consistent with the names given to VDNs by your switch administrator.
- If a name is assigned to a VDN, it will appear on VDN reports and windows instead of the VDN number.

# Viewing a VDN name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > VDNs.

CMS Supervisor displays the list of VDNs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDNs.

CMS Supervisor displays the list of VDNs administered for the selected ACD.

# Adding a VDN name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > VDNs.

CMS Supervisor displays the list of VDNs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDNs.

CMS Supervisor displays the list of VDNs administered for the selected ACD.

3. Click Add VDN.

CMS Supervisor displays the Add VDN window.

- 4. Administer the following options:
  - In the VDN field, enter the VDN. It must be a unique 3-13 digit number.
  - In the VDN Name field, enter a VDN name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

# Modifying a VDN name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > VDNs.

CMS Supervisor displays the list of VDNs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDNs.

CMS Supervisor displays the list of VDNs administered for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The **VDN** field is a display-only field.
  - In the VDN Name field, enter a VDN name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting a VDN name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > VDNs.

CMS Supervisor displays the list of VDNs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDNs.

CMS Supervisor displays the list of VDNs administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing a VDN name using the PC Client

### Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **VDNs**.

- 3. In the **ACD** field, enter the ACD on which you want to view a VDN.
- 4. Click OK.

CMS Supervisor displays the Dictionary VDNs window.

- 5. To find a VDN name to view, only one of the fields requires a VDN to be specified. Perform one of the following actions to specify an existing VDN in the Dictionary:
  - In the VDN Name field, enter the name of the VDN.
  - In the **VDN** field, enter the number of the VDN.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified VDN name, if valid.

# Listing all VDN names

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **VDNs**.
- 3. In the **ACD** field, enter the ACD on which you want to view all the VDNs.
- 4. Click OK.

CMS Supervisor displays the Dictionary VDNs window.

5. From the Actions menu, select List all.

# Adding a VDN name using the PC Client

### Procedure

- From the Controller window, select Commands > Dictionary.
   CMS Supervisor displays the Dictionary window.
- 2. In the **Operations** list, highlight **VDNs**.
- 3. In the **ACD** field, enter the ACD on which you want to name a VDN.
- 4. Click OK.

CMS Supervisor displays the Dictionary VDNs window.

- 5. In the VDN Name field, enter the name of the VDN.
- 6. In the **VDN** field, enter the number of the VDN.

Any additional information about the VDN, can be entered in the **Description** field. Only 50 or fewer characters can be entered in this field.

7. From the Actions menu, select Add.

# Modifying a VDN name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **VDNs**.
- 3. In the ACD field, enter the ACD on which you want to modify the name of a VDN.
- 4. Click OK.

CMS Supervisor displays the Dictionary VDNs window.

- 5. To find a VDN name to modify, only one of the fields requires a VDN to be specified. Perform one of the following actions to specify an existing VDN in the Dictionary:
  - In the VDN Name field, enter the name of the VDN.
  - In the **VDN** field, enter the number of the VDN.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified VDN name, if valid.

- 7. In the VDN Name or Description field, make the necessary changes.
- 8. From the Actions menu, select Modify.

# Deleting a VDN name using the PC Client

### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **VDNs**.
- 3. In the **ACD** field, enter the ACD on which the VDN you want to delete resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary VDNs window.

- 5. To find a VDN name to delete, only one of the fields requires a VDN to be specified. Perform one of the following actions to specify an existing VDN in the Dictionary:
  - In the VDN Name field, enter the name of the VDN.
  - In the VDN field, enter the number of the VDN.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified VDN, if valid.

7. From the **Actions** menu, select **Delete**.

The name and description for this VDN is removed from the Dictionary.

# About administering vector names in the Dictionary

From the Vectors window, you can assign names to vectors so that the names instead of the vector numbers are displayed on vector reports and administration windows. Vector names should reflect the configuration of your ACD and convey one or more of the following:

- The vector's purpose, for example, sales or customer service.
- The VDNs assigned to the vector; for example, vdn2001, vdn3001, and vdn4001.
- The splits or skills to which the vector sends calls; for example, sales1, sales2, AUDIX system.

# Permissions required to administer vector names

Depending on the procedure that you want to perform, you need the following permissions:

- To view the name that is assigned to a vector, you need "read" permissions for the Dictionary subsystem and for the vector.
- To add, delete, or modify the name that is assigned to a vector, you need "write" permissions for the Dictionary subsystem and for the vector.

# Before using vector names

The following items should be read and understood before working with vector names in the Dictionary:

- The Vectors window is available only if the Call Vectoring feature is installed and activated on the switch.
- You can assign a name to a vector even if the steps to the vector have not been assigned.
- The number of available vectors depends on the switch type.

- If a name is assigned to a vector, it appears on reports and windows instead of the vector number.
- If you make changes to vector names when a report that includes those vectors is running, you must exit the report and rerun it to see the changes.

Viewing a vector name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Vectors.

CMS Supervisor displays the list of vectors administered for the current ACD.

 In the Current ACD drop-down list, select the active ACD for which you want to administer vectors.

CMS Supervisor displays the list of vectors administered for the selected ACD.

# Adding a vector name using the Web Client

### Procedure

1. Navigate to **Administration > Dictionary > Vectors**.

CMS Supervisor displays the list of vectors administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer vectors.

CMS Supervisor displays the list of vectors administered for the selected ACD.

3. Click Add Vectors.

CMS Supervisor displays the Add Vector window.

- 4. Administer the following options:
  - In the **Vector Number** field, enter a value between 1-8000.
  - In the Vector Name field, enter a vector name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying a vector name using the Web Client Procedure

1. Navigate to Administration > Dictionary > Vectors.

CMS Supervisor displays the list of vectors administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer vectors.

CMS Supervisor displays the list of vectors administered for the selected ACD.

3. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Administer the following options:
  - The Vector Number field is a display-only field.
  - In the Vector Name field, enter a vector name.

The first character must be A-Z or a-z. The remaining characters can be A-Z, a-z, 0-9, underscore, space, period, or comma.

- In the **Description** field, enter any additional information about the item. You can enter up to 50 characters in this field. This field cannot contain a pipe symbol (|), double quotes ("), or a semi-colon (;).
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

# Deleting a vector name using the Web Client

### Procedure

1. Navigate to Administration > Dictionary > Vectors.

CMS Supervisor displays the list of vectors administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer vectors.

CMS Supervisor displays the list of vectors administered for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing a vector name using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Vectors**.
- 3. In the ACD field, enter the ACD on which you want to view a vector name.
- 4. Click OK.

CMS Supervisor displays the Dictionary Vectors window.

- 5. To find a vector name to view, only one of the fields requires a vector to be specified. Perform one of the following actions to specify an existing vector in the Dictionary:
  - In the Vector Name field, enter the name of the vector.
  - In the Vector Number field, enter the number of the vector.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified vector, if valid.

### Listing all vector names using the PC Client

### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Vectors**.
- 3. In the ACD field, enter the ACD on which you want to list all vector names.
- 4. Click **OK**.

CMS Supervisor displays the Dictionary Vectors window.

5. From the Actions menu, select List all.

### Adding a vector name using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Vectors**.
- 3. In the **ACD** field, enter the ACD on which you want to name a vector.
- 4. Click OK.

CMS Supervisor displays the Dictionary Vectors window.

- 5. In the Vector Name field, enter the name of the vector.
- 6. In the Vector Number field, enter the number of the vector.

Any additional information about the vector, can be entered in the **Description** field. Only 50 or fewer characters can be entered in this field.

7. From the Actions menu, select Add.

### Modifying a vector name using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Vectors**.
- 3. In the ACD field, enter the ACD on which you want to modify a vector name.
- 4. Click OK.

CMS Supervisor displays the Dictionary Vectors window.

- 5. To find a vector name to modify, only one of the fields requires a vector to be specified. Perform one of the following actions to specify an existing vector in the Dictionary:
  - In the Vector Name field, enter the name of the vector.
  - In the Vector Number field, enter the number of the vector.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified vector, if valid.

- 7. In the Vector Name or Description field, make the necessary changes.
- 8. From the Actions menu, select Modify.

### Deleting a vector name using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

- 2. In the **Operations** list, highlight **Vectors**.
- 3. In the **ACD** field, enter the ACD on which the vector name to delete resides.
- 4. Click OK.

CMS Supervisor displays the Dictionary Vectors window.

- 5. To find a vector name to delete, only one of the fields requires a vector to be specified. Perform one of the following actions to specify an existing vector in the Dictionary:
  - In the Vector Name field, enter the name of the vector.
  - In the Vector Number field, enter the number of the vector.
- 6. From the Actions menu, select Find one.

CMS Supervisor retrieves and displays the information for the specified vector, if valid.

7. From the **Actions** menu, select **Delete**.

The name for this vector is removed from the Dictionary.

# Chapter 5: Administering call center features

### About administering call center features

This section provides the procedures to perform operations to configure call center features.

Depending on the type of Communication Manager system and the features that are enabled on it, the items on the **Call Center Administration** menu will vary.

### Before administering call center features

If an ACD Group is selected as the current ACD in the Dictionary window, only those add, modify, or delete operations that are valid for the ACD Group will appear in the list of operations.

### About administering ACD groups

An ACD group is an administrator-assigned collection of ACDs. Putting multiple ACDs in an ACD group allows you to easily administer Dictionary synonyms across several ACDs in one administrative operation. You can also run reports on ACD groups to get data about multiple ACDs.

### Before using ACD groups

The following items should be read and understood before you work with ACD groups

#### Availability

• If you add an ACD group, you will need to log out of Supervisor and log back in to see this group as a choice in the appropriate dialogs.

#### **Capacities/Performance**

- A maximum of 12 ACD groups can exist on an Avaya CMS server.
- Each ACD group can contain up to eight ACDs.

• CMS must be in single-user mode to administer ACD groups.

#### **Roles/Definitions**

- An ACD group cannot serve as the CMS master ACD.
- An ACD group cannot be deleted if it is set as the current ACD.
- When created, ACD groups will be assigned an ACD ID number from 27 through 38. This number is automatically assigned by CMS and cannot be altered.
- ACD groups will not disallow an ACD being added as a member based on its version or feature set.
- Pseudo-ACDs cannot be a member of an ACD group.
- When an ACD group is deleted, all synonyms assigned to its member ACDs will remain.
- Names must begin with an alphabetic character and can be up to 20 characters long. Valid characters are alphanumerical (a-z, A-Z, 0-9), underscore (\_), blank (), comma (,), period (.), single quote ('), and plus (+). Multiple values are not allowed.

#### Synonyms

- Overlapping ACD groups (groups having common member ACDs), could result in synonym conflict within the members of an ACD group if poorly administered. Because of this capability, entity IDs in overlapping ACD groups must be mutually exclusive.
- Entity synonyms must be unique for an ACD group and across all of the ACDs that are members of the ACD group.

#### Other

- User permissions are administered separately for an ACD group and its member ACDs.
- CMS real-time custom reports are only displayed if data collection is enabled and the ACD link status is 'up' for at least one member ACD in the specified ACD group. An error message will be displayed if these conditions are not met.
- Custom reports that are created with the Single ACD option enabled cannot be run for an ACD group and vice versa.
- If a backup was created on a CMS server where the Global Dictionary feature was authorized, the data can only be restored on a CMS server that also has this feature authorized. If the Global Dictionary feature authorizations between a backup and the target CMS server do not match, an error is displayed, a message is written to the error log, and the restore or migration fails.

### **Benefits of using ACD groups**

This optional feature provides the following capabilities:

• Easy administration of synonyms in the Dictionary across multiple ACDs. A synonym assigned to a CMS entity for an ACD group is then propagated to all members ACDs within that group. For example, if you assign skill 102 in the ACD group with the synonym of "Sales", this synonym is assigned to skill 102 for all ACDs within that group. This feature

should be utilized when a call center uses multiple ACDs that require the same synonyms across all of the ACDs for the following entities:

- Agent login IDs
- Agent groups
- Splits or skills
- AUX reason codes
- Logout reason codes
- Agent string values
- Split or skill string values
- Generic string value synonyms
- The reporting of data from multiple ACDs through the use of custom reports. Reports for ACD groups collect, aggregate, and display call center data as a single value for the ACD group instead of one set of values for each member ACD. Custom reports can be created through the CMS ASCII interface or ordered through the Avaya Professional Services Organization. For example, the reporting aspect of this feature can be used to view data for a CMS entity across multiple ACDs such as a skill, a specific agent login ID, and so forth.

### ACD groups feature interfaces

The ACD groups feature is available through two interfaces:

- Call Center Administration This subsystem is used for administrators to create, modify, and delete ACD groups.
- Dictionary This subsystem is used by CMS users who need to view ACD groups, their contents, and to assign ACD group synonyms.

### Permissions required to administer ACD groups

- To create, modify, and delete ACD groups, a CMS user must have the "read" and "write" permissions for the Call Center Administration subsystem.
- If a CMS user only requires the ability to view ACD groups and the member ACDs, "read" permission is required for the Dictionary subsystem.
- To assign synonyms to an ACD group, a CMS user requires the "read" and "write" permissions for the Dictionary subsystem as well as the ACD group and its member ACDs.

### Listing ACD groups using the Web Client

#### About this task

This topic provides the procedure for listing all ACD groups defined on the CMS server.

Listing all ACD groups can be done through either the Call Center Administration or Dictionary subsystems. Only those CMS users who have "read" permission for the Call Center Administration subsystem can use the procedure listed below. CMS users who only work with synonyms or running reports should use the procedure associated with the Dictionary subsystem for listing all ACD groups.

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

#### Procedure

#### Navigate to Administration > Call Center Administration > ACD Groups.

CMS Supervisor displays the list of ACD groups administered for the system.

### Viewing the contents of an ACD group using the Web Client

#### About this task

This topic provides the procedure for displaying the contents of an ACD group.

Viewing the contents of an ACD group can be done through either the Call Center Administration or Dictionary subsystems. Only those CMS users who have "read" permission for the Call Center Administration subsystem can use the following procedure. CMS users who only work with synonyms or running reports should use the procedure in <u>About administering ACD Groups in the Dictionary</u> on page 49.

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

#### Procedure

1. Navigate to Administration > Call Center Administration > ACD Groups.

CMS Supervisor displays the list of ACD groups administered for the system.

2. Click Group Contents for one of the ACD groups.

CMS Supervisor displays the list of ACDs administered for the ACD group.

3. Click **Back to Group List** to get back to the list of ACD groups administered for the current ACD.

### Adding an ACD group using the Web Client

#### About this task

Use this procedure to create an ACD group. After creating an ACD group, add member ACDs using the procedure Adding an ACD to an ACD group using the Web Client on page 151.

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

#### Procedure

1. Navigate to Administration > Call Center Administration > ACD Groups.

CMS Supervisor displays the list of ACD groups administered for the system.

2. Click Add ACD Group.

CMS Supervisor displays the Add ACD Group window.

- 3. In the **ACD Group Name** field, enter a name for the ACD group.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

### Adding an ACD to an ACD group using the Web Client

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

This procedure can only be done after an ACD group has been created. For more information, see <u>Adding an ACD group using the Web Client</u> on page 150.

#### Procedure

1. Navigate to Administration > Call Center Administration > ACD Groups.

CMS Supervisor displays the list of ACD groups administered for the system.

2. Click Group Contents for one of the ACD groups.

CMS Supervisor displays the list of ACDs administered for the ACD group.

3. Click Add ACD.

CMS Supervisor displays the ACD Groups: Contents window.

- 4. In the **ACD Number** field, select an ACD from the drop-down list of ACDs.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **Yes** to propagate reason codes and string-valued database items from the ACD group to the ACD. Click **No** to not propagate reason codes and string-valued database items from the ACD group to the ACD.

CMS Supervisor displays a success message.

7. Click OK.

CMS Supervisor displays an updated list of items.

8. Click **Back to Group List** to get back to the list of ACD groups administered for the current ACD.

### Deleting an ACD from an ACD group using the Web Client

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

#### Procedure

1. Navigate to Administration > Call Center Administration > ACD Groups.

CMS Supervisor displays the list of ACD groups administered for the system.

2. Click Group Contents for one of the ACD groups.

CMS Supervisor displays the list of ACDs administered for the ACD group.

3. Click **Remove** on the ACD you want to remove from the group.

CMS Supervisor displays the Confirm Delete window.

- 4. Click **Yes** to delete the ACD from the ACD group and delete ACD group synonyms from the ACD. Click **No** to delete the ACD from the ACD group but not delete ACD group synonyms from the ACD.
- 5. Click **OK**.

CMS Supervisor displays an updated list of items.

6. Click **Back to Group List** to get back to the list of ACD groups administered for the current ACD.

### Deleting an ACD group using the Web Client

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

#### Procedure

- Navigate to Administration > Call Center Administration > ACD Groups.
   CMS Supervisor displays the list of ACD groups administered for the system.
- 2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

3. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

4. Click **OK**.

CMS Supervisor displays an updated list of items.

### Listing ACD groups using the PC Client

#### About this task

This topic provides the procedure for listing all ACD groups defined on the CMS server.

Listing all ACD groups can be done through either the Call Center Administration or Dictionary subsystems. Only those CMS users who have "read" permission for the Call Center Administration subsystem can use the procedure listed below. CMS users who only work with synonyms or running reports should use the procedure associated with the Dictionary subsystem for listing all ACD groups.

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **ACD Groups**.
- 3. Click **OK**.

CMS Supervisor displays the Call Center Administration ACD Groups window.

- 4. From the menu bar, select **Edit** > **Clear All** to remove any data from the fields.
- 5. Select Actions > List all.

Supervisor displays a dialog listing the ACD groups defined on this CMS server.

### Viewing the contents of an ACD group using the PC Client

#### About this task

This topic provides the procedure for displaying the contents of an ACD group.

Viewing the contents of an ACD group can be done through either the Call Center Administration or Dictionary subsystems. Only those CMS users who have "read" permission for the Call Center Administration subsystem can use the following procedure. CMS users who only work with synonyms or running reports should use the procedure in <u>About administering ACD Groups in the Dictionary</u> on page 49.

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **ACD Groups**.
- 3. Click OK.

CMS Supervisor displays the Call Center Administration ACD Groups window.

4. In the ACD Group Name field, enter the name of the ACD group you want to view.

😵 Note:

If you are unsure of the name of the ACD group, use <u>Listing ACD groups using the PC</u> <u>Client</u> on page 153 to determine the name.

5. From the menu bar, select **Actions > Find one**.

If the ACD group name is valid, its numeric ID is displayed in the ACD Group Number field and 1 matches found is displayed in the status bar.

#### 6. Select Actions > Get contents.

Supervisor displays the Call Center Admin ACD Groups Get contents dialog.

7. In the ACD drop-down list box, select (none).

😵 Note:

If you do not select the **(none)** item, only the selected item in the ACD list will be displayed in the resulting dialog if it is a member of the specified ACD group. If it is not a member of the ACD group, the resulting dialog will be blank.

8. From the menu bar, select **Actions > List all**.

Supervisor displays the Call Center Admin ACD Groups Get Contents List All dialog showing all ACDs that are members of this ACD group.

### Adding an ACD group using the PC Client

#### About this task

Use this procedure to create an ACD group. After creating an ACD group, add member ACDs using the procedure Adding an ACD to an ACD group using the PC Client on page 155.

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

#### Procedure

1. From the Controller window, select **Commands** > **Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **ACD Groups**.
- 3. Click OK.

CMS Supervisor displays the Call Center Administration ACD Groups window.

- 4. In the **ACD Group Name** field, enter a name for this new ACD group.
- 5. From the menu bar, select **Actions > Add**.

CMS creates the ACD group and assigns an ACD group number.

### Adding an ACD to an ACD group using the PC Client

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

This procedure can only be done after an ACD group has been created. See <u>Adding an ACD</u> group using the PC Client on page 155 for more information.

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **ACD Groups**.
- 3. Click OK.

CMS Supervisor displays the Call Center Administration ACD Groups window.

- 4. In the **ACD Group Name** field, enter the name of the ACD group that will receive a new ACD member.
- 5. Select **Actions > Find one** from the menu bar.

If the ACD group name is valid, its numeric ID is displayed in the ACD Group Name field and 1 matches found is displayed in the status bar.

6. From the menu bar, select **Actions > Get contents**.

Supervisor displays the Call Center Admin ACD Groups Get contents dialog.

7. From the **ACD** drop-down list box, select the ACD that will be added to this group.

Note:

If a CMS user does not have read and write permissions for an ACD, that ACD will not appear in this list. To view all of the ACDs assigned to this ACD group, see <u>Viewing the contents of an ACD group using the PC Client</u> on page 154.

8. Select Actions > Add from the menu bar.

The selected ACD is added to this ACD group and  ${\tt Successful}$  is displayed in the status bar.

### Modifying an ACD group name using the PC Client

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **ACD Groups**.
- 3. Click **OK**.

CMS Supervisor displays the Call Center Administration ACD Groups window.

4. In the **ACD Group Name** field, enter the name of the ACD group to change.

If you do not know the name of the ACD group, use the procedure, <u>Listing ACD groups</u> using the PC Client on page 153.

5. From the menu bar, select **Actions > Find one**.

If the ACD group name is valid, its numeric ID is displayed in the ACD Group Number field and 1 matches found is displayed in the status bar.

6. In the **ACD Group Name** field, change the name of this ACD group.

See <u>Before using ACD groups</u> on page 147 for information on naming conventions.

7. When you have finished changing the name of the ACD group, select **Actions** > **Modify** from the menu bar.

The modification for the ACD group is made to the CMS database and Successful is displayed in the status bar.

### Deleting an ACD from an ACD group using the PC Client

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **ACD Groups**.
- 3. Click OK.

CMS Supervisor displays the Call Center Administration ACD Groups window.

4. In the **ACD Group Name** field, enter the name of the ACD group from which you want to delete a member ACD.

😵 Note:

If you are unsure of the name of the ACD group, use the procedure, <u>Listing ACD</u> groups using the PC Client on page 153.

5. From the menu bar, select **Actions > Get contents**.

Supervisor displays the Call Center Admin ACD Groups Get contents dialog.

6. In the **ACD** drop-down list box, select the ACD to remove from this ACD group.

😵 Note:

If a CMS user does not have read and write permissions for an ACD, that ACD will not appear in this list. To view all of the ACDs assigned to this ACD group, see <u>Viewing the contents of an ACD group using the PC Client</u> on page 154.

7. From the menu bar, select **Actions > Find one**.

If the select ACD is a member of the specified ACD group, 1 matches found is displayed in the status bar.

8. Select Actions > Delete.

The selected ACD is removed from the specified ACD group and CMS Supervisor displays a message box asking if the synonyms assigned to this ACD should be removed as well.

9. Select the **OK** button to remove all synonyms that were assigned to this ACD through ACD group administration.

Otherwise, select **NO** to preserve all synonyms on the ACD.

### Deleting an ACD group using the PC Client

#### Before you begin

Before doing this procedure, you should ensure that you have read and understood <u>Before using</u> <u>ACD groups</u> on page 147.

CMS must be in single-user mode to administer ACD groups.

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **ACD Groups**.
- 3. Click OK.

CMS Supervisor displays the Call Center Administration ACD Groups window.

4. In the ACD Group Name field, enter the name of the ACD group to delete.

If you do not know the name of the ACD group, you can find it using the procedure, <u>Listing</u> <u>ACD groups using the PC Client</u> on page 153.

5. Select **Actions > Find one** from the menu bar.

If the ACD group name is valid, its numeric ID is displayed in the ACD Group Number field and 1 matches found is displayed in the status bar.

6. Select Actions > Delete.

The specified ACD group is deleted from the CMS server.

### About administering call work codes

A call work code (CWC) is a number that represents a particular call type or activity to track in the call center, for example, promotional ads, complaints, or repeat orders. Agents use the dial pad on their voice terminal to enter call work codes. This information is sent to CMS for management reporting and can then be viewed in the call work code and call record historical reports.

#### 😵 Note:

Some telephony applications that are used on PCs require that digits be entered through the software interface instead of the dial pad on the voice terminal.

### Before using call work codes

The following items should be read and understood before beginning to work with call work codes:

- Call work codes must be positive integers with 1 to 16 digits. It is recommended that a fixed number of digits be used consistently for all call work codes. The use of a consistent number of digits makes it easier to add, delete, and search for call work codes.
- Call work code 0 is always assigned and is used to collect information on unassigned call work codes. Call work code 0 cannot be deleted. If an agent enters an unassigned call work code, it is displayed as code 0 on the call work code report. If a call work code exception is defined, the agent exceptions historical report shows the agents who entered invalid or unassigned call work codes.
- Disk space must be allocated for call work codes before they can be used. Call work codes are assigned to a specific ACD. The number of call work codes that can be assigned depends on the Data Storage Allocation settings for the ACD. See <u>About administering Data</u> <u>Storage Allocation</u> on page 336 for more information.
- Daily, weekly, and monthly standard historical reports are available for call work codes. Call work codes also appear on the standard historical call record report. For more information, see *Avaya CMS Supervisor Reports*.
- For standard call work code reports, the codes are assigned in the Call Work Codes window.
- To have a name refer to a call work code in a report instead of its numerical code, the name must first be assigned in the Dictionary.

### Permissions required to administer call work codes

Depending on the procedure to be performed, the following permissions are needed:

- To view call work codes, the user ID used to log in to this Supervisor session requires "read" permission for the Call Center Administration subsystem.
- To add or delete call work codes, the user ID used to log in to this Supervisor session requires "read" and "write" permission for the Call Center Administration subsystem.

### Viewing call work codes using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > Call Work Codes.

CMS Supervisor displays the list of call work codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer call work codes.

CMS Supervisor displays the list of call work codes administered for the selected ACD.

### Adding call work codes using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > Call Work Codes.

CMS Supervisor displays the list of call work codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer call work codes.

CMS Supervisor displays the list of call work codes administered for the selected ACD.

3. Click Add Call Work Code(s).

CMS Supervisor displays the Add Call Work Code(s) window.

4. In the **Call Work Codes** field, enter one or more call work codes that you want to add to the system. Separate entries using a semicolon (;).

The system displays each code in the Search Results pane.

- 5. Click each code that you want to add to the system to move it into the **Selected Call Work Code(s)** pane.
- 6. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

7. Click OK.

CMS Supervisor displays an updated list of items.

### Deleting call work codes using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > Call Work Codes.

CMS Supervisor displays the list of call work codes administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer call work codes.

CMS Supervisor displays the list of call work codes administered for the selected ACD.

- 3. Do one of the following to delete call work codes:
  - To delete call work codes one at a time:
    - Click **Remove** for the call work code you want to remove. CMS Supervisor displays the Confirm Delete window.
    - Click **Yes** to continue with the change. Click **Cancel** to cancel the operation.
  - To delete multiple call work codes in one operation:
    - Click **Remove Call Work Code(s)**. CMS Supervisor displays the Remove Call Work Code(s) window.
    - In the **Call Work Codes** field, enter one or more call work codes that you want to delete from the system. Separate entries using a semicolon (;). The system displays each code in the **Search Results** pane.
    - Click each code that you want to delete from the system to move it into the **Selected Call Work Code(s)** pane.
    - Click OK.
- 4. Click OK.

CMS Supervisor displays an updated list of items.

#### Viewing call work codes using the PC Client Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **Call Work Code**.
- 3. Click **OK**.

CMS Supervisor displays the Call Work Codes window.

- 4. Enter the call work code to view in the Call work code(s) field.
- 5. Select Actions > Find one.

If the call work code exists in the CMS database, the status bar displays the message, 1  $\tt matches\ found.$ 

### Listing all call work codes using the PC Client

#### Procedure

From the Controller window, select Commands > Call Center Administration.
 CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **Call Work Code**.
- 3. Click OK.

CMS Supervisor displays the Call Work Codes window.

4. Select **Actions** > **List all**.

Supervisor displays a secondary window that lists all call work codes having a synonym in the Dictionary.

### Adding call work codes using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **Operations** list, highlight **Call Work Code**.
- 3. Click **OK**.

CMS Supervisor displays the Call Work Codes window.

The following fields are displayed in the Call Work Codes window:

- Number of codes allocated Total number of call work codes that exist in the CMS database
- Number of codes administered Total number of call work codes currently in use
- Call work code(s): Used to specify a call work code that will receive an action
- 4. Enter the new call work code in the **Call work code(s)** field.
- 5. Select **Actions** > **Add**.

The status bar displays Successful if the call work code is added to the CMS database.

### Deleting call work codes using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the Operations list, highlight Call Work Code.
- 3. Click **OK**.

CMS Supervisor displays the Call Work Codes window.

4. Enter the call work code that you want to delete in the **Call work code(s)** field.

#### 5. Select **Actions > Find one**.

If the specified call work code is found in the CMS database, the status bar displays the message, 1 matches found.

#### 6. Select Actions > Delete.

The status bar displays Successful if the call work code is deleted from the CMS database.

### About administering VDN skill preferences

A Vector Directory Number (VDN) is an extension number that enables calls to connect to a vector for processing. A VDN is not assigned an equipment location, but is assigned to a vector. A VDN can connect calls to a vector when the calls arrive over an assigned automatic-in trunk group or when calls arrive over a dial-repeating, Direct-Inward-Dialing (DID) trunk group and the final digits match the VDN. The VDN, by itself, may be dialed to access the vector from any extension that is connected to the switch.

Calls use VDN skills for routing based on the preferences that are assigned. The skill preferences are used in the assigned vector as 1st, 2nd, and 3rd.

This section describes the procedures to change the first, second, and third skill preferences assigned to a VDN. You can also list the currently assigned skill preferences for VDNs as well as list all the VDNs that currently have skill preferences assigned to them.

### Before using VDN skill preferences

The following items should be read and understood before working with VDN skill preferences:

- You can only work with VDN skill preferences on a Communication Manager system and the Expert Agent Selection (EAS) feature is present and activated.
- When VDN skill preferences are changed through Supervisor, the change takes place immediately on the Communication Manager system. This can affect the processing of calls at the time of the change.
- If the changes to VDN skill preferences should occur at a specific time, they can be run through scripts that can then be scheduled through a third-party scheduling application.

### Permissions required to administer VDN skill preferences

Depending on the procedure that you want to perform, you need the following permissions:

• To view current VDN skill preferences, the user ID used to log in to this Supervisor session requires "read" permission for the Call Center Administration subsystem and the affected VDNs.

• To change VDN skill preferences, the user ID used to log in to this Supervisor session requires "write" permission for the Call Center Administration subsystem and the affected VDNs.

### Viewing VDN skill preferences using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > Change VDN Skill Preferences.

CMS Supervisor displays the list of VDNs and skill preferences administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDNs skill preferences.

CMS Supervisor displays the list of VDNs and skill preferences administered for the selected ACD.

### **Changing VDN skill preferences using the Web Client**

#### Procedure

1. Navigate to Administration > Call Center Administration > Change VDN Skill Preferences.

CMS Supervisor displays the list of VDNs and skill preferences administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDNs skill preferences.

CMS Supervisor displays the list of VDNs and skill preferences administered for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

4. **(Optional)** Enter additional VDN names or IDs in the **VDNs** field. Do this only if you want to assign the same skill preferences to additional VDNs in addition to the VDN you originally selected. Separate entries using a semicolon (;).

The system displays each VDN in the **Search Results** pane.

- 5. **(Optional)** Click each VDN to which you want to assign the same skills and move it into the **Selected VDN(s)** pane.
- 6. Enter up to three preferred skills into the Skill Preferences fields.
- 7. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

8. Click OK.

CMS Supervisor displays an updated list of items.

### Viewing VDN skill preferences using the PC Client

#### Procedure

- From the Controller window, select Commands > Call Center Administration.
   Supervisor displays the Call Center Administration window.
- 2. In the ACD field, select the ACD on which VDN skill preferences will be viewed.
- 3. In the Operations list, highlight Change VDN Skill Preferences.
- 4. Select OK.

Supervisor displays the Change VDN Skill Preferences window.

- 5. In the **VDNs** field, enter the VDN for which skill preferences are to be viewed.
- 6. Select **Actions > Find one**.

The status bar displays a successful message if the VDN was found and lists the skill preferences, if any exist for this VDN.

### Listing all VDN skill preferences using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

Supervisor displays the Call Center Administration window.

- 2. In the **ACD** field, select the ACD on which the VDNs and their skill preferences will be viewed.
- 3. In the **Operations** list, highlight **Change VDN Skill Preferences**.
- 4. Select OK.

Supervisor displays the Change VDN Skill Preferences window.

5. Select **Actions** > **List all**.

Supervisor displays a window listing all VDNs on this ACD and the associated skill preferences.

### Changing VDN skill preferences using the PC Client Procedure

- From the Controller window, select Commands > Call Center Administration.
   Supervisor displays the Call Center Administration window.
- 2. In the ACD field, select the ACD on which VDN skill preferences will be changed.
- 3. In the **Operations** list, highlight **Change VDN Skill Preferences**.
- 4. Select OK.

Supervisor displays the Change VDN Skill Preferences window.

- 5. In the **VDNs** field, enter the VDN for which skill preferences are to be changed.
- 6. Select Actions > Find one.

The status bar displays a successful message if the VDN was found.

- 7. Enter skill preferences for the VDN in the **1st**, **2nd**, and **3rd** fields using one of the following methods:
  - Enter the skill name or number.
  - · Select the skill name or number from the drop-down list.
  - Use the Browse button at the right of each field to select a skill.
- 8. Select Actions > Modify.

The status bar displays a successful message when the operation completes.

### About administering split or skill call profiles

Call profiles are settings for a split or skill that assist in determining how much time passes before a call is answered or abandoned. The accumulated number of seconds that have passed for an unanswered call are divided into different service-level increments. If a call surpasses the time that is allowed for the first service-level increment, it then moves to the next service-level increment. This information is recorded for each call and can later be viewed through the split/skill call profile report to determine the number of calls that were answered or abandoned in each increment.

### Before using split or skill call profiles

The following items should be read and understood before working with split or skill call profiles:

• Each service-level increment value can be set to a different length of time in seconds.

- Each of the first nine service-level increments can have a different time length and represents a unit of wait time. The number of seconds for the second through the ninth increment must be at least 1 second greater than the number of seconds in the previous increment.
- CMS counts the calls that are either answered or abandoned within each increment and shows the totals on split or skill call profile reports. Therefore, the settings of these increments affect what is displayed in reports.
- Making changes to the service level field after data was collected with a different service level value causes reports to give inaccurate data for the **Percent within Service Level** value. If you must change the service level, it is best to change the value at midnight on the first day of a month so that data for the entire month is gathered using the same service level value.

### Permissions required to administer split or skill call profiles

Depending on the procedure that you want to perform, you need the following permissions:

- To view split or skill call profiles, the user ID used to log in to this Supervisor session requires "read" permission for the Call Center Administration subsystem and all affected splits and skills.
- To add, delete, or change a split or skill call profile, the user ID used to log in to this Supervisor session requires "write" permission for the Call Center Administration subsystem and all affected splits and skills.

### Viewing split or skill call profiles using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > Split/Skill Call Profile Setup.

CMS Supervisor displays the list of split or skill call profiles administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer split or skill call profiles.

CMS Supervisor displays the list of split or skill call profiles administered for the selected ACD.

### Adding split or skill call profiles using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > Split/Skill Call Profile Setup.

CMS Supervisor displays the list of split or skill call profiles administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer split or skill call profiles.

CMS Supervisor displays the list of split or skill call profiles administered for the selected ACD.

3. Click Add Split(s)/Skill(s).

CMS Supervisor displays the Add Split(s)/Skill(s) window.

4. In the **Split/Skill** field, enter one or more split or skill names or IDs that you want to add to the system. Separate entries using a semicolon (;).

The system displays each entry in the **Search Results** pane.

- 5. Click each name or ID that you want to administer to move it into the **Selected Split(s)**/ **Skill(s)** pane.
- 6. In the Acceptable service level field, enter the speed of answer objective for the profile.

Acceptable service level represents the maximum number of seconds it should take for a call to be answered. Valid values are 0 to 9999. This value should be no larger than the number of seconds in the intrahour interval that is set on CMS. For example, 1800 for a 30-minute intrahour interval or 3600 for a 60-minute intrahour interval. You must enter a value in this field.

7. In the **Service Level Increments (seconds)** fields, enter a progressively greater number of seconds in each **To** field. Each field can support values from 0 to 999.

If the unanswered call surpasses the time limit for an increment, it moves on to the next increment. For example, 0 to 5 to 10 to 25 represents 0 to 5 seconds, 6 to 10 seconds, and 11 to 25 seconds.

Each of the nine increments can vary in length. For example, 0 to 15, 16 to 20, 21 to 26, 27 to 38, 39 to 43, and so forth.

8. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

9. Click **OK**.

CMS Supervisor displays an updated list of items.

### Modifying a split or skill call profile using the Web Client Procedure

1. Navigate to Administration > Call Center Administration > Split/Skill Call Profile Setup.

CMS Supervisor displays the list of split or skill call profiles administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer split or skill call profiles.

CMS Supervisor displays the list of split or skill call profiles administered for the selected ACD.

3. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

4. In the **Acceptable service level** field, enter the speed of answer objective for the profile.

Acceptable service level represents the maximum number of seconds it should take for a call to be answered. Valid values are 0 to 9999. This value should be no larger than the number of seconds in the intrahour interval that is set on CMS. For example, 1800 for a 30-minute intrahour interval or 3600 for a 60-minute intrahour interval. You must enter a value in this field.

5. In the **Service Level Increments (seconds)** fields, enter a progressively greater number of seconds in each **To** field. Each field can support values from 0 to 999.

If the unanswered call surpasses the time limit for an increment, it moves on to the next increment. For example,  $0 \pm 5 \pm 10 \pm 25$  represents 0 to 5 seconds, 6 to 10 seconds, and 11 to 25 seconds.

Each of the nine increments can vary in length. For example, 0 to 15, 16 to 20, 21 to 26, 27 to 38, 39 to 43, and so forth.

6. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a message warning you about any issues that may arise with the change you are making.

7. Click **Yes** to continue with the change. Click **No** to cancel the operation.

CMS Supervisor displays a confirmation message.

8. Click **OK**.

CMS Supervisor displays an updated list of items.

### Deleting a split or skill call profile using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > Split/Skill Call Profile Setup.

CMS Supervisor displays the list of split or skill call profiles administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer split or skill call profiles.

CMS Supervisor displays the list of split or skill call profiles administered for the selected ACD.

- 3. Do one of the following to delete split or skill call profiles:
  - To delete split or skill call profiles one at a time, click **Remove** for each split or skill call profiles you want to remove.
  - To delete multiple split or skill call profiles in one operation:
    - Click **Remove Split(s)/Skill(s)**. CMS Supervisor displays the Remove Split(s)/Skill(s) window.
    - In the **Split/Skill** field, enter one or more split or skill call profiles that you want to delete from the system. Separate entries using a semicolon (;). The system displays each code in the **Search Results** pane.
    - Click each split or skill call profile that you want to delete from the system to move it into the **Selected Split(s)/Skill(s)** pane.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

### Viewing split or skill call profiles using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **ACD** field, select the ACD on which the existing split or skill call profile resides.
- 3. In the **Operations** list, highlight **Split/Skill Call Profile Setup**.
- 4. Click OK.

CMS Supervisor displays the Split/Skill Call Profile Setup window.

- 5. In the **Split(s)/Skill(s)** field, enter the split or skill that is represented by the call profile to view.
- 6. From the Actions menu, select Find one.

The status bar displays a Successful message if the call profile for the specified split or skill is found. Additionally, Supervisor populates the **Service Level Increments (seconds)** fields with the service level increments for this call profile.

### Adding split or skill call profiles using the PC Client Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the ACD field, select the ACD on which the new split or skill call profile will be created.
- 3. In the **Operations** list, highlight **Split/Skill Call Profile Setup**.
- 4. Click OK.

CMS Supervisor displays the Split/Skill Call Profile Setup window.

- 5. In the **Split(s)/Skill(s)** field, enter the split or skill numbers or names.
- 6. In the Acceptable service level field, enter the speed of answer objective for the profile.

Acceptable service level represents the maximum number of seconds it should take for a call to be answered. Valid values are 0 to 9999. This value should be no larger than the number of seconds in the intrahour interval that is set on CMS. For example, 1800 for a 30-minute intrahour interval or 3600 for a 60-minute intrahour interval. You must enter a value in this field.

7. In the **Service Level Increments (seconds)** fields, enter a progressively greater number of seconds in each **To** field. Each field can support values from 0 to 999.

If the unanswered call surpasses the time limit for an increment, it moves on to the next increment. For example,  $0 \pm 5 \pm 10 \pm 25$  represents 0 to 5 seconds, 6 to 10 seconds, and 11 to 25 seconds.

Each of the nine increments can vary in length. For example, 0 to 15, 16 to 20, 21 to 26, 27 to 38, 39 to 43, and so forth.

The following example displays how an administrator might set up a call profile:

Acceptable service level: 1800							
Service level increments (seconds):							
Inc 1	Inc 2	Inc 3	Inc 4	Inc 5			
0 to 5	to 15	5 to [	30 to	60 <b>to</b> 90			
Inc 6 to 120	Inc 7 to 18	Inc 8 30 to [	Inc 9 240 to	Inc 10 360 and above			

In this example, the **Acceptable service level** field is set to 1800 seconds to correspond with the intrahour interval on the CMS server.

Inc 1 has been set for the range of  $0 \pm 0.5$  seconds. Inc 2 ranges covers  $5 \pm 0.15$  seconds. The other service level increments continue on until Inc 10. This last service level increment is used in this example is for those calls that extend beyond 360 seconds. If a call is not answered after the acceptable service level of 1800 seconds, the call is then tracked in a different CMS database category.

#### 8. Select Actions > Add.

The status bar displays a message stating if the operation succeeded or failed.

### Modifying a split or skill call profile using the PC Client Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **ACD** field, select the ACD on which the split or skill call profile to modify resides.
- 3. In the **Operations** list, highlight **Split/Skill Call Profile Setup**.
- 4. Click OK.

CMS Supervisor displays the Split/Skill Call Profile Setup window.

- 5. In the **Split(s)/Skill(s)** field, enter the split or skill on which the call profile to modify resides.
- 6. Select **Actions > Find one**.

The status bar displays a Successful message if the call profile for the specified split or skill is found. Additionally, Supervisor populates the **Service Level Increments (seconds)** fields with the service level increments for this call profile.

7. In the Acceptable service level field, enter the speed of answer objective for the profile.

Acceptable service level represents the maximum number of seconds it should take for a call to be answered. Valid values are 0 to 9999. This value should be no larger than the number of seconds in the intrahour interval that is set on CMS. For example, 1800 for a 30-minute intrahour interval or 3600 for a 60-minute intrahour interval. You must enter a value in this field.

8. In the **Service Level Increments (seconds)** fields, enter a progressively greater number of seconds in each **To** field. Each field can support values from 0 to 999.

If the unanswered call surpasses the time limit for an increment, it moves on to the next increment. For example, 0 to 5 to 10 to 25 represents 0 to 5 seconds, 6 to 10 seconds, and 11 to 25 seconds.

Each of the nine increments can vary in length. For example, 0 to 15, 16 to 20, 21 to 26, 27 to 38, 39 to 43, and so forth.

The following example displays how an administrator might set up a call profile:

Acceptable service level: 1800							
Service level increments (seconds):							
Inc 1	Inc 2	Inc 3	Inc 4	Inc 5			
0 to	5 to	15 to	30 to	60 <b>to</b> 90			
Inc 6	Inc 7	Inc 8	Inc 9	Inc 10			
to	120 <b>to</b>	180 to	240 to	360 and above			

In this example, the **Acceptable service level** field is set to 1800 seconds to correspond with the intrahour interval on the CMS server.

Inc 1 has been set for the range of  $0 \pm 0.5$  seconds. Inc 2 ranges covers  $5 \pm 0.15$  seconds. The other service level increments continue on until Inc 10. This last service level increment is used in this example is for those calls that extend beyond 360 seconds. If a call is not answered after the acceptable service level of 1800 seconds, the call is then tracked in a different CMS database category.

9. From the Actions menu, select Modify.

The status bar displays a Successful message when the operation completes.

### Deleting a split or skill call profile using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **ACD** field, select the ACD on which the split or skill call profile to delete resides.
- 3. In the **Operations** list, highlight **Split/Skill Call Profile Setup**.
- 4. Click OK.

CMS Supervisor displays the Split/Skill Call Profile Setup window.

- 5. In the **Split(s)/Skill(s)** field, enter the split or skill on which the call profile to delete resides.
- 6. From the Actions menu, select Find one.

The status bar displays a Successful message if the call profile for the specified split or skill is found. Additionally, Supervisor populates the **Service Level Increments (seconds)** fields with the service level increments for this call profile.

7. From the Actions menu, select Delete.

Supervisor deletes the specified split or skill call profile and displays a <code>Successful</code> message in the status bar.

### About viewing trunk group assignments

A trunk group is a group of circuits that are assigned the same dialing digits, either a telephone number or a Direct-Inward-Dialing (DID) prefix. Trunk groups can be assigned to Vector Directory Numbers (VDNs) or non-vector-controlled splits. Use these procedures to view those trunk group assignments using CMS Supervisor.

### Before viewing trunk group assignments

The following items should be read and understood before viewing trunk group assignments:

- You cannot use these procedures to change trunk group assignments. Changing trunk group assignments is done through an administration tool for the Communication Manager system.
- Automatic-in trunk groups, such as those that are used as Listed Directory Numbers, must be assigned to VDNs or splits through an administration tool for the Communication Manager system.
- DID or dial-repeating trunks, such as those that toll-free numbers are assigned to, are not assigned to VDNs or splits since the Central Office (CO) passes VDN digits or the split extension number to the Communication Manager system. Because of this, toll-free numbers do not appear during these procedures.
- Vector-controlled splits cannot have trunk groups assigned to them because they can only receive calls through vector processing.

### Permissions required to view trunk group assignments

To view trunk group assignments, the user ID must have "read" permission for the Call Center Administration subsystem and for all affected trunk groups, splits, and VDNs.

### Viewing trunk group assignments using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > Trunk Group Assignments.

CMS Supervisor displays the list of trunk groups assigned for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to view the trunk groups assigned.

CMS Supervisor displays the list of trunk groups assigned for the selected ACD.

### Viewing all trunk group assignments using the PC Client Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **ACD** field, select the ACD on which trunk group assignments are to be viewed.
- 3. In the **Operations** list, highlight **Trunk Group Assignments**.
- 4. Click OK.

Supervisor displays the Trunk Group Assign window.

5. With all fields blank, select **Actions** > **List all**.

Supervisor displays the Trunk Group Assignments - List All window showing all trunk groups and their current assignments.

6. To clear all fields of information, select Edit > Clear All.

### Viewing a single trunk group assignment using the PC Client Procedure

- From the Controller window, select Commands > Call Center Administration.
   CMS Supervisor displays the Call Center Administration window.
- 2. In the **ACD** field, select the ACD for which trunk group assignments are to be viewed.
- 3. In the **Operations** list, highlight **Trunk Group Assignments**.
- 4. Click OK.

Supervisor displays the Trunk Group Assign window.

5. In the **Trunk Groups** field, enter the trunk group for which assignments are to be viewed.

More than one trunk group can be entered in this field. Multiple trunk groups must be separated with a semicolon (;).

6. Select **Actions > Find one**.

The VDN or split assignment for the specified trunk group is displayed in the corresponding field.

If a VDN or split is not assigned to this trunk group, the status bar displays 0  $\,\, \tt matches$  found.

## Viewing a trunk group assignment by VDN or split using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **ACD** field, select the ACD for which trunk group assignments are to be viewed.
- 3. In the **Operations** list, highlight **Trunk Group Assignments**.
- 4. Click OK.

Supervisor displays the Trunk Group Assign window.

Either a VDN or split can be specified to display the trunk group or groups assigned to it. Complete one of the following two steps.

- 5. To display the trunk groups that are assigned to a VDN:
  - a. In the Select one group, select VDN.
  - b. Enter the VDN number or name in the field for the **VDN** option.
- 6. To display the trunk groups that are assigned to a split:
  - a. In the Select one group, select Split.
  - b. Enter the split number or name in the field for the **Split** option.
- 7. Select **Actions > Find one**.

Supervisor displays the first trunk group that is assigned to the specified VDN or split in the **Trunk Groups** field. If more trunk groups are currently assigned, click the **Next** button to view them.

### About administering VDN assignments

A Vector Directory Number (VDN) is an extension number that enables incoming calls to be connected to a vector for processing. The VDN by itself may be dialed to access the vector from any extension that is connected to the Communication Manager system.

Initial assignment of a VDN to a vector is done on the Communication Manager system, but can later be changed using CMS Supervisor.

### **Before using VDN assignments**

The following items should be read and understood before working with VDN assignments:

- · Changing any VDN-to-vector assignments can alter call processing
- Multiple VDNs can be assigned to the same vector.
- VDNs cannot be assigned to more than one vector.
- You cannot exit the VDN-to-vector assignment window until Supervisor receives a response to the requested change.
- Calls that are already in vector processing are not affected by a VDN-to-vector change.
- Changing the VDN-to-vector assignment affects the next call that enters the VDN.
- VDN-to-vector assignment changes that are scheduled should either be grouped together in a timetable or individually scheduled so that one assignment completes before the next assignment change request is scheduled.

### Permissions required to administer VDN assignments

Depending on the procedure that you want to perform, you need the following permissions:

- To view VDN assignments, the user ID must have "read" permission for the Call Center Administration subsystem and for all affected VDNs and vectors.
- To modify VDN assignments, the user ID must have "write" permission for the Call Center Administration subsystem and for all affect VDNs and vectors.

### Administering VDN assignments using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > VDN Assignments.

CMS Supervisor displays the list of VDNs administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDNs.

CMS Supervisor displays the list of VDNs administered for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

4. **(Optional)** Enter additional VDN names or IDs in the **VDNs** field. Do this only if you want to assign the same vectors to additional VDNs in addition to the VDN you originally selected. Separate entries using a semicolon (;).

The system displays each VDN in the **Search Results** pane.

- 5. (**Optional**) Click each VDN to which you want to assign the same vector and move it into the **Selected VDN(s)** pane.
- 6. Enter up to three preferred skills into the Skill Preferences fields.
- 7. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

8. Click OK.

CMS Supervisor displays an updated list of items.

### Viewing VDN assignments using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the ACD field, select the ACD for which VDN-to-vector assignments are to be viewed.
- 3. In the **Operations** list, highlight **VDN Assignments**.
- 4. Click OK.

CMS Supervisor displays the VDN Assignments window.

5. Select Actions > List all from the menu bar.

CMS Supervisor displays a secondary window that lists all VDNs for which this user ID has "read" permission.

### Listing VDNs associated with a vector using the PC Client

#### Procedure

- From the Controller window, select Commands > Call Center Administration.
   CMS Supervisor displays the Call Center Administration window.
- 2. In the **ACD** field, select the ACD on which the vector resides.
- 3. In the **Operations** list, highlight **VDN Assignments**.
- 4. Click **OK**.

CMS Supervisor displays the VDN Assignments window.

- 5. In the Vector field, enter the name or number of the vector.
- 6. Select **Actions** > **List all** from the menu bar.

CMS Supervisor displays a secondary window that lists all VDNs assigned to the specified vector.

### About administering VDN call profiles

Call profiles are time ranges for a VDN that CMS uses to track how much time passes before a call is resolved by being answered, connected to a non-ACD destination, or abandoned. CMS refers to these time ranges as "service-level increments".

The accumulated number of seconds that pass for an unanswered call are divided into different service-level increments. If a call surpasses the time that is allowed for the first service-level increment, it then moves to the next service-level increment. This information is recorded for each call and can later be viewed through the VDN call profile reports to determine the number of calls that were addressed in each increment.

Use these procedures to view, add, change, and delete VDN call profiles.

### **Before using VDN call profiles**

The following items should be read and understood before work is done with VDN call profiles.

- When installed, CMS sets all service-level increments to 0 by default. This causes all calls to appear in the first increment on the VDN call profile report.
- Each service level can be set to different lengths of time.
- Service-level increments can only be used to categorize a call to a maximum limit of 999 seconds.
- The number of seconds for the second through the ninth increment must be at least 1 second greater than the number of seconds in the previous increment. For example, if the second increment covers the range of 5 to 10 seconds, the maximum value in the third increment must be set to 11 or greater.
- Making changes to the service level field after data was collected with another service level value causes reports to give inaccurate data for the **Percent within Service Level** value. If you must change the service level, it is best to change the value at midnight on the first day of a month so that data for the entire month is gathered using the same service level value.

### Permissions required to administer VDN call profiles

Depending on the procedure that you want to perform, you need the following permissions:

- To view a VDN call profile, the user must have "read" permission for the Call Center Administration subsystem and all affected VDNs.
- To add, delete, or change a VDN call profile, the user must have "write" permission for the Call Center Administration subsystem and all affected VDNs.

### Viewing a VDN call profile using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > VDN Call Profile Setup.

CMS Supervisor displays the list of VDN call profiles administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDN call profiles.

CMS Supervisor displays the list of VDN call profiles administered for the selected ACD.

### Adding a VDN call profile using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > VDN Call Profile Setup.

CMS Supervisor displays the list of VDN call profiles administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDN call profiles.

CMS Supervisor displays the list of VDN call profiles administered for the selected ACD.

3. Click Add VDNs.

CMS Supervisor displays the Add VDNs window.

4. In the **VDNs** field, enter one or more VDN names or IDs that you want to add to the system. Separate entries using a semicolon (;).

The system displays each entry in the Search Results pane.

- 5. Click each name or ID that you want to administer to move it into the **Selected VDN(s)** pane.
- 6. In the Acceptable service level field, enter the speed of answer objective for the profile.

Acceptable service level represents the maximum number of seconds it should take for a call to be answered. Valid values are 0 to 9999. This value should be no larger than the number of seconds in the intrahour interval that is set on CMS. For example, 1800 for a 30-minute intrahour interval or 3600 for a 60-minute intrahour interval. You must enter a value in this field.

7. In the **Service Level Increments (seconds)** fields, enter a progressively greater number of seconds in each **To** field. Each field can support values from 0 to 999.

If the unanswered call surpasses the time limit for an increment, it moves on to the next increment. For example, 0 to 5 to 10 to 25 represents 0 to 5 seconds, 6 to 10 seconds, and 11 to 25 seconds.

Each of the nine increments can vary in length. For example, 0 to 15, 16 to 20, 21 to 26, 27 to 38, 39 to 43, and so forth.

8. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

9. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying a VDN call profile using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > VDN Call Profile Setup.

CMS Supervisor displays the list of VDN call profiles administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDN call profiles.

CMS Supervisor displays the list of VDN call profiles administered for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

4. In the **Acceptable service level** field, enter the speed of answer objective for the profile.

Acceptable service level represents the maximum number of seconds it should take for a call to be answered. Valid values are 0 to 9999. This value should be no larger than the number of seconds in the intrahour interval that is set on CMS. For example, 1800 for a 30-minute intrahour interval or 3600 for a 60-minute intrahour interval. You must enter a value in this field.

5. In the **Service Level Increments (seconds)** fields, enter a progressively greater number of seconds in each **To** field. Each field can support values from 0 to 999.

If the unanswered call surpasses the time limit for an increment, it moves on to the next increment. For example,  $0 \pm 5 \pm 10 \pm 25$  represents 0 to 5 seconds, 6 to 10 seconds, and 11 to 25 seconds.

Each of the nine increments can vary in length. For example, 0 to 15, 16 to 20, 21 to 26, 27 to 38, 39 to 43, and so forth.

6. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a message warning you about any issues that may arise with the change you are making.

7. Click **Yes** to continue with the change. Click **No** to cancel the operation.

CMS Supervisor displays a confirmation message.

8. Click **OK**.

CMS Supervisor displays an updated list of items.

# Deleting a VDN call profile using the Web Client

#### Procedure

1. Navigate to Administration > Call Center Administration > VDN Call Profile Setup.

CMS Supervisor displays the list of VDN call profiles administered for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDN call profiles.

CMS Supervisor displays the list of VDN call profiles administered for the selected ACD.

- 3. Do one of the following to delete VDN call profiles:
  - To delete VDN call profiles one at a time, click **Remove** for each VDN call profiles you want to remove.
  - To delete multiple VDN call profiles in one operation:
    - Click **Remove VDNs**. CMS Supervisor displays the Remove VDNs window.
    - In the **VDNs** field, enter one or more VDN call profiles that you want to delete from the system. Separate entries using a semicolon (;). The system displays each code in the **Search Results** pane.
    - Click each VDN call profile that you want to delete from the system to move it into the **Selected VDN(s)** pane.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing a VDN call profile using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **ACD** field, select the ACD on which the VDN call profile will be viewed.
- 3. In the **Operations** list, highlight **VDN Call Profile Setup**.
- 4. Click OK.

CMS Supervisor displays the VDN Call Profile Setup window.

5. In the **VDNs** field, enter the name or number of the VDN for which the associated call profile is to be viewed.

6. Select **Actions > Find one** from the menu bar.

Supervisor populates the remaining fields on the VDN Call Profile Setup window with the call profile settings for this VDN. If no call profile has been created for this VDN, the **Service Level Increments (seconds)** values are set to 0.

# Adding a VDN call profile using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the **ACD** field, select the ACD on which the VDN call profile will be added.
- 3. In the **Operations** list, highlight **VDN Call Profile Setup**.
- 4. Click OK.

CMS Supervisor displays the VDN Call Profile Setup window.

- 5. In the **VDNs** field, enter the name or number of the VDN which will have a new call profile.
- 6. In the Acceptable service level field, enter the speed of answer objective for the profile.

Acceptable service level represents the maximum number of seconds it should take for a call to be answered. Valid values are 0 to 9999. This value should be no larger than the number of seconds in the intrahour interval that is set on CMS. For example, 1800 for a 30-minute intrahour interval or 3600 for a 60-minute intrahour interval. You must enter a value in this field.

7. In the **Service Level Increments (seconds)** fields, enter a progressively greater number of seconds in each **To** field. Each field can support values from 0 to 999.

If the unanswered call surpasses the time limit for an increment, it moves on to the next increment. For example, 0 to 5 to 10 to 25 represents 0 to 5 seconds, 6 to 10 seconds, and 11 to 25 seconds.

Each of the nine increments can vary in length. For example, 0 to 15, 16 to 20, 21 to 26, 27 to 38, 39 to 43, and so forth.

The following example displays how an administrator might set up a call profile:

	Acceptable service level: 1800 Service level increments (seconds):					
Inc 1 0 to		c 2 to 15	Inc 3	sj. Inc 4 30 to	Inc 5 60 to 90	_
Inc 6 to [	120	Inc 7 to 18	Inc 8 O to	Inc 9 240 to	Inc 10 360 and abov	/e

In this example, the **Acceptable service level** field is set to 1800 seconds to correspond with the intrahour interval on the CMS server.

Inc 1 has been set for the range of  $0 \pm 0.5$  seconds. Inc 2 ranges covers  $5 \pm 0.15$  seconds. The other service level increments continue on until Inc 10. This last service level increment is used in this example is for those calls that extend beyond 360 seconds. If a call is not answered after the acceptable service level of 1800 seconds, the call is then tracked in a different CMS database category.

8. Select **Actions** > **Add** from the menu bar.

The status bar displays a Successful message when the operation completes.

# Modifying a VDN call profile using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the ACD field, select the ACD on which the VDN call profile will be modified.
- 3. In the **Operations** list, highlight **VDN Call Profile Setup**.
- 4. Click OK.

CMS Supervisor displays the VDN Call Profile Setup window.

- 5. In the **VDNs** field, enter the name or number of the VDN for which the associated call profile is to be modified.
- 6. Select **Actions** > **Find one** from the menu bar.

Supervisor populates the remaining fields on the VDN Call Profile Setup window with the call profile settings for this VDN. If no call profile has been created for this VDN, the **Service Level Increments (seconds)** values are set to 0.

7. In the Acceptable service level field, enter the speed of answer objective for the profile.

Acceptable service level represents the maximum number of seconds it should take for a call to be answered. Valid values are 0 to 9999. This value should be no larger than the number of seconds in the intrahour interval that is set on CMS. For example, 1800 for a 30-minute intrahour interval or 3600 for a 60-minute intrahour interval. You must enter a value in this field.

8. In the **Service Level Increments (seconds)** fields, enter a progressively greater number of seconds in each **To** field. Each field can support values from 0 to 999.

If the unanswered call surpasses the time limit for an increment, it moves on to the next increment. For example,  $0 \pm 5 \pm 10 \pm 25$  represents 0 to 5 seconds, 6 to 10 seconds, and 11 to 25 seconds.

Each of the nine increments can vary in length. For example, 0 to 15, 16 to 20, 21 to 26, 27 to 38, 39 to 43, and so forth.

TI f-I	I		I				administrator		+		11	<b></b>
	IOWIDA	evamn	ie dier	nave	n_\\//	an	administrator	miant		nar	וובי	nrotile
		Crains		лахэ		an	auninistrator	IIIIGIII	SCLU	Jav	Jan	DI UIIIC.

Acceptab	Acceptable service level: 1800						
Service le	evel increment	s (seconds):					
Inc 1	Inc 2	Inc 3	Inc 4	Inc 5			
0 to 🛛	5 to 1	15 to 🗔	30 <b>to</b>	60 to 90			
Inc 6 to [	Inc 7 120 to 1	Inc 8 80 to 2	Inc 9 240 to	Inc 10 360 and above			

In this example, the **Acceptable service level** field is set to 1800 seconds to correspond with the intrahour interval on the CMS server.

Inc 1 has been set for the range of  $0 \pm 0.5$  seconds. Inc 2 ranges covers  $5 \pm 0.15$  seconds. The other service level increments continue on until Inc 10. This last service level increment is used in this example is for those calls that extend beyond 360 seconds. If a call is not answered after the acceptable service level of 1800 seconds, the call is then tracked in a different CMS database category.

9. Select **Actions** > **Modify** from the menu bar.

The status bar displays a Successful message when the operation completes.

# Deleting a VDN call profile using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. In the ACD field, select the ACD on which the VDN call profile will be deleted.
- 3. In the **Operations** list, highlight **VDN Call Profile Setup**.
- 4. Click OK.

CMS Supervisor displays the VDN Call Profile Setup window.

- 5. In the **VDNs** field, enter the name or number of the VDN for which the associated call profile is to be deleted.
- 6. Select **Actions > Find one** from the menu bar.

Supervisor displays the call profile data for the selected VDN in the **Acceptable service level** and **Service Level Increments (seconds)** fields.

7. Select Actions > Delete from the menu bar.

The status bar displays a Successful message when the operation completes.

# Administering a data summarization time zone using the PC Client

#### About this task

To allow for alternative time zone reporting for daily, weekly, and monthly data, a second time zone can be defined to archive the data. This second time zone is in addition to the default ACD time zone, Doing this results in aggregating the data for two different time zones. Each time zone is aggregated based on the boundary of a day for the selected time zone. You can choose one time zone from the possible 600+ time zones to use as the second time zone for an ACD.

If tenant partitioning is installed, the user can define a time zone for each tenant within an ACD and choose from those time zones to have the data additionally aggregated. This results in storing the data in up to three different time zones. With the multi-tenancy feature installed, one time zone per tenant and one additional time zone for the ACD are supported.

In addition, the agent trace and exception data will be stored in UTC/GMT time enabling filtering and reporting of agent trace and exception data based on the time zone selected on CMS Supervisor.

#### 😵 Note:

The administration of time zones does not automatically create the time zone data in the daily, weekly, and monthly tables. The Archiver must run after the time zone is administered.

#### Before you begin

Change the system to single-user state before you do this task.

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

- 2. In the CMS System Setup window, select **Data Summarization Time Zone** in the **Operations** list.
- 3. In the System Setup Data Summarization Time Zone window, do any of the following operations as explained in the table below:

#### 😵 Note:

The System Setup Data Summarization Time Zone window displays the tenant option only if the customer has installed the tenancy feature.

Field	Description
Add	Adds the entry for the selected time zone and the associated ACD and tenant (if the tenancy feature is installed) in the current user window to the database. If an entry already exists, the system displays <code>Already exists</code> on the window status line.
Delete	Removes the entry for the selected time zone and the associated ACD and tenant (if the tenancy feature is installed) in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line.
Find one	Finds an entry in the database that matches the time zone and associated ACD and tenant (if the tenant feature is installed) in the current window. The status line for the current window indicates the total number of matches found.
List all	Lists all the ACDs, tenants and tenant users (if the tenancy feature is installed), and the time zones in the database that match with the values entered in the fields of the current user window.
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.

# Data summarization time zone fields

#### 😵 Note:

The System Setup Data Summarization Time Zone window displays the tenant option only if the customer has installed the tenancy feature.

Field	Description
Add	Adds the entry for the selected time zone and the associated ACD and tenant (if the tenancy feature is installed) in the current user window to the database. If an entry already exists, the system displays <code>Already exists</code> on the window status line.

Table continues...

Field	Description
Delete	Removes the entry for the selected time zone and the associated ACD and tenant (if the tenancy feature is installed) in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line.
Find one	Finds an entry in the database that matches the time zone and associated ACD and tenant (if the tenant feature is installed) in the current window. The status line for the current window indicates the total number of matches found.
List all	Lists all the ACDs, tenants and tenant users (if the tenancy feature is installed), and the time zones in the database that match with the values entered in the fields of the current user window.
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.

# **Chapter 6: Administering call center agents**

# About administering call center agents

This section provides information on using Agent Administration.

The items on the **Agent Administration** menu vary depending on the type of switch that CMS is connected to and the features that are activated on the switch. These procedures include instructions for administering agents in an Automatic Call Distribution (ACD) with and without the Expert Agent Selection (EAS) feature.

# Administering agent skills

# Before changing agent skills

The following items should be read and understood before changing agent skills:

- The Change Agent Skills item is only available for ACDs on which EAS is activated.
- When agent skills are changed, the change is made to the Communication Manager system and remains in effect until another change is made through Supervisor or the Communication Manager system itself.
- When agent skills are changed, you cannot exit the Change Agent Skills window until the ACD responds to the requested agent changes.
- A template can be any existing agent profile where the skill settings of the profile are applied to other agent profiles. You can specify multiple agents individually and by using ranges. Entries must be separated with semicolons. You are limited to 250 characters in this field. After you apply the skill settings, all of the agents specified will have the same skills, levels, interrupt types and percents as the agent profile being used as a template. It is assumed you have the same level of permissions for all agents specified in the change.
- Skill changes take effect immediately for agents who are in AUX work mode, AVAIL (available), or logged out. Changes are pending for agents on calls or in ACW work mode until the agent enters the AUX work mode, becomes available, or logs out. Because of this, agents who frequently have calls on hold may have skill changes remain pending for a longer time than expected.

 Changing agent skills should only be done through Supervisor as it checks if the agent has the appropriate permissions for the newly assigned skills. The CMS ASCII interface does not perform permission checking which can result in agents belonging to skills to which the Supervisor does not have permissions.

# Permissions required to change agent skills

Depending on the procedure that you want to perform, you need the following permissions:

- If you are a tenant user and the tenancy feature is enabled, you need permissions to modify the agent and the agent skills belonging to the tenant to which you are assigned.
- To view agent skill assignments, the user ID used to log in to this Supervisor session requires "read" permission for the Agent Administration subsystem.
- To change agent skills, the user ID used to log in to this Supervisor session requires "write" permission for the Agent Administration subsystem.

😵 Note:

Tenant users can activate or list agent trace for any agent for which they have permission.

# About changing agent skills using the Web Client

Use this administrative procedure to change, add, or delete agent skills for a single agent in CMS Supervisor Web. These features are only available to users with Feature Access Agent Administration read permission. You can modify agent skill assignments only if you have Feature Access Agent Administration write permission.

#### **Related links**

Adding agent skills using the Web Client on page 190 Changing agent skills using the Web Client on page 191 Deleting agent skills using the Web Client on page 192

#### Adding agent skills using the Web Client

#### About this task

Use this task to add agent skills. You can only modify the **LEVEL** and **Interrupt Type** fields if you have write permissions for the skill. Tenant users must have write permission for the agent.

#### Before you begin

Ensure that you select an active ACD. If the ACD link is inactive, you cannot modify the agent skills.

#### Procedure

- 1. Navigate to Administration > Agent Administration > Change Agent Skills.
- 2. In the **Current ACD** drop-down list, select the active ACD for which you want to change the agent skills.

3. In **Agent**, enter an agent name or ID, or use the drop-down list, and select the agent.

The **Agent** drop-down list is limited to a fixed number of results and provides additional choices when you enter the agent name or ID.

4. Click **Add Skill** in the Agent Skills window.

The Add Skill window displays.

- 5. Administer values for the following options:
  - Skill
  - LEVEL
  - Interrupt Type

The **Skill** drop-down list is limited to a fixed number of results and provides additional choices when you type the name or ID.

- 6. Optionally, to apply changes to multiple agents, do the following in the **Select additional agents** field:
  - a. Type the agent name, ID, or range of IDs in the search field. Separate multiple names, IDs, or ranges using semicolons.
  - b. Add the agents from Search Results to Selected Agents.

The default maximum number of agents that you can add to Selected Agents is 99.

7. Click Apply.

The system makes the requested changes to the selected agents.

#### Changing agent skills using the Web Client

#### About this task

Use this task to change skills of agents. You can only modify the **LEVEL** and **Interrupt Type** fields if you have write permissions for the skill. Tenant users must have write permission for the agent.

#### Before you begin

Ensure that you select an active ACD. If the ACD link is inactive, you cannot modify the agent skills.

#### Procedure

- 1. Navigate to Administration > Agent Administration > Change Agent Skills.
- 2. In the **Current ACD** drop-down list, select the active ACD for which you want to change the agent skills.
- 3. In **Agent**, enter an agent name or ID, or use the drop-down list, and select the agent.

The **Agent** drop-down list is limited to a fixed number of results and provides additional choices when you enter the agent name or ID.

- 4. In Call Handling Preference, select one of the following:
  - Skill Level
  - Greatest Need
  - Percent Allocation
- 5. (Optional) In Direct Agent Skill, select a skill to use when the agent is contacted directly.
- 6. **(Optional)** Select **Service Objective** to assign service objectives to the call handling preferences.
- 7. In the Agent Skills window, click the skill that you want to change and select the required values for **LEVEL** and **Interrupt Type**.
- 8. Optionally, to apply changes to multiple agents, do the following in the **Select additional agents** field:
  - a. Type the agent name, ID, or range of IDs in the search field. Separate multiple names, IDs, or ranges using semicolons.
  - b. Add the agents from Search Results to Selected Agents.

The default maximum number of agents that you can add to Selected Agents is 99.

9. Click Apply.

The system makes the requested changes to the selected agents.

#### Deleting agent skills using the Web Client

#### About this task

Use this task to delete agent skills. You can only remove skills if you have write permission for the skill. Tenant users must have write permission for the agent.

#### Before you begin

Ensure that you select an active ACD. If the ACD link is inactive, you cannot modify the agent skills.

#### Procedure

- 1. Navigate to Administration > Agent Administration > Change Agent Skills.
- 2. In the **Current ACD** drop-down list, select the ACD for which you want to delete the agent skills.
- 3. In **Agent**, enter an agent name or ID, or use the drop-down list, and select the agent.

The **Agent** drop-down list is limited to a fixed number of results and provides additional choices when you enter the agent name or ID.

- 4. Locate the entry for the skill in the Agent Skills window.
- 5. Click the remove icon next to the selected entry to delete the agent skill.

The direct agent skill cannot be removed. If an agent is assigned only one skill, the skill cannot be removed.

- 6. Optionally, to apply changes to multiple agents, do the following in the **Select additional agents** field:
  - a. Type the agent name, ID, or range of IDs in the search field. Separate multiple names, IDs, or ranges using semicolons.
  - b. Add the agents from Search Results to Selected Agents.

The default maximum number of agents that you can add to Selected Agents is 99.

7. Click Apply.

The system makes the requested changes to the selected agents.

# About changing agent skills using the PC Client

Use the Change Agent Skills window to configure agent skills on systems with Expert Agent Selection (EAS).

Use this feature to perform the following actions:

- View the current skill assignment
- Change the skills of an agent or agent template
- Add agents to an agent template
- Set the skill of an agent or agent template to Primary or Secondary
- Set the level of the skill for an agent from 1 to 16

#### **Related links**

Changing agent skills using the PC Client on page 193 Changing call handling preference using the PC Client on page 195 Changing skills for direct agent calls using the PC Client on page 195 Changing the type associated with the skill using the PC Client on page 195 Changing the interrupt type associated with the skill using the PC Client on page 196 Removing skill assigned to the agent or template using the PC Client on page 196 Adding a skill to the agent or template using the PC Client on page 196 Specifying a new percent allocation using the PC Client on page 196 Assigning the top skill for the agent using the PC Client on page 197 Applying changes to multiple agents using the PC Client on page 197 Finishing making changes using the PC Client on page 198 Changing skill assignment for other agents or templates using the PC Client on page 198

# Changing agent skills using the PC Client

#### Procedure

1. From the Controller window, select **Commands > Agent Administration**.

CMS Supervisor displays the Agent Administration window.

- 2. In the **ACD** field, select the ACD for which you want to change agent skills.
- 3. In the **Operations** list, highlight **Change Agent Skills**.
- 4. Select OK.

Supervisor displays the Select Agent/Template window.

- 5. In the Select Agent/Template window, enter the Agent ID using one of the following methods in order view or change their skills:
  - The agent login ID
  - The name of the agent
  - An agent template

See the beginning of this section for more information on agent templates.

6. Select OK.

Supervisor displays the Change Agent Skills window with the agent or template name and login ID in the title bar.

The skills and skill level for the agent or template that you named are shown in the **Assigned Skills** field and **LEVEL** field, respectively.

Skill names are shown for the skills that are defined in the Dictionary. Skill numbers are shown for the skills that are not defined in the Dictionary.

These skill settings for an agent can be passed on to other agent profiles. To specify the agents who are to receive the skill settings, select **Use for one or more Agents** and enter the agent IDs in the associated field.

- 7. Choose one of the following options to change the skills of this agent or template:
  - To change which calls an agent receives first, perform <u>Changing call handling</u> <u>preference</u> on page 195.
  - To change the skill that is used to queue an agent's direct agent calls, perform <u>Changing</u> <u>skills for direct agent calls</u> on page 195.
  - To change the level or type that is associated with the skill that is already assigned, perform <u>Changing the type associated with the skill</u> on page 195.
  - To change the interrupt type associated with skill that is already assigned for Communication Manager version 6.0 and up, perform <u>Changing the interrupt type</u> <u>associated with the skill</u> on page 196.
  - To remove skills that are assigned to this agent or template, perform <u>Removing skill</u> assigned to the agent or template on page 196.
  - To add skills to this agent or template, perform <u>Adding skill to the agent or template</u> on page 196.
  - To specify a new percent allocation when you have Avaya Business Advocate, perform <u>Specifying a new percent allocation</u> on page 196.

- To make a **Direct Agent Calls First** the **Top Skill** for this agent, perform <u>Assigning the</u> top skill for the agent on page 197.
- To apply the changes to multiple agents, perform <u>Applying changes to multiple</u> <u>agents</u> on page 197.
- To finish making changes, perform Finishing making changes on page 198.
- To change skill assignment for other agents or templates, perform <u>Making skill</u> <u>assignment changes for other agents</u> on page 198.

#### Changing call handling preference using the PC Client Procedure

Select a different method in the Call Handling Preference group box.

Calls can be distributed to the selected agent based on:

- Skill Level
- Greatest Need
- Percent Allocation

The **Skill Level** for the agent is shown in the **Assigned Skills** list. All three call handling preferences are manage by Avaya Aura<sup>®</sup> Call Center Elite and are only available if Avaya Business Advocate is enabled on the Communication Manager system. For more information about call handling preferences, see *Using Avaya Business Advocate*.

# Changing skills for direct agent calls using the PC Client

#### Procedure

Perform one of the following actions:

- Select a new skill from the Direct Agent Calls drop-down list.
- Enter the name or number of the skill in the **Assigned Skills** column of the **Agent Skills and Skill Levels** group that will be used for queuing the direct agent calls to the specified agent. You may then select the skill from the **Direct Agent Calls** drop-down list.

The **Direct Agent Calls** list does not contain reserve skills. If the agent who is currently displayed has only reserve skills in the **Assigned Skills** list, no **Direct Agent Calls** can be assigned to that agent.

# Changing the type associated with the skill using the PC Client

#### Procedure

1. In the **Assigned Skills** list, select the level of the skill for which you want to change the value.

If you have a Skill Level Call Handling Preference, an arrow indicates the agent's Top Skill assignment.

2. Select a new value for the skill level from the **LEVEL** drop-down list in the **Agent Skills and Skill Levels** group.

If **Skill Level** is selected in the **Call Handling Preference** group and only reserve levels are assigned to an agent, that agent does not have a top skill and the **Make Top Skill** button is disabled.

3. Select OK.

## Changing the interrupt type associated with the skill using the PC Client Procedure

- 1. In the **Assigned Skills** list, select the interrupt type of the skill for which you want to change the value.
- 2. Select a new value for the interrupt type from the interrupt type drop-down list in the **Agent Skills and Skill Levels** group.
- 3. Select OK.

#### Removing skill assigned to the agent or template using the PC Client

#### Procedure

- 1. In the **Assigned Skills** field, select the skills to remove from the agent.
- 2. Select the Delete Skills button.

If an agent has only one assigned skill, this skill cannot be deleted.

# Adding a skill to the agent or template using the PC Client

#### Procedure

- 1. Select the Add Skills button.
- 2. In the **Available Skills** list of the Add Agent Skills window, highlight one or more skills that you want to assign to the agent as well as the **Skill Level** for these new skills.

The **Available Skills** field lists all the skills that are defined on this ACD.

3. Select the **OK** button in the Add Agent Skills window.

# Specifying a new percent allocation using the PC Client Procedure

1. In the Call Handling Preference group, select Percent Allocation.

The **Percent Allocation** field is unavailable if a reserve level has already been specified for an agent or template.

2. Select the **YES** button from the warning window.

This indicates that you want to enable the Percent Allocation feature.

If an agent or template has **Percent Allocation** call handling preference, the total percent allocation for all standard skills must equal 100%.

By default, **Direct Agent Calls First** is activated. If a call handling preference other than **Percent Allocation** is selected, direct agent calls are delivered first, and the **Direct Agent Calls First** check box is not applicable.

#### Assigning the top skill for the agent using the PC Client

#### About this task

Use this task to make the selected skill the agent's top skill. The skill selected here becomes the highest level skill for the agent. For example, if you have an agent with skill 1 at level 4, skill 2 at level 6, skill 3 at level 10, and skill 4 at level 16, if the customer wants to make skill 4 the agent's top skill, selecting that skill here automatically changes skill 4 to level 1 and move it to the top of the agent's login skill list.

#### Procedure

- 1. In the **Assigned Skills** column of the **Agent Skills and Skill Levels** group, select the skill that you want to be the top skill of the agent.
- 2. Select the Make Top Skill button.

#### Applying changes to multiple agents using the PC Client Procedure

- 1. Select the Use for one or more Agents check box.
- 2. Enter the agent names or login IDs in the **Agent names or logids** field, select them from the drop-down list, or select them from the Browse window.

If an error in encountered with changes to agent skills, Supervisor displays a message that states what is in error. Select **OK** or **Cancel** to dismiss the error message and return to the Change Agent Skills window so that the error can be corrected.

3. Select OK.

Changes are submitted to the CMS server. If a move is pending, you are notified that the operation will not occur until the pending conditions are resolved. If you are applying a template to multiple agents, Supervisor buffers the change agents skills requests and send them to the CMS server one at a time. Supervisor displays a status box that indicates the status of each requested agent change.

If an error in encountered with changes to agent skills, Supervisor displays a message that states what is in error. Select **OK** or **Cancel** to dismiss the error message and return to the Change Agent Skills window so that the error can be corrected.

4. Select OK.

If the change is successfully made, Supervisor displays a successful message in the status bar.

If the state of an agent is not in AUX or AVAIL, Supervisor displays a message which states that the changes will be applied when the agent returns to one of those states.

5. Select **OK**.

Supervisor closes the Change Agent Skills window.

# Finishing making changes using the PC Client Procedure

1. Select **OK** in the Select Agent/Template window.

This action saves the changes that you made to the agent skills.

2. Select **Cancel** in the Select Agent/Template window. This action cancels any changes that you made.

# Changing skill assignment for other agents or templates using the PC Client

#### Procedure

- 1. Select another agent or template in the Select Agent/Template window.
- 2. Resume from step 5 of the main procedure.

# Administering multi-agent skill change

# Before changing skills for multiple agents

The following items should be read and understood before beginning work with the Multi-Agent Skill Change window:

- When agent skills are changed, the change is made to the Communication Manager system and remains in effect until another change is made through Supervisor or the Communication Manager system.
- You cannot exit from the Multi-Agent Skill Change window until the Communication Manager system responds to the requested changes.
- Skill changes take effect immediately for agents who are in AUX work mode, AVAIL (available), or logged out. Changes are pending for agents on calls or in ACW work mode until the agent enters the AUX work mode, becomes available, or logs out.
- For agents who frequently have calls on hold, skill changes can remain pending for a longer time than expected.

# Permissions required to change skills for multiple agents

Depending on the procedure that you want to perform, you need the following permissions:

- To view agent skill assignments, the user ID used to log in to this Supervisor session requires "read" permission for the Agent Administration subsystem.
- To change agent skills, the user ID used to log in to this Supervisor session requires "write" permission for the Agent Administration subsystem and for the skills to which agents are assigned.

# About administering multi-agent skill change using the Web Client

Use this administrative procedure to add, move, or delete skills for multiple agents using the Web Client . This feature is only available to users with Feature Access Agent Administration write permission.

#### Adding skills for multiple agents using the Web client

#### Before you begin

Ensure that you select an active ACD. If the ACD link is inactive, you cannot modify the agent skills.

#### Procedure

- 1. Navigate to Administration > Agent Administration > Multi-Agent Skill Change.
- 2. In **Operation**, click **Add**.
- 3. In the **Current ACD** drop-down list, select the ACD for which you want to add skills for multiple agents.
- 4. Select values to assign to multiple agents by using the drop-down list for **Skill**, **LEVEL**, and **Interrupt Type**.

The drop-down list for **Skill** is limited to a fixed number of results. You must type the name or ID to display additional results.

- 5. In the **Agents** field, type the agent name or ID, or a range of IDs to populate Search Results. Separate multiple names, IDs, or ranges using semicolons.
- 6. Add the agents from Search Results to Selected Agents.

The maximum number of agents that you can add to Selected Agents is 32.

7. Click Apply.

The system displays the result of this action.

# Moving skills for multiple agents using the Web Client

#### Before you begin

Ensure that you select an active ACD. If the ACD link is inactive, you cannot modify the agent skills.

#### Procedure

- 1. Navigate to Administration > Agent Administration > Multi-Agent Skill Change.
- 2. In **Operation**, click **Move**.
- 3. In the **Current ACD** drop-down list, select the ACD for which you want to move skills for multiple agents.
- 4. Click the drop-down list for From Skill to select the skill that you want to move.

The drop-down list for **Skill** is limited to a fixed number of results. You must type the name or ID to display additional results.

5. Use the drop-down list for **To Skill**, **LEVEL**, and **Interrupt Type** to select the new skill values to assign to multiple agents.

The drop-down list for **To Skill** is limited to a fixed number of results. Type the name or ID to display additional results .

- 6. In the **Agents** field, type the agent name or ID, or a range of IDs to populate Search Results. Separate multiple names, IDs, or ranges using semicolons.
- 7. Add the agents from Search Results to Selected Agents.

The maximum number of agents that you can add to Selected Agents is 32.

8. Click Apply.

The system displays the result of this action.

#### Deleting skills for multiple agents using the Web Client

#### Before you begin

Ensure that you select an active ACD. If the ACD link is inactive, you cannot modify the agent skills.

#### Procedure

- 1. Navigate to Administration > Agent Administration > Multi-Agent Skill Change.
- 2. In Operation, click Remove.
- 3. Select the ACD for which you want to delete skills for multiple agents.
- 4. Use the drop-down list for Skill to select the skill to delete for multiple agents.

The drop-down list for **Skill** is limited to a fixed number of results. You must type the name or ID to display additional results.

- 5. In the **Agents** field, type the agent name or ID, or a range of IDs to populate Search Results. Separate multiple names, IDs, or ranges using semicolons.
- 6. Add the agents from Search Results to Selected Agents.

The maximum number of agents that you can add to Selected Agents is 32.

7. Click Apply.

The system displays the result of this action.

# About administering multi-agent skill change using the PC Client

This section provides the procedure for changing skills for more than one agent at a time. Use the Multi-Agent Skill Change window to view current skill assignments or to change a skill for as many as 32 agents. You can also use this window to specify the skill levels and type of the skills.

#### Changing skills for multiple agents using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Agent Administration**.

Supervisor displays the Agent Administration window.

- 2. In the ACD field, select the ACD for which you want to change agent skills.
- 3. In the **Operations** list, highlight the **Multi-Agent Skill Change** item.
- 4. Select OK.

Supervisor displays the Multi-Agent Skill Change window.

- 5. Use one of the following methods to choose a skill:
  - Double-click the skill name or number.
  - Highlight a skill and press the Enter key.

Supervisor displays a second window that shows the agents assigned to this skill who are currently logged in.

Clicking the left mouse button on the column headings sorts the contents between ascending and descending order.

To view or change the current skills of an agent in the skill window, double-click the agent name.

- 6. To move agents from the current skill to another skill, perform one of the following actions:
  - To move a single agent, use the mouse to drag-and-drop an agent to a new skill in the Skill List window.
  - To move multiple agents to a new skill, hold down the Ctrl key and click on multiple agents to select them. You can select a range of agents by clicking on the agent at the beginning of the range, holding down the Shift key, and then clicking the agent at the bottom of the range.

Use the drag-and-drop method to move the agents from the window for their current skill to a new skill in the Skill List window.

Another way of moving agents from one skill to another is to open a window for the new, target skill by double-clicking that skill in the Skill List window. You can then drag-and-drop agents between the two skill windows.

Note that holding down the Ctrl key while dragging and dropping agents will add, not move, the agent or agents to the new skill.

Supervisor displays the Move Agents Between Skills window with the **Agents** field showing the following:

- The agents you moved
- The call-handling preferences of the agents
- The reserve level or skill level of each agent
- · The service objective of each agent
- The percent allocation for the skill of each agent. Percent allocation is only available on Communication Manager systems with Avaya Business Advocate.
- The interrupt type for the skill of each agent. Interrupt type is only available on Communication Manager Version 6.0 and up.

The **Move** group displays information showing the skills involved in moving this agent. If the agent is being added to a new skill, not moved, the **From Skill** information is blank and the **Preserve Original Levels** option is unavailable.

- 7. In the Move Agents Between Skills window, perform one of the following actions to complete moving agents from skill to skill:
  - Select the Level option and enter a skill-level value for each agent that you moved to this new skill.
  - To keep the current skill level of the agent, select the **Preserve Original Levels** option. This action deactivates the **LEVEL** option.
  - For Communication Manager Version 6.0 and up, select the interrupt type for the new skill for the selected agents.
- 8. Select OK.

If one or more agent moves fail, Supervisor displays a status window showing the reasons for failure. Otherwise, the status window notifies you that the change is pending.

# Administering agent trace

# About starting or stopping an agent trace

This section provides the procedure for starting and stopping the tracing of agents. Tracing an agent records the activities of the agent, state changes, and time when these events occurred. The agent trace report displays this information when it is run. The agent trace report can help you to evaluate how well agents use their time.

#### Before starting or stopping an agent trace

The following items should be read and understood before working with agent traces:

- Traces can be activated for a limited number of agents across all ACDs from one CMS server. This limit depends on the platform model. You can find this limit in *Avaya Call Management System Overview and Specification*.
- The maximum number of agent trace records that can be stored is documented in *Avaya Aura*<sup>®</sup> *Communication Manager System Capacities Table*. The oldest record is discarded and overwritten by the newest record when the file reaches the allocated maximum number of records.
- Turning a trace off does not delete the trace records for that agent. Agent trace records are overwritten automatically when the trace file reaches the maximum number of allocated records.
- The settings in the Data Storage Allocation window determine the maximum number of agent trace records that CMS can record. See <u>About administering Data Storage Allocation</u> on page 336 for more information on this window.
- Starting and stopping agent traces requires that the Data Collection feature is currently activated.
- An agent trace must be started before the Agent Trace report can be run.
- Scripts can open and use the Agent Activate Trace window. You can also schedule the script. See <u>Chapter 6: Scripting CMS operations</u> on page 483, for more information on scripting.
- The Agent Activate Trace window can be set on a timetable. See <u>Chapter 14: Using</u> <u>timetables and shortcuts</u> on page 499, for more information.

#### Permissions required to start or stop an agent trace

Depending on the procedure that you want to perform, you need the following permissions:

- To start or stop an agent trace, the user ID used to log in to this Supervisor session requires "write" permission for the Agent Administration subsystem.
- To list the agents being traced, the user ID used to log in to this Supervisor session requires "read" permission for the Agent Administration subsystem.

#### 😒 Note:

Tenant users can activate or list agent trace for any agent for which they have permissions.

#### Starting or stopping an agent trace using the Web Client

#### Procedure

1. Navigate to Administration > Agent Administration > Activate Agent Trace.

CMS Supervisor displays the Activate Agent Trace window, showing the **Current ACD** and any active agents that have trace enabled.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to start or stop agent traces.
- 3. Select Activate Agent Trace or Deactivate Agent Trace.

CMS Supervisor displays a selection window where you can search on agent names or login IDs. Use this window to select agents to either activate or deactivate agent trace.

4. After selecting one or more agents, select Activate or Deactivate to save your selections.

CMS Supervisor displays any active agents that have trace enabled. While viewing the trace results, you can:

- Enter a search string in the "Enter a filter string to search" box to limit the agents being displayed.
- Click **Remove** to stop tracing any of the displayed agents.

# Starting or stopping an agent trace using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Agent Administration**.

Supervisor displays the Agent Administration window.

- 2. In the **Operations** list, highlight **Activate Agent Trace**.
- 3. In the **ACD** drop-down list, select the ACD on which the agent trace will be run or is currently running.
- 4. Select OK.

Supervisor displays the Activate Agent Trace window.

5. In the **Agent names or logids** field, enter the names or login IDs of the agents who are to be traced or are being traced.

This field can accept multiple values. Multiple values must be separated by a semicolon (;).

Using the browse button to the right of this field will only display those agents that have synonyms assigned to them through the Dictionary.

- 6. Perform one of the following actions for the **Agent Trace** options:
  - To start an agent trace, select **On**.

- To stop an agent trace that is currently running, select Off.
- 7. Select **Actions** > **Modify** from the menu bar to start or stop the agent trace.

The status bar displays Working and then, if successful, displays Successful when the operation finishes.

# Viewing current agent trace states using the Web Client Procedure

1. Navigate to Administration > Agent Administration > Activate Agent Trace.

CMS Supervisor displays the Activate Agent Trace window, showing the **Current ACD** and any active agents that have trace enabled.

2. In the **Current ACD** drop-down list, select the ACD for which you want to view current agent traces.

CMS Supervisor displays any active agents that have trace enabled.

# Viewing current agent trace states using the PC Client

#### Procedure

1. From the Controller Window, select **Commands** > **Agent Administration**.

Supervisor displays the Agent Administration window.

- 2. In the **Operations** list, highlight **Activate Agent Trace**.
- 3. In the **ACD** drop-down list, select the ACD on which the agent trace will be run or is currently running.
- 4. Select OK.

Supervisor displays the Activate Agent Trace window.

- 5. Ensure that the **Agent names or logids** field is blank.
- 6. In the Agent Trace options, select the state to view:
  - On Displays all currently active agent traces.
  - **Off** The system cannot identify which agents do not have trace activated, but it does display those agents that are defined in the Dictionary with trace enabled.
- 7. From the menu bar, select **Actions** > **List all**.

Supervisor displays a window with a list of all agents who are currently in the selected trace state.

# About listing agents traced

This section provides the procedure for listing agents and dates for which agent trace data is available on reports. As with most operations, it is possible to run these operations through scripts and timetables.

#### **Related links**

<u>Before listing agents traced</u> on page 206 <u>Permissions required to list agents being traced</u> on page 206 <u>Listing agents traced using the Web Client</u> on page 206 <u>Listing agents traced using the PC Client</u> on page 207

#### Before listing agents traced

To view data through this operation, an agent trace must be activated for one or more agents. Also, agents for whom traces are activated must log in so that CMS creates agent trace records.

#### Permissions required to list agents being traced

Depending on the procedure that you want to perform, you need the following permissions:

• To list all agents traced, the user ID used to start this Supervisor session must have "write" permission for the Agent Administration subsystem.

#### Listing agents traced using the Web Client

#### Procedure

1. Navigate to Administration > Agent Administration > List Agents Traced.

CMS Supervisor displays the List Agents Traced window.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to list the agent traces.
- 3. **(Optional)** In the **Agent (optional)** field, select an agent from the drop-down list or enter characters to search for the agent.
- 4. **(Optional)** In the **Date(s) (optional)** field, do one of the following operations:enter a date, a range of dates, or click the calendar icon to select a date or range of dates.
  - Enter a single date or a range of dates.
  - Click the calendar icon to select a single date or a range of dates. Click the calendar icon again to leave the selection process. Click **Reset** to clear the **Date(s)** (optional) field.
- 5. Click Search.

CMS Supervisor displays the list of the agents traced based on the search criteria.

# Listing agents traced using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Agent Administration**.

CMS Supervisor displays the Agent Administration window.

- 2. In the **Operations** list, highlight **List Agents Traced**.
- 3. In the **ACD** field, select the ACD for which agents being traced will be listed.
- 4. Select OK.

#### 😵 Note:

The procedure for viewing agent trace records varies according to the information that you enter in the fields of the List Agents Traced window. The results for listing agents traced relies on the entries made in the **Agents** field, the **Date** field, or a combination of the two. For example, you can specify a small range of agents in the **Agents** field and a date range in the **Date** field. This will result in a list of only the specified agents for the date range entered.

CMS Supervisor displays the List Agents Traced window.

- 5. Use the following descriptions to determine how information is entered in the **Agents** and **Date** fields:
  - Use the **Agents** field to specify none, one, or more agents to use in displaying agent trace records.

Leave this field blank to show all agent trace records for the dates entered in the **Date** field.

Only those agents with login IDs in the Dictionary can be entered in the Agents field.

This field can accept multiple values. Multiple values must be separated by a semicolon (;).

• Use the **Date** field to specify no date, a single date, multiple dates, or a range of dates.

Leave this field blank to show all agent trace records for the agents entered in the **Agents** field.

This field can accept multiple dates or a range of dates. Multiple dates must be separated by a semicolon (;).

Leave both the **Agents** and **Date** fields blank to have CMS Supervisor display all agent trace records.

6. Select **Actions** > **List all** to display the agent trace records that match the information that you entered in the **Agents** and **Date** fields.

Supervisor displays a secondary window listing the dates and agents for which agent trace data is available, sorted by date.

# Administering splits using the PC Client

# About administering splits using the PC Client

Splits are supported only on systems without Expert Agent Selection (EAS) and can only be administered using the PC Client. Split administration is not supported on the Web Client.

# About changing extension split assignments

This section provides the procedure for assigning an extension to a different split. This feature is used for Communication Manager systems without Expert Agent Selection (EAS). Use the Change Extension Split Assignments window to list the extensions that are in the currently assigned splits or to change the splits that are assigned to a specific extension number.

#### **Related links**

<u>Before changing extension split assignments</u> on page 208 <u>Permissions required to change extension split assignments</u> on page 208 <u>Changing extension split assignments</u> on page 208

#### Before changing extension split assignments

The following should be read and understood before changing extension split assignments:

- You cannot exit from the Change Extension Split Assignments window until the Communication Manager system responds to the requested changes.
- Extension split assignment changes take effect immediately for agents who are in AUX work mode, AVAIL (available), or logged out. Changes are pending for agents on calls or in ACW work mode until the agent enters the AUX work mode, becomes available, or logs out.
- For agents who frequently have calls on hold, extension split assignment changes can remain pending for a long time.

#### Permissions required to change extension split assignments

Depending on the procedure that you want to perform, you need the following permissions:

- To view extension split assignments, you need "read" permission for the Agent Administration subsystem.
- To change extension split assignments, you need "write" permission for the Agent Administration subsystem and for the splits to which the extensions are assigned.

#### Changing extension split assignments

#### Procedure

1. From the Controller window, select **Commands** > **Agent Administration**.

Supervisor displays the Agent Administration window.

- 2. In the **ACD** field, select the ACD for which you want to change extension split assignments.
- 3. Select **Operations > Change Extension Split Assignments**.
- 4. Select OK.

Supervisor displays the Select Extension window.

5. In the Select Extension window, enter the extension number for which the split assignment is to be changed.

The extensions that are assigned to each split can be viewed in the Move Extensions Between Splits window. See <u>Move extensions between splits</u> on page 209 for more information.

6. Select OK.

Supervisor displays the Change Extension Split Assignments window.

The **Move Extension From Split** field shows the current split assignment. The **Move Extension To Split** field shows available split names or numbers. If an agent is logged in on the extension, the logged-in icon is displayed as shown in the above graphic. If an agent is not logged in on the extension, an icon is not displayed.

7. Perform one of the following actions:

If	Then
You want to change split assignments for an extension other than the one that is displayed	Select <b>Cancel</b> to return to the Select Extension window and then return to step $\frac{5}{2}$ on page 209.
You want to change split assignments for this extension	Continue with the next step.

8. Perform one of the following actions:

lf	Then
You want to remove a split assignment from this extension	Select the split name or number that is to be removed from this extension in the <b>Move Extension From Split</b> box.
You want to assign a split assignment to this extension	Select the split name or number that is to be assigned to this extension in the <b>Move Extension To Split</b> box.

9. Select OK.

CMS applies the split assignment changes made to the extension.

# Move extensions between splits

This section provides the procedures for adding a split to an extension, removing a split from an extension, and moving an extension to another split. This features is for those systems without

Expert Agent Selection (EAS). You can also use the Move Extensions Between Splits window to view extension split assignments.

#### Before moving extensions between splits

The following items should be read and understood before moving extensions between splits:

- As many as 32 agents can be moved at one time.
- You cannot exit from the Move Extensions Between Splits window until the Communication Manager system responds to your request.
- Extension split assignment changes take effect immediately for agents who are in AUX work mode, AVAIL (available), or logged out. Changes are pending for agents on call or in ACW work mode until the agent enters the AUX work mode, becomes available, or logs out.
- For agents who frequently have calls on hold, an extension move request can remain pending for an extended period of time.

#### Permissions required to move extensions between splits

Depending on the procedure that you want to perform, you need the following permissions:

- To view extension assignments, the user ID used to log in to this Supervisor session requires "read" permission for the Agent Administration subsystem and the affected splits.
- To move extension assignments, the user ID used to log in to this Supervisor session requires "write" permission for the Agent Administration subsystem and the affected splits.

#### Moving extensions between splits

#### About this task

To move extensions between splits:

#### Procedure

1. From the Controller window, select **Commands** > **Agent Administration**.

Supervisor displays the Agent Administration window.

- 2. In the **ACD** field, select the ACD that contains the extensions to move.
- 3. In the **Operations** list, highlight **Move Extensions Between Splits**.
- 4. Select OK.

Supervisor displays the Move Extensions Between Splits window.

- 5. Select the split to work with by performing one of the following actions:
  - Double-click the split name or number in the Split List window.
  - Highlight the split to work with in the Split List window and then select **Split** > **Open selected split** from the menu bar.

- 6. To move one or more extensions from the current split to another split, perform one of the following actions:
  - To move a single extension, use the mouse to drag-and-drop an extension to a new split in the Split List window.
  - To move multiple extensions to a new split, hold down the Ctrl key and click on multiple extensions to select them. You can select a range of extensions by clicking on the extension at the beginning of the range, holding down the Shift key, and then clicking the extension at the bottom of the range.

Use the drag-and-drop method to move the extensions from the window for their current split to a new split in the Split List window.

Another way of moving extensions from one split to another is to open a window for the new, target split by double-clicking that split in the Split List window. You can then dragand-drop extensions between the two split windows.

Supervisor displays the Move Extensions Between Splits window.

7. Select **OK** in the Move Extensions Between Splits window to complete the moving of the selected extensions.

# About running a split members report

#### 😵 Note:

The split members report is only available to customers who have non-EAS systems and to those using the PC Client.

This section provides the procedure for running a split members report. This report displays the extensions that are members of a specific split. Unlike regular reports, a custom or designer report cannot be created from the split members report. The split members report lists the selected splits in numerical order, each split's assigned name, and the extensions that are assigned to the split.

#### **Related links**

<u>Permissions required to run a split members report</u> on page 211 <u>Running a split members report</u> on page 211

#### Permissions required to run a split members report

Depending on the procedure that you want to perform, you need the following permissions:

• To run a split members report, the user ID used to log in to this Supervisor session requires "read" permission for the Agent Administration subsystem and for all affected splits.

#### Running a split members report

#### Procedure

1. From the Controller window, select **Commands** > **Agent Administration**.

Supervisor displays the Agent Administration window.

2. Select the **Reports** tab.

Supervisor displays the Reports tab of the Agent Administration window.

- 3. In the **ACD** field, select the ACD on which to run the split members report.
- 4. In the **Reports** list, highlight **Split Members**.
- 5. Select OK.

Supervisor displays the Split Members window.

- 6. Enter the split information in the **Splits** field. This can be one split, multiple splits, or a range of splits. Multiple splits must be separated by a semicolon (;).
- 7. In the **Destination** group, select **View Report on Screen** or **Print Report on**.
- 8. Select OK.

Supervisor displays or prints the Split Members report.

If the split does not have a name assigned, the Split Name columns on the report shows the split number. If the split has no extensions assigned to it, the Extension column is blank.

# Chapter 7: Administering users and user permissions

# About administering users and user permissions

The User Permissions subsystem is used to create CMS user IDs and to administer user permissions such as "read", "write", and "exception" permissions for features, main menu additions, splits or skills, trunk groups, ACDs, vectors, VDNs, and tenants.

The default CMS administrator user ID, "cms", provides access to the entire system. Using the cms user ID, you can create user IDs for each person requiring access to CMS and set the permissions necessary to perform job duties.

#### **I** Security alert:

Users must not share an ID because of security on the system. Sharing user IDs also affects system performance since logging in with the same ID at multiple terminals uses more system resources than if each user their own IDs.

# Before using the User Permissions subsystem

If an ACD Group is selected as the current ACD in the User Permissions window, only those operations that are valid for the ACD Group will appear in the **Operations** list.

# Example of user permissions

#### Important:

Any user ID (normal or administrator) given "write" access to the User Permission feature will be able to alter their own permissions for all CMS subsystems.

The following table displays an example of permissions that would be necessary for a supervisor:

If the call center has one skill called	And assigned to it are	The Skill 1 supervisor requires read/write permissions for
---	------------------------	--

Table continues...

Skill 1	Trunk groups 22 and 23	Skill 1
		Trunk groups 22 and 23
		Dictionary
		Exceptions

# About administering users

For users to access CMS Supervisor, you must first assign those users to the system using the User Data feature. Once created, users can use their assigned ID to log in through CMS Supervisor and through CMS. User IDs must only be created for those persons who will be using Supervisor as a part of their job duties in administering the call center.

User Data is used to assign the following user features:

- CMS user ID.
- User's name, room number, and phone number.
- Default CMS printer for the user ID.
- Designate the user ID as a Normal user, Administrator, or Tenant user.
- Maximum number of simultaneously-opened windows allowed for the user ID.
- Minimum refresh rate for real-time reports for the user ID.
- Default logon ACD for the user ID.

# **Viewing CMS users**

#### Before viewing CMS users

The following items should be read and understood before attempting to view users through the User Data window:

• The default values in the User Data window should be cleared before attempting to perform a **Find one** or **List all** action unless these values should be included in the search.

#### Permissions required to view users

Depending on the procedure to be performed, the following permissions must be observed:

- To display the User Data window and view user information, the user ID used to log in to this Supervisor session requires "read" permission for the User Permissions subsystem.
- To add, delete, or modify users through the User Data window, the user ID used to log in to this Supervisor session requires "write" permission for the User Permissions sub system.

• Tenant users cannot view other users. Their access to User Permissions is limited to viewing their own user data and is found under the Tenant Access Permissions tab under the **Tools** drop down.

#### Viewing users using the Web Client

#### Procedure

#### Navigate to Administration > User Permissions > User Data.

CMS Supervisor displays the list of users administered for the system.

#### Viewing users using the PC Client

#### Procedure

1. From the Controller window, select **Tools** > **User Permissions**.

Supervisor displays the User Permissions window.

The **Vector Access** and **VDN Access** menu items are listed if the Call Vectoring feature has been purchased.

- 2. In the **Operations** list, highlight **User Data**.
- 3. Click OK.

Supervisor displays the User Permissions User Data window.

4. Using the menu bar, select **Edit** > **Clear All**.

The information in all fields is removed. This includes the default information that appears when this window is first displayed.

- 5. There are two possible methods in searching for and displaying CMS user information:
  - List all Selecting this item from the **Actions** menu will display a secondary window displaying all users whose settings match those in the fields of this window. If no information is present in the fields, all users are displayed. This method is convenient when the need arises to look for one or more user IDs.
  - Find one Selecting this item from the Actions menu will take the information currently in all the fields of this dialog and query the database for users with matching settings. For example, having a 6 in the Maximum user window count (1-12) field with all other fields blank and selecting Find one will result in a search for all CMS users having a 6 for their Maximum user window count. If multiple users are found, each can be viewed by selecting the Next and Previous items under the Actions menu.

When using the **Find one** command, partial text strings are not supported in the search. Therefore, to view the settings for a user ID, the complete name must be entered in the **User ID** field.

If multiple users are found using the **Find one** action, the **Next** action will not become disabled at the last user, but instead cause the first user found to be displayed again.

# Adding a CMS user

#### Before adding a CMS user

The following items should be read and understood before adding a user:

#### Important:

The following internal CMS user IDs cannot be added as regular CMS users: inads, sroot, init, craft, con, nul, aux, com1 through com9, and lpt1 through lpt9.

- A user ID must be created before any permissions can be assigned to it.
- Users added using an operating system utility, such as useradd, instead of the CMS Supervisor User Data window will not be able to run c without assuming the role of a valid user by using the su command. Users created using an operating system utility will have a shell type of /usr/bin/ksh. The User Data window does not display users that were created using an operating system utility.
- Users added through the User Data window will automatically have CMS launch when they log in. The shell for these users will be /usr/bin/cms.
- The User Data window can be run through scripts and timetables.

#### Permissions required to add a user

Depending on the procedure to be performed, the following permissions must be observed:

- To display the User Data window and view user information, the user ID used to log in to this Supervisor session requires "read" permission for the subsystem.
- To add, delete, or modify users through the User Data window, the user ID used to log in to this Supervisor session requires "write" permission for the User Permissions subsystem.
- Tenant users do not have write permissions to the User Permissions sub system and thus cannot add, delete, or modify any users.

#### Adding a user using the Web Client

#### Procedure

#### 1. Navigate to Administration > User Permissions > User Data.

CMS Supervisor displays the list of users administered for the system.

2. Click Add User.

CMS Supervisor displays the Add User window.

- 3. Administer the options as described in <u>User field definitions</u> on page 217.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

#### Next steps

Assign a temporary password to the new user. For more information, see <u>Creating temporary</u> passwords for new users using the Web Client on page 224.

### Adding a user using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

Supervisor displays the User Permissions window.

The **Vector Access** and **VDN Access** menu items are listed if the Call Vectoring feature has been purchased.

2. In the **ACD** field, select the ACD or ACD Group on which the user will be created.

The same user ID does not need to be created on each ACD. A user created on one ACD can be given permissions to the other ACDs.

- 3. In the **Operations** list, highlight **User Data**.
- 4. Click OK.

Supervisor displays the User Permissions User Data window.

- 5. Administer the options as described in <u>User field definitions</u> on page 217.
- 6. Select Actions > Add from the menu bar.

The user ID is created on the ACD specified earlier in the User Permissions dialog box. If the user ID already exists, Supervisor displays an Already exists message in the status bar.

#### Caution:

The password of the new user is blank at this time. SSH connections to the CMS server require that the password of the user is set. Refer to <u>Changing a user's</u> <u>password</u> on page 496 if users are going to connect to the CMS server using SSH.

#### **User field definitions**

The following table provides the definitions for the different agent exceptions:

Field	Definition
User ID	This is a required field. Enter the new user ID to be created. The user ID must adhere to the following rules:
	The user ID must be 3 to 31 characters, using alphanumeric characters only.
	<ul> <li>The user ID must not contain spaces, special characters, or punctuation such as underscore, hyphen, or period.</li> </ul>
	<ul> <li>The user ID cannot contain certain diacritical, accented, special characters, or blanks (for example, á, ñ, ç,  , <sup>©</sup>). If a user ID is entered with an invalid character, Supervisor displays an error message.</li> </ul>
	<ul> <li>LDAP-authenticated users are limited to 20 characters, which is a limitation of LDAP, not CMS.</li> </ul>
	<ul> <li>CMS Supervisor PC Client users that continue to use Release 19.1 of the PC Client are limited to 26 characters. To use CMS user IDs of 27-31 characters with the PC Client, you must upgrade the PC Client to Release 19.2.</li> </ul>
User Name	Optional
Room Number	Optional
Phone Number	Optional
Printer	Optional.
	For the Web Client, the printer name must match the printer administered on the CMS server.
	For the PC Client, select a printer from the drop-down list of administered printers.
	Table continues

Table continues...

Field	Definition
Login type	• <b>Normal user</b> - Select this type to designate those users whose job responsibilities "do not" include maintenance, configuration, and updating of CMS .
	This role of user has only the "read" permission for the following features:
	Agent Administration
	Custom Reports/Report Designer
	• Dictionary
	• Exceptions
	• Forecast
	Maintenance
	Reports
	• Timetable
	• Administrator - Select this type to designate those users who job responsibilities include maintenance, configuration, or updating of CMS . This user role is assigned "read" and "write" permissions for all features.
	Important:
	Changing the role of the user after creation will not change any permissions assigned to the user. All permission changes need to be done manually.
	• <b>Tenant user</b> — Select this type to provide a tenant user limited access to CMS administration and reporting data. A newly created tenant user ID will have read, write, and exceptions permissions for his/her Login ACD only. The administrator can add read, write, and exceptions permissions for one or more ACDs besides the Login ACD.
LDAP Integration	Use this option if you are importing the CMS user from an Active Directory database.
Maximum user window count	Enter the number of windows $(1-12)$ that the user may have open simultaneously. The default for this field is 4.
	Important:
	Allowing many users to have multiple windows open will consume more CMS processor resources.
Minimum refresh rate	Enter the number of seconds (3-300) in which data for real-time reports is retrieved again from the database and displayed for this user ID.
	Important:
	Faster refresh rates consume more CMS processor resources.
Login ACD	Select the ACD which will be used to log on this user ID. The user can change the current ACD after logging on, but each time the user logs on, the current ACD defaults to the value entered in this field.
	This is a required field and cannot be left with the default value of <b>(none)</b> .

## Modifying CMS users

### Before modifying CMS users

The following items should be read and understood before modifying users through the User Data window:

- If a user's login ACD is removed and the user tries to log into CMS, an acknowledgment tells the user either to contact the CMS administrator or to change the login ACD.
- Changing the login type for a user from **Administration** to **Normal** or vice versa does not change the permissions for that user ID. Permissions must be changed manually.
- The Login ID of a tenant user cannot be changed to a Normal user or an Administration user from the **User Permissions** screen.
- A Normal user or Administrative user cannot be changed to a Tenant user. The login id that the modification is being attempted on can only be removed and administered with the desired user level access.
- Changes to maximum window count, minimum refresh rate, or default login ACD for a user do not take effect until the user logs out and back in again.

### Permissions required to modify users

Depending on the procedure to be performed, the following permissions must be observed:

- To display the User Data window and view user information, the user ID used to log in to this Supervisor session requires "read" permission for the User Permissions subsystem.
- To add, delete, or modify users through the User Data window, the user ID used to log in to this Supervisor session requires "write" permission for the User Permissions subsystem.
- Tenant users can only view their own user data and cannot add, delete or modify themselves or any other users.

#### Modifying users using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > User Data.

CMS Supervisor displays the list of users administered for the system.

2. Click **Modify** on the user you want to change.

CMS Supervisor displays the Modify Item window.

- 3. Administer the options as described in <u>User field definitions</u> on page 217. You cannot modify the **User ID** option.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

## Modifying users using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

Supervisor displays the User Permissions window.

The **Vector Access** and **VDN Access** menu items are listed if the Call Vectoring feature has been purchased.

- 2. In the **Operations** list, highlight **User Data**.
- 3. Click OK.

Supervisor displays the User Permissions User Data window.

- 4. Clear all field default values by selecting Edit > Clear All from the menu bar.
- 5. In the **Login type (select only one)** field, select the login type for the user that will be modified.
- 6. Enter the name of the user to modify in the User ID field.
- 7. Select Actions > Find one.

The settings for the specified user ID will populate their associated fields.

If the user ID was not found, try selecting the other login type in the **Login type (select only one)** field.

- 8. Modify the settings for this user as needed.
- 9. After all necessary modifications have been made, select Actions > Modify.

The settings for this user are updated and the status bar will display a Successful message.

## **Deleting CMS users**

#### Before deleting CMS users

The following items should be read and understood before deleting users through the User Data window:

- Deleting a user ID added through the User Data window of CMS will remove that ID and its associated permissions from CMS and the operating system.
- Deleting a user who had custom reports, designer reports, or timetables, will result in an
  acknowledgment window asking if those items should be moved to your user ID. If they are
  moved and there is a conflict between the assigned names, a prompt window will appear
  allowing the moved items to be renamed. If not moved, any custom reports, designer reports,
  and timetables will be deleted along with the user ID.

## Permissions required to delete users

Depending on the procedure to be performed, the following permissions must be observed:

- To display the User Data window and view user information, the user ID used to log in to this Supervisor session requires "read" permission for the User Permissions subsystem.
- To add, delete, or modify users through the User Data window, the user ID used to log in to this Supervisor session requires "write" permission for the User Permissions sub system.
- Tenant users can only view their own user data and cannot add, delete or modify themselves or any other users.

## **Deleting users using the Web Client**

#### Procedure

1. Navigate to Administration > User Permissions > User Data.

CMS Supervisor displays the list of users administered for the system.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

3. Click **Yes** to continue with the change. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

4. Click OK.

CMS Supervisor displays an updated list of items.

## **Deleting users using the PC Client**

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

Supervisor displays the User Permissions window.

The **Vector Access** and **VDN Access** menu items are listed if the Call Vectoring feature has been purchased.

- 2. In the **Operations** list, highlight **User Data**.
- 3. Click **OK**.

Supervisor displays the User Permissions User Data window.

4. Using the menu bar, select **Edit** > **Clear All**.

The information in all fields is removed. This includes the default information that appears when this window is first displayed.

- 5. In the **Login type (select only one)** field, select the login type of the user that will be deleted.
- 6. Enter the name of the user in the User ID field.

If the user ID is not known, the other fields of this dialog box can be used to enter information that can return all users having matching information. For example, the **User Name** and **Room number** fields can have information entered in them.

7. After user-identifying data has been entered in the fields, select **Actions** > **Find one** from the menu bar.

The status bar will return the number of matches found. Select **Actions** > **Next** to navigate to the next user in the list, if necessary.

8. When the dialog box displays the correct user, select **Actions > Delete** from the menu bar.

The identified user is deleted from the system and the status bar displays a Successful message.

## About changing user passwords using the Web Client

The Web Client supports the following scenarios for changing user passwords:

- Individual users can change their own passwords.
- Administrative users can change passwords for current users.
- Administrative users can create temporary passwords for new users.

#### **I** Security alert:

Passwords must follow length and character usage rules set by your local CMS administrator.

#### Important:

Only an administrative user with the Password permission can change a password for another user. Only the "cms" and "cmssvc" user IDs can grant or revoke the Password permission. Only CMS users can have their password changed using the Web Client. That is, you cannot change the password for a Linux user ID, such as "root".

#### 😒 Note:

Web Client password management cannot be used for LDAP-authenticated users or tenant users.

#### Changing your own password using the Web Client

#### About this task

#### Security alert:

Passwords must follow length and character usage rules set by your local CMS administrator.

#### Procedure

1. Log on to the Web Client.

#### 2. Navigate to **Your User ID** > **Change Password**.

CMS Supervisor displays the Change password window.

- 3. Enter your old password.
- 4. Enter your new password.
- 5. Enter your new password again to confirm the change.
- Click **OK** to commit the operation. Click **Cancel** to cancel the operation. CMS Supervisor displays a confirmation message.
- 7. Click OK.

#### Changing passwords for current users using the Web Client

#### About this task

#### Security alert:

Passwords must follow length and character usage rules set by your local CMS administrator.

#### Procedure

- 1. Log on to the Web Client.
- 2. Navigate to Administration > Other > Change User Password.

CMS Supervisor displays the Change User Password window.

- 3. Enter the user ID that requires a password change.
- 4. Enter a new password.
- 5. Enter a new password again to confirm the change.
- 6. Click **Apply** to make the change or click **Reset** to clear the entry fields.

CMS Supervisor displays a confirmation message.

#### Creating temporary passwords for new users using the Web Client

#### About this task

**I** Security alert:

Passwords must follow length and character usage rules set by your local CMS administrator.

#### Security alert:

Inform the new user that they must change this temporary password after they log on to CMS Supervisor the first time.

#### Procedure

- 1. Log on to the Web Client.
- 2. Navigate to Administration > Other > Change User Password.

CMS Supervisor displays the Change User Password window.

- 3. Enter the user ID of the new user that requires a temporary password.
- 4. Enter a new password.

- 5. Enter a new password again to confirm the change.
- 6. Click **Apply** to make the change or click **Reset** to clear the entry fields.

CMS Supervisor displays a confirmation message.

## About administering access to CMS features

The Feature Access window is used to view and modify the permissions available to a CMS user ID for the following features:

- Agent Administration
- Call Center Administration
- Custom Reports
- Dictionary
- Exceptions
- Forecast
- Maintenance
- Reports
- CMS System Setup
- Tenant
- Timetable
- User Permissions
- OS command line (Linux)
- Password (Web Client only)

The permissions assigned to a user will affect which administration feature areas are displayed to user on CMS Supervisor. For example, a user without permissions for the Dictionary feature will not see the Dictionary administration option.

## Before administering access to CMS features

The following items should be read and understood before working with feature access permissions:

- Feature Access permissions cannot be modified for the cms and cmssvc user IDs. This prevents a user with access to the User Permissions feature from disabling access to all or part of CMS for the administrator or services personnel.
- If the feature access permissions for a user are modified, the changes do not take effect until the user logs off and back on again.

- A user ID must be created through the User Data feature before that user can have feature access permissions assigned.
- Default feature access permissions are assigned when a user ID is created. The Administrator type of user ID has permissions for all features. The Normal type of user ID is given "read" permissions for all features except User Permissions, System Setup, Call Center Administration, and Forecasting. User ID types are set through the User Data feature. The administrator has both read and write permissions to the Tenant feature by default. A normal user does not have read and write permissions to the Tenant feature by default. A tenant user has restricted feature access. The tenant user cannot turn on the Forecast, Maintenance, and System Setup features and does not have access to the OS command line shell (Linux).
- Assigning a user the "write" permission for the User Permissions feature allows that user to change permissions for all users.
- A user ID cannot have "write" permissions without also having "read" permissions.
- If a user does not have "read" permission for a feature, that feature will not be displayed as a toolbar button or menu item on CMS Supervisor.
- Assigning only the necessary access permissions ensures the best system performance.

## Permissions required to administer access to CMS features

Depending on the procedure that you want to do, you need the following permissions:

- To view feature access permissions, the user ID must have "read" permission for the User Permissions subsystem.
- To add, delete, or modify feature access permissions, the user ID must have "write" permission for the User Permissions subsystem.

#### Important:

Only an administrative user with the Password permission can change a password for another user. Only the "cms" and "cmssvc" user IDs can grant or revoke the Password permission. Only CMS users can have their password changed using the Web Client. That is, you cannot change the password for a Linux user ID, such as "root".

## Viewing and modifying feature access permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > Feature Access.

CMS Supervisor displays the list of users administered for the system and to which CMS features they have Read or Write access. The permissions for each feature are shown left-to-right as Read and Write permissions. If a feature has only one permission, it is the Write permission.

2. Click **Modify** on the user you want to change.

CMS Supervisor displays the Modify Item window.

- 3. For each feature in the list, select which features the user should have **Read** and **Write** access.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

#### Viewing feature access user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Feature Access**.
- 3. In the **ACD** field, select the ACD or ACD Group on which you want to view user permissions for its feature set.
- 4. Click OK.

Supervisor displays the User Permissions Feature Access window.

5. In the User ID field, enter the ID of an existing CMS user.

This field can accept more than one user ID. Multiple IDs must be separated by a semicolon (;).

6. From the menu bar, select **Actions > Find one**.

Supervisor will display the permissions for the first user found. If multiple user IDs were entered, the status bar will display the number of matches found.

If multiple matches were found, use the **Actions** > **Next** command to navigate through the user IDs and their permissions.

## Listing all feature access user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

2. In the **Operations** list, highlight **Feature Access**.

- 3. In the **ACD** field, select the ACD or ACD Group on which you want to view user permissions for its feature set.
- 4. Click OK.

Supervisor displays the User Permissions Feature Access window.

5. From the menu bar, select **Actions** > **List all**.

Supervisor displays a secondary window listing all users and their associated feature permissions.

## Modifying feature access user permissions using the PC Client

#### About this task

This section provides the procedure for modifying Feature Access permissions for a CMS user on an ACD or ACD Group.

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the Operations list, highlight Feature Access.
- 3. In the **ACD** field, select the ACD or ACD Group on which the user permissions for its feature set will be modified.
- 4. Click OK.

Supervisor displays the User Permissions Feature Access window.

- 5. In the **User ID** field, enter the ID of an existing CMS user.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor will display the permissions for the user.

A check mark in a check box signifies that the associated feature permission is enabled for the user.

- 7. Change the **Read** and **Write** permissions as necessary by placing or removing check marks in the check boxes for each feature.
- 8. When the necessary changes have been made to the user feature permissions, select **Actions > Modify** from the menu bar.

The user permissions definition for this ACD is updated and the status bar displays a Successful message.

## About administering custom menu items and access

The Main Menu Addition Access feature is used to control which custom menu items appear on the CMS main menu for a user and whether the user has access to the menu item.

Custom menu items are created through the Main Menu Addition feature which is located in the System Setup screen from the Web Client or the CMS ASCII interface.

These menu items cannot be created through the PC Client.

The custom menu items display on the CMS Main Menu which is seen through either Terminal Emulator, a telnet session to the CMS server, or the CMS console. The custom menu items do not display in the CMS Supervisor user interface.

## Before using custom menu items and access

The following items should be read and understood before working with custom menu items and access:

- Main menu additions must be created through System Setup before these custom menu items can be assigned to users.
- If the assigned Main Menu Addition Access permission for a user is disabled, the custom menu item will not be displayed on the CMS main menu for that user.
- A user ID must be created through the User Data feature before assignments or changes can be made to that user ID through the Main Menu Addition Access feature.
- If a the Main Menu Addition Access permission is changed for a user, those changes will not take effect until the user logs out and back in again.

# Permissions required to administer custom menu items and access

Depending on the procedure that you want to do, you need the following permissions:

- To view Main Menu Addition Access user configurations, the user ID used to log in to CMS requires "read" permission for the User Permissions subsystem.
- To add, delete, or modify Main Menu Addition Access user configurations, the user ID used to log in to CMS requires "write" permission for the User Permissions subsystem.

# Viewing, adding, or modifying custom menu items and access using the Web Client

#### Procedure

Viewing Custom Menu Items and Access

1. Navigate to Administration > User Permissions > Main Menu Addition Access.

CMS Supervisor displays the list of users administered for the system, to which custom main menu items are assigned to each user, and whether the user has access to the custom main menu item.

Adding Custom Menu Items and Access

2. Click Add Main Menu Addition Access.

CMS Supervisor displays the Add Main Menu Addition Access window.

- 3. Administer the following options:
  - In the **User ID** field, select or enter the user ID to which you want to add access to a custom menu item.
  - In the **Addition** field, enter the name of the custom menu item administered in System Setup.
  - Select the **Access** option if you want the user to see and access the custom menu item. Deselect the option if you want the user to see the custom menu item, but not have access to the custom menu item.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

Modifying Custom Menu Items and Access

6. Click **Modify** on the user you want to change.

CMS Supervisor displays the Modify Item window.

- 7. Select the **Access** option if you want the user to see and access the custom menu item. Deselect the option if you want the user to see the custom menu item, but not have access to the custom menu item. This is the only option you can change.
- 8. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

9. Click **OK**.

CMS Supervisor displays an updated list of items.

## Viewing custom menu items and access using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Main Menu Addition Access**.
- 3. Click OK.

Supervisor displays the User Permissions Main Menu Addition Access window.

4. In the **User ID** field, enter a CMS user ID that has been previously defined through the User Data feature.

This field can accept the entry of multiple users at one time. Multiple entries must be separated by a semicolon (;).

5. From the menu bar, select **Actions > Find one**.

Supervisor retrieves the Main Menu Addition Access information for the specified CMS user ID and displays this information in the remaining fields.

If multiple users were specified in the **User ID** field, the other users and their configurations can be seen by using **Actions** > **Next** from the menu bar.

## Listing all custom menu items and access using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Main Menu Addition Access**.
- 3. Click OK.

Supervisor displays the User Permissions Main Menu Addition Access window.

4. From the menu bar, select Actions > List all .

Supervisor displays a secondary window listing all CMS users that have custom menu items assigned and the permissions for those custom menu items.

# Assigning or modifying custom menu items and access using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the Operations list, highlight Main Menu Addition Access.
- 3. Click **OK**.

Supervisor displays the User Permissions Main Menu Addition Access window.

4. In the **User ID** field, enter a CMS user ID that has been previously defined through the User Data feature.

This field can accept the entry of multiple users at one time. Multiple entries must be separated by a semicolon (;).

5. From the menu bar, select **Actions > Find one**.

Supervisor retrieves the Main Menu Addition Access information for the specified CMS user ID and displays this information in the remaining fields.

If multiple users were specified in the **User ID** field, the other users and their configurations can be seen by using **Actions** > **Next** from the menu bar.

- 6. In the **Addition** field, enter the custom menu item to be assigned or modified for the specified CMS user.
- 7. In the **Access** check box, place a check mark to enable this custom menu item or remove the check mark to disable this menu item for the specified CMS user.
- 8. From the menu bar, select Actions > Modify .

The user configuration is updated and the status bar displays a Successful message.

Only the current CMS displayed in the **User ID** field is modified. If other user IDs are available through using the **Next** command, each one will require the **Modify** action for assignments to be applied.

## About administering access to splits or skills

This section provides the procedures for working with user permissions regarding splits and skills.

For users providing administration for splits and skills or running split and skill reports, it is necessary for them to have the proper permissions to perform their job functions.

Split and skill exceptions notification is also configured through this interface. Users who are given the "Exceptions" permission will be notified of split and skill exceptions when they occur.

## Before administering access to splits or skills

The following items should be read and understood before working with split or skill permissions:

- A CMS user ID must be created through the User Data feature before split or skill permissions can be assigned.
- When a new user ID is created through the User Data feature, split or skill permissions for that user are not created. This is done to conserve disk space. When a split or skill permissions definition does not exist for a user ID, CMS will deny "read" and "write" access to splits or skills.

- A user ID must first have permissions for the ACD on which the split or skill resides before split or skill permissions can be assigned. If a user ID is assigned split or skill permissions and does not have the appropriate ACD permissions, the system displays an error message.
- A user ID cannot be assigned the "write" permission without first having the "read" permission.
- Assigning only those permissions that are necessary for each user ID ensures the best system performance.
- When the permissions definition for a user is created or modified, the split or skill permissions do not take effect until the user logs off and back on again.
- The wildcard characters "\*" and "?" cannot be used in the User Permissions Split/Skill Access window.
- The tenant user cannot be given permissions to splits/skills unless the splits/skills are assigned to the tenant to which the tenant user is assigned.
- The permissions for the splits/skills cannot be greater than the permissions given to the tenant to which the splits/skills belong.
- The tenant user has the permissions for the tenant to which the splits/skills belong.

## Permissions required to administer access to splits or skills

Depending on the procedure that you want to do, you need the following permissions:

- To view split or skill user permissions, the user ID must have "read" permission for the User Permissions subsystem.
- To add, delete, or modify split or skill user permissions, the user ID must have "write" permission for the User Permissions subsystem.

## Viewing split or skill user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Split/Skill Access.

CMS Supervisor displays the list of administered users and their current split or skill and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer split or skill user permissions.

CMS Supervisor displays the list of administered users and their current split or skill and exception access permissions for the selected ACD.

## Adding split or skill user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Split/Skill Access.

CMS Supervisor displays the list of administered users and their current split or skill and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer split or skill user permissions.

CMS Supervisor displays the list of administered users and their current split or skill and exception access permissions for the selected ACD.

#### 3. Click Add Split/Skill Access.

CMS Supervisor displays the Add Split/Skill Access window.

- 4. Administer the following options:
  - In the **User ID** field, select, search, or enter the user ID to which you want to add access to a split or skill or to exceptions.
  - In the **Splits/Skills** field, enter the split or skill names to which you want the user to have access. Use the **Search Results** windows to select multiple splits or skills.
  - Select the Read, Write, and Exceptions options as required.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

## Modifying split or skill user permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > Split/Skill Access.

CMS Supervisor displays the list of administered users and their current split or skill and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer split or skill user permissions.

CMS Supervisor displays the list of administered users and their current split or skill and exception access permissions for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Select the **Read**, **Write**, and **Exceptions** options as required. You cannot change any other options.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

## Deleting split or skill user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Split/Skill Access.

CMS Supervisor displays the list of administered users and their current split or skill and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer split or skill user permissions.

CMS Supervisor displays the list of administered users and their current split or skill and exception access permissions for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **Yes** to continue with the change. Click **No** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

### Viewing split or skill user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Split/Skill Access**.
- 3. In the **ACD** field, select the ACD or ACD Group containing the split/skill for which all permission definitions will be shown.
- 4. Click OK.

Supervisor displays the User Permissions Split/Skill Access window.

- 5. In the **User ID** field, enter the name of the user for which the split/skill permissions definition is to be viewed.
- If the specific split/skill to view for this user is known, enter the name or number of the split/ skill in the **Splits/Skills** field. To have all splits/skills returned for this user ID, leave this field blank.

This field can accept multiple splits/skills. Multiple entries must be separated by a semicolon (;).

7. From the menu bar, select **Actions > Find one**.

Supervisor queries the database and displays the number of matches found for this user ID in the status bar.

## Listing all split or skill user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Split/Skill Access**.
- 3. In the **ACD** field, select the ACD or ACD Group containing the split/skill for which all permission definitions will be shown.
- 4. Click OK.

Supervisor displays the User Permissions Split/Skill Access window.

5. From the menu bar, select **Actions > List all**.

Supervisor displays a secondary window listing all user permissions for splits/skills on the specified ACD.

A filter can be created when listing all user split/skill permission definitions. This filter is based on any information contained in the **User ID** and **Splits/Skills** fields on this dialog box when the **List all** action is performed.

For example, to view all of the user permission definitions for skill 26, enter 26 in the **Splits/Skills** field before performing the **List all** action. This will cause only the user permission definitions for skill 26 to display. If more information is entered into the other fields of this dialog box, the results will be more restricted. If information for the user ID, splits/skills, and permissions are entered, the **List all** command will only return those permission definitions which match all of the information.

## Adding split or skill user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Split/Skill Access**.
- 3. In the **ACD** field, select the ACD or ACD Group containing the split/skill for which the user will be given permissions.
- 4. Click OK.

Supervisor displays the User Permissions Split/Skill Access window.

- 5. In the **User ID** field, enter the name of the user who will be assigned split/skill permissions.
- 6. In the **Splits/Skills** field, enter the name or number of the split/skill for which the user will have permissions assigned.

This field can accept multiple splits/skills. Multiple entries must be separated by a semicolon (;).

Multiple splits/skills can be entered by using a range, for example, 1-256.

- 7. Place a check mark in the permissions that will be assigned to this user:
  - **Read** User can view but not modify information for the specified splits/skills including reports.
  - Write User can modify information on the specified splits/skills. This permission requires that the user also have the "read" permission.
  - **Exceptions** User will receive notification of exceptions occurring on the specified splits/skills.

Only the split/skill exceptions made active through the **Exceptions** feature will provide notification to the user. See <u>Chapter 9: Administering exceptions</u> on page 271 for more information.

8. After assigning the necessary permissions, select **Actions > Add** from the menu bar.

The split/skill permissions for this user are saved.

It is possible to add permission definitions for multiple splits/skills at one time. To do so, enter multiple splits/skills in the **Splits/Skills** field and separate them with semicolons (;).

## Modifying split or skill user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Split/Skill Access**.
- 3. In the **ACD** field, select the ACD or ACD Group containing the split/skill for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions Split/Skill Access window.

- 5. In the **User ID** field, enter the name of the user for which the split/skill permissions definition is to be modified.
- 6. If the specific split/skill to view for this user is known, enter the name or number of the split/ skill in the **Splits/Skills** field. For all splits/skills to be returned for this user ID, leave this field blank.

This field can accept multiple splits/skills. Multiple entries must be separated by a semicolon (;).

7. From the menu bar, select **Actions > Find one**.

Supervisor queries the database and displays the number of matches found for this user ID in the status bar.

If multiple matches are found, use the **Next** and **Previous** items found under the **Actions** menu to navigate to the correct split/skill.

- 8. Change the permissions for the user on this split/skill as needed:
  - **Read** User can view but not modify information for the specified splits/skills including reports.
  - Write User can modify information on the specified splits/skills. This permission requires that the user also have the "read" permission.
  - **Exceptions** User will receive notification of exceptions occurring on the specified splits/skills.

Only the split/skill exceptions made active through the Exceptions feature will provide notification to the user. See <u>Chapter 9: Administering exceptions</u> on page 271 for more information.

9. After the necessary permission changes have been completed, select **Actions** > **Modify** from the menu bar.

The permissions definition for this user ID and split/skill is updated. The status bar displays a Successful message.

## Deleting split or skill user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Split/Skill Access**.
- 3. In the **ACD** field, select the ACD or ACD Group containing the split/skill for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions Split/Skill Access window.

- 5. In the **User ID** field, enter the name of the user for which the split/skill permissions definition is to be deleted.
- 6. If the specific split/skill to view for this user is known, enter the name or number of the split/ skill in the **Splits/Skills** field. To return all split/skills for this user ID, leave this field blank.
- 7. From the menu bar, select **Actions > Find one**.

Supervisor queries the database and displays the number of matches found for this user ID in the status bar.

If multiple matches are found, use the **Next** and **Previous** items found under the **Actions** menu to navigate to the correct split/skill.

8. From the menu bar, select **Actions > Delete**.

Supervisor deletes the permissions definition for this user ID and the associated split/skill. The status bar displays a Successful message upon completion of the action.

This action does not delete the permission definitions for all splits/skills for this user, only the one displayed in the **Splits/Skills** field.

## About administering access to trunk group data

Trunk group permissions allow users to view data for trunk group reports, view trunk group configuration information, and change trunk group configurations. The Trunk Group Access window is also used to configure which users receive exception notifications.

## Before administering access to trunk group data

The following items should be read and understood before working with trunk group permissions:

- A CMS user ID must be created through the User Data feature before it can be assigned trunk group permissions.
- When a new user ID is created through the User Data feature, trunk group permission definitions for that user are not created. This is done to conserve disk space. When a trunk group permissions definition does not exist for a user ID, CMS will deny "read" and "write" access to trunk groups.

- A user ID must first have permissions for the ACD on which the trunk group resides before trunk group permissions can be assigned. If a user ID is assigned trunk group permissions and does not have the appropriate ACD permissions, the system displays an error message.
- A user ID cannot be assigned the "write" permission without first having the "read" permission.
- When the permissions definition for a user is added or modified, the change does not take effect until the user logs off and back on again.
- Assigning only those permissions that are necessary for each user ID ensures the best system performance.
- The wildcard characters "\*" and "?" cannot be used in the User Permissions Trunk Group Access window.
- The permissions for the trunk groups cannot be greater than the permissions given to the tenant to which the trunk groups belong.
- The tenant user cannot be given permissions to trunk groups unless the trunk groups are assigned to the tenant to which the tenant user is assigned.
- The tenant user must have the permissions for the tenant to which the trunk groups belong.

## Permissions required to administer access to trunk group data

Depending on the procedure that you want to do, you need the following permissions:

- To view trunk group user permissions, the user ID must have "read" permission for the User Permissions subsystem.
- To add, delete, or modify trunk group user permissions, the user ID must have "write" permission for the User Permissions subsystem.

## Viewing trunk group data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Trunk Group Access.

CMS Supervisor displays the list of administered users and their current trunk group data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk group data user permissions.

CMS Supervisor displays the list of administered users and their current trunk group data and exception access permissions for the selected ACD.

## Adding trunk group data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Trunk Group Access.

CMS Supervisor displays the list of administered users and their current trunk group data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk group data user permissions.

CMS Supervisor displays the list of administered users and their current trunk group data and exception access permissions for the selected ACD.

#### 3. Click Add Trunk Group Access.

CMS Supervisor displays the Add Trunk Group Access window.

- 4. Administer the following options:
  - In the **User ID** field, select, search, or enter the user ID to which you want to add access to trunk group data or to exceptions.
  - In the **Trunk Groups** field, enter the trunk group names or IDs to which you want the user to have access. Use the **Search Results** windows to select multiple trunk groups.
  - Select the Read, Write, and Exceptions options as required.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying trunk group data user permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > Trunk Group Access.

CMS Supervisor displays the list of administered users and their current trunk group data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk group data user permissions.

CMS Supervisor displays the list of administered users and their current trunk group data and exception access permissions for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Select the **Read**, **Write**, and **Exceptions** options as required. You cannot change any other options.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

## Deleting trunk group data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Trunk Group Access.

CMS Supervisor displays the list of administered users and their current trunk group data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer trunk group data user permissions.

CMS Supervisor displays the list of administered users and their current trunk group data and exception access permissions for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **Yes** to continue with the change. Click **No** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

#### Viewing trunk group data user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Trunk Group Access**.
- 3. In the **ACD** field, select the ACD containing the trunk group for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions Trunk Group Access window.

- 5. In the **User ID** field, enter the name of the user for which the trunk group permissions definition is to be viewed.
- 6. If the specific trunk group to view for this user is known, enter the name or number of the trunk group in the **Trunk Groups** field. To have all trunk groups returned for this user ID, leave this field blank.

This field can accept multiple trunk groups. Multiple entries must be separated by a semicolon (;).

7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID displays in the status bar.

## Listing all trunk group data user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Trunk Group Access**.
- 3. In the **ACD** field, select the ACD containing the trunk group for which all permission definitions will be shown.
- 4. Click OK.

Supervisor displays the User Permissions Trunk Group Access window.

5. From the menu bar, select **Actions** > **List all**.

Supervisor displays a secondary window listing all user permissions for trunk groups on the specified ACD.

A filter can be created when listing all user trunk group permission definitions. This filter is based on any information contained in the **User ID** and **Trunk Groups** fields on this dialog box when the **List all** action is performed.

For example, to view all of the user permission definitions for trunk group 4, enter 4 in the **Trunk Groups** field before performing the List all action. This will cause only the user permission definitions for trunk group 4 to display. If more information is entered into the other fields of this dialog box, the results will be more restricted. If information for the user ID, trunk groups, and permissions are entered, the **List all** command will only return those permission definitions which match all of the information.

## Adding trunk group data user permissions using the PC Client Procedure

1. From the Controller window, select **Tools** > **User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Trunk Group Access**.
- 3. In the **ACD** field, select the ACD containing the trunk group for which the user will be given permissions.
- 4. Click OK.

Supervisor displays the User Permissions Trunk Group Access window.

- 5. In the **User ID** field, enter the name of the user who will be assigned trunk group permissions.
- 6. In the **Trunk Groups** field, enter the name or number of the trunk group for which the user will have permissions assigned.

This field can accept multiple trunk groups. Multiple entries must be separated by a semicolon (;).

- 7. Place a check mark in the permissions that will be assigned to this user:
  - **Read** User can view but not modify information for the specified trunk groups including reports.
  - Write User can modify information on the specified trunk groups. This permission requires that the user also have the "read" permission.
  - **Exceptions** User will receive notification of exceptions occurring on the specified trunk groups.

Only the trunk group exceptions made active through the **Exceptions** feature will provide notification to the user. See <u>Chapter 9: Administering exceptions</u> on page 271 for more information.

8. After assigning the necessary permissions, select **Actions > Add** from the menu bar.

The trunk group permissions for this user are saved.

It is possible to add permission definitions for multiple trunk groups at one time. To do so, enter multiple trunk groups in the **Trunk Groups** field and separate them with semicolons (;).

## Modifying trunk group data user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Trunk Group Access**.
- 3. In the **ACD** field, select the ACD containing the trunk group for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions Trunk Group Access window.

- 5. In the **User ID** field, enter the name of the user for which the trunk group permissions definition is to be modified.
- 6. If the specific trunk group to view for this user is known, enter the name or number of the trunk group in the **Trunk Groups** field. To have all trunk groups returned for this user ID, leave this field blank.

This field can accept multiple trunk groups. Multiple entries must be separated by a semicolon (;).

7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID displays in the status bar. The first match found populates the fields of this dialog box.

If multiple matches are found, use the **Next** and **Previous** items found under the **Actions** menu to navigate to the correct trunk group.

- 8. Change the permissions for the user on this trunk group as needed:
  - **Read** User can view but not modify information for the specified trunk groups including reports.
  - Write User can modify information on the specified trunk groups. This permission requires that the user also have the "read" permission.
  - Exceptions User will receive notification of exceptions occurring on the specified trunk groups.

Only the trunk group exceptions made active through the **Exceptions** feature will provide notification to the user. See <u>Chapter 9: Administering exceptions</u> on page 271 for more information.

9. After the necessary permission changes have been completed, select **Actions** > **Modify** from the menu bar.

The permissions definition for this user ID and trunk group is updated. The status bar displays a Successful message upon completion.

## Deleting trunk group data user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Trunk Group Access**.
- 3. In the **ACD** field, select the ACD containing the trunk group for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions Trunk Group Access window.

- 5. In the **User ID** field, enter the name of the user for which the trunk group permissions definition is to be deleted.
- 6. If the specific trunk group to view for this user is known, enter the name or number of the trunk group in the **Trunk Groups** field. To return all trunk groups for this user ID, leave this field blank.
- 7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID displays in the status bar. The first match found populates the fields of this dialog box.

If multiple matches are found, use the **Next** and **Previous** items found under the **Actions** menu to navigate to the correct trunk group.

8. From the menu bar, select **Actions > Delete**.

The permissions definition for this user ID and the associated trunk group is deleted. The status bar displays a Successful message upon completion of the action.

This action does not delete the permission definitions for all trunk groups for this user, only the one displayed in the **Trunk Groups** field.

## About administering access to ACDs

The ACD Access window is used to view and modify the user permissions for a selected real or pseudo-ACD. This window can also be used to turn exception notification on or off for a selected ACD.

## Before administering access to ACDs

The following items should be read and understood before working with ACD access permissions:

- By default, a newly-created user is granted "read", "write", and "exceptions" permissions for all real and pseudo ACDs.
- A newly created tenant user is, by default, granted read, write, and exceptions permissions only to the login ACD of the tenant user. An administration user can allow the tenant user to gain access to another ACD if required.

- User permissions for ACD access are stored separately from the user ID created using <u>Before adding a CMS user</u> on page 216. Because of this, user permissions for the ACD can be deleted and modified without affecting the state of the user ID.
- If the ACD permissions for a user are changed, the change does not take effect until the user logs out and logs back in again.
- If the "read" and "write" permissions are disabled for a user, then the user will not be able to access any splits/skills, trunk groups, vectors, or VDNs in that ACD. If "read" is enabled and "write" is disabled, the user will not be able to modify splits/skills, trunk groups, vectors, or VDNs in that ACD.
- If the permissions for the default login ACD of a user are removed, the user must have another login ACD assigned.
- A user must be created before any ACD permissions can be assigned.
- Users should only have the ACD permissions necessary to perform job duties. Assigning only those necessary user permissions will ensure the best system performance.
- In some instances, it may be necessary to restrict a user from viewing information on an ACD. To do so, either delete the permissions definition for the user or remove all permissions for the necessary ACDs. Deleting the ACD permissions definition for a user will save more disk space.
- If the user permissions definition is deleted for the ACD that the user logs into, that user will
  no longer be able to log on. A new default login ACD must be set for the user. Deleting the
  permissions definition does not restrict the permissions for the user, but actually deletes the
  user from the specified ACD. This action does not affect the user ID created through the User
  Data feature.

## Permissions required to administer access to ACDs

Depending on the procedure that you want to do, you need the following permissions:

- To view user permission settings in the ACD Access window, the user ID must have "read" permission for the User Permissions subsystem.
- To add, delete, or modify user permission settings in the ACD Access window, the user ID must have "write" permission for the User Permissions subsystem.

## Viewing ACD access permissions using the Web Client

#### Procedure

#### Navigate to Administration > User Permissions > ACD Access.

CMS Supervisor displays the list of users administered for the system and to which ACDs they have Read or Write access.

## Adding ACD access permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > ACD Access.

CMS Supervisor displays the list of users administered for the system and to which ACDs they have Read or Write access.

#### 2. Click Add ACD Access.

CMS Supervisor displays the Add ACD Access window.

- 3. Administer the following options:
  - In the **User ID** field, select or search for the user ID to which you want to add access to an ACD or to exceptions for that ACD.
  - In the **ACD** field, select or search for the ACD to which you want the user to have access.
  - Select the Read, Write, and Exceptions options as required.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

## Modifying ACD access permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > ACD Access.

CMS Supervisor displays the list of users administered for the system and to which ACDs they have Read or Write access.

2. Click **Modify** on the user you want to change.

CMS Supervisor displays the Modify Item window.

- 3. Select the **Read**, **Write**, and **Exceptions** options as required. You cannot change any other options.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

## **Deleting ACD access permissions using the Web Client**

#### Procedure

1. Navigate to Administration > User Permissions > ACD Access.

CMS Supervisor displays the list of users administered for the system and to which ACDs they have Read or Write access.

2. Click **Remove** on the item you want to delete.

#### 😵 Note:

You cannot delete any of the ACDs assigned to the "cmssvc" user ID.

CMS Supervisor displays the Confirm Delete window.

3. Click **Yes** to continue with the change. Click **No** to cancel the operation.

CMS Supervisor displays a confirmation message.

4. Click **OK**.

CMS Supervisor displays an updated list of items.

## Viewing ACD user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight ACD Access.
- 3. Click OK.

Supervisor displays the User Permissions ACD Access window.

4. In the **User ID** field, enter the ID of the CMS user for which the permissions for ACDs are to be viewed.

This field is required.

When searching for the user permissions definitions on specific ACDs, these ACDs can be entered in the **ACDs** field. Multiple entries must be separated by a semicolon (;).

5. From the menu bar, select **Actions > Find one**.

The status bar displays how many matching permission definitions are available. The fields of this window display the user permissions definition for the first ACD.

If more than one ACD is returned, use the **Next** action to view the permission definitions for the other ACDs.

## Listing all ACD user permissions using the PC Client Procedure

From the Controller window, select Tools > User Permissions.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight ACD Access.
- 3. Click OK.

Supervisor displays the User Permissions ACD Access window.

4. From the menu bar, select Actions > List all.

All user permission definitions are displayed with their corresponding ACDs. Only those ACDs for which you have "read" permission will be shown.

## Adding ACD user permissions using the PC Client

#### **Procedure**

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight ACD Access.
- 3. Click OK.

Supervisor displays the User Permissions ACD Access window.

4. In the User ID field, enter the ID of the user for whom to create an ACD permissions definition.

This field is required.

5. In the **ACD** field, enter the names or numbers for one or more ACDs that this user will be able to access (real, pseudo, or group).

Multiple values in this field must be separated with a semicolon (;).

- 6. Place a check mark in the permissions that will be assigned to this user:
  - Read User can view but not modify information for the specified ACDs.
  - Write User can modify information on the specified ACDs. This permission requires that the user also have the "read" permission.
  - Exceptions User will receive notification of exceptions occurring on the specified ACDs.
- 7. After assigning the necessary permissions, select **Actions > Add** from the menu bar.

The ACD permissions for this user are saved.

It is possible to add permission definitions for multiple users at one time. To do so, enter multiple CMS users in the **User ID** field and separate them with semicolons (;). The ACDs specified in the **ACDs** field and the selected permissions are then created for these user IDs when the **Add** action is performed.

## Modifying ACD user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight ACD Access.
- 3. Click OK.

Supervisor displays the User Permissions ACD Access window.

4. In the **User ID** field, enter the ID of the CMS user for which the permissions for ACDs are to be modified.

When searching for the user permissions definitions on specific ACDs, these ACDs can be entered in the **ACDs** field. Multiple entries must be separated by a semicolon (;). These entries can include real ACDs, pseudo-ACDs, or ACD Groups.

5. From the menu bar, select **Actions > Find one**.

The status bar displays how many matching permission definitions are available. The fields of this window display the user permissions definition for the first ACD.

If more than one ACD is returned, use the **Next** action to view the permission definitions for the other ACDs.

- 6. Once the correct permission definition is displayed in the window, change the permissions by adding or removing check marks in the **Read**, **Write**, or **Exceptions** check boxes.
- 7. Once the permissions have been changed to the necessary settings, select **Actions** > **Modify** from the menu bar.

The user permissions definition for this ACD is updated and the status bar displays a Successful message.

## **Deleting ACD user permissions using the PC Client**

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

2. In the **Operations** list, highlight ACD Access.

3. Click OK.

Supervisor displays the User Permissions ACD Access window.

4. In the **User ID** field, enter the ID of the CMS user for which the permissions for ACDs are to be modified.

When searching for the user permissions definitions on specific ACDs, these ACDs can be entered in the **ACDs** field. Multiple entries must be separated by a semicolon (;). These entries can include real ACDs, pseudo-ACDs, or ACD Groups.

5. From the menu bar, select **Actions > Find one**.

The status bar displays how many matching permission definitions are available. The fields of this window display the user permissions definition for the first ACD.

If more than one ACD is returned, use the **Next** action to view the permission definitions for the other ACDs.

6. Once the correct permission definition is displayed in the window, select **Actions** > **Delete** from the menu bar.

The ACD permissions definition for this user is deleted and the status bar displays a Successful message.

7. Once the permissions have been changed to the necessary settings, select **Actions** > **Modify** from the menu bar.

The user permissions definition for this ACD is updated and the status bar displays a Successful message.

## About administering access to vector data

Vector permissions allow users to view data for vector reports, view vector configuration information, and change vector configurations. It is also used to configure which users receive exception notifications.

This feature is not available if the Vectoring product has not been purchased and installed.

## Before administering access to vector data

The following items should be read and understood before working with vector permissions:

- A CMS user ID must be created through the User Data feature before it can be assigned vector permissions.
- When a new user ID is created through the User Data feature, vector permission definitions for that user are not created. This is done to conserve disk space. When a vector permissions definition does not exist for a user ID, CMS will deny "read" and "write" access to vectors.

- A user ID must first have permissions for the ACD on which the vector resides before vector permissions can be assigned. If a user ID is assigned vector permissions and does not have the appropriate ACD permissions, Supervisor displays an error message.
- When the permissions definition for a user is added or modified, the change does not take effect until the user logs off and back on again.
- If a user does not have corresponding ACD permissions for the permissions set for them on the vector, Supervisor displays an error message.
- A user ID cannot be assigned the "write" permission without first having the "read" permission.
- Assigning only those permissions that are necessary for each user ID ensures the best system performance.
- A user must be given the "Exceptions" permission in order to be notified of vector exceptions that occur.
- The wildcard characters "\*" and "?" cannot be used.
- The tenant user cannot be given permissions to vectors unless the vectors are assigned to the tenant to which the tenant user is assigned.
- The tenant user must have the permissions for the tenant to which the vectors belong.
- The permissions for the vectors cannot be greater than the permissions given to the tenant to which the vectors belong.

## Permissions required to administer access to vector data

Depending on the procedure that you want to do, you need the following permissions:

- To view vector user permissions, the user ID must have "read" permission for the User Permissions subsystem.
- To add, delete, or modify vector user permissions, the user ID must have "write" permission for the User Permissions subsystem.

## Viewing vector data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Vector Access.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer vector data user permissions.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the selected ACD.

## Adding vector data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Vector Access.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer vector data user permissions.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the selected ACD.

3. Click Add Vector Access.

CMS Supervisor displays the Add Vector Access window.

- 4. Administer the following options:
  - In the **User ID** field, select, search, or enter the user ID to which you want to add access to vector data or to exceptions.
  - In the **Vectors** field, enter the vector names or IDs to which you want the user to have access. Use the **Search Results** windows to select multiple vectors.
  - Select the Read, Write, and Exceptions options as required.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

# Modifying vector data user permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > Vector Access.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer vector data user permissions.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Select the **Read**, **Write**, and **Exceptions** options as required. You cannot change any other options.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

## Deleting vector data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Vector Access.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer vector data user permissions.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **Yes** to continue with the change. Click **No** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

# Viewing vector data user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Vector Access**.
- 3. In the **ACD** field, select the ACD containing the vector for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions Vector Access window.

- 5. In the **User ID** field, enter the name of the user for which the vector permissions definition is to be viewed.
- 6. If the specific vector to view for this user is known, enter the name or number of the vector in the **Vectors** field. To have all vectors returned for this user ID, leave this field blank.

This field can accept multiple vectors. Multiple entries must be separated by a semicolon (;).

7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID displays in the status bar.

# Listing all vector data user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Vector Access**.
- 3. In the **ACD** field, select the ACD containing the vector for which all permission definitions will be shown.
- 4. Click OK.

Supervisor displays the User Permissions Vector Access window.

5. From the menu bar, select **Actions** > **List all**.

Supervisor displays a secondary window listing all user permissions for vectors on the specified ACD.

A filter can be created when listing all user vector permission definitions. This filter is based on any information contained in the fields on this dialog box when the **List all** action is performed.

For example, to view all of the user permission definitions for vector 1, enter 1 in the **Vectors** field before performing the **List all** action. This will cause only the user permission definitions for vector 1 to display. If more information is entered into the other fields of this dialog box, the results will be more restricted. If information for the user ID, vectors, and permissions are entered, the **List all** command will only return those permission definitions which match all of the information.

#### Adding vector data user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Vector Access**.
- 3. In the **ACD** field, select the ACD containing the vector for which the user will be given permissions.
- 4. Click OK.

Supervisor displays the User Permissions Vector Access window.

- 5. In the **User ID** field, enter the name of the user who will be assigned vector permissions.
- 6. In the **Vectors** field, enter the name or number of the vector for which the user will have permissions assigned.

This field can accept multiple vectors. Multiple entries must be separated by a semicolon (;).

- 7. Place a check mark in the permissions that will be assigned to this user:
  - **Read** User can view but not modify information for the specified vectors including reports.
  - Write User can modify information on the specified vectors. This permission requires that the user also have the "read" permission.
  - **Exceptions** User will receive notification of exceptions occurring on the specified vectors.

Only the vector exceptions made active through the **Exceptions** feature will provide notification to the user. See <u>Chapter 9: Administering exceptions</u> on page 271 for more information.

8. After assigning the necessary permissions, select **Actions > Add** from the menu bar.

The vector permissions for this user are saved.

It is possible to add permission definitions for multiple vectors at one time. To do so, enter multiple vectors in the **Vectors** field and separate them with semicolons (;).

#### Modifying vector data user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Vector Access**.
- 3. In the **ACD** field, select the ACD containing the vector for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions Vector Access window.

- 5. In the **User ID** field, enter the name of the user for which the vector permissions definition is to be modified.
- 6. If the specific vector to view for this user is known, enter the name or number of the vector in the **Vectors** field.

To have all vectors returned for this user ID, leave this field blank. This field can accept multiple vectors. Multiple entries must be separated by a semicolon (;).

7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID displays in the status bar. The first match found populates the fields of this dialog box.

If multiple matches are found, use the **Next** and **Previous** items found under the **Actions** menu to navigate to the correct vector.

- 8. Change the permissions for the user on this vector as needed:
  - **Read** User can view but not modify information for the specified vectors including reports.
  - Write User can modify information on the specified vectors. This permission requires that the user also have the "read" permission.
  - **Exceptions** User will receive notification of exceptions occurring on the specified vectors.

Only the vector exceptions made active through the **Exceptions** feature will provide notification to the user. See <u>Chapter 9: Administering exceptions</u> on page 271 for more information.

9. After the necessary permission changes have been completed, select **Actions** > **Modify** from the menu bar.

The permissions definition for this user ID and vector is updated. The status bar displays a Successful message upon completion.

## Deleting vector data user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **Vector Access**.
- 3. In the **ACD** field, select the ACD containing the vector for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions Vector Access window.

- 5. In the **User ID** field, enter the name of the user for which the vector permissions definition is to be deleted.
- 6. If the specific vector to view for this user is known, enter the name or number of the vector in the **Vectors** field. To return all vectors for this user ID, leave this field blank.
- 7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID displays in the status bar. The first match found populates the fields of this dialog box.

If multiple matches are found, use the **Next** and **Previous** items found under the **Actions** menu to navigate to the correct vector.

8. From the menu bar, select **Actions > Delete**.

The permissions definition for this user ID and the associated vector is deleted. The status bar displays a successful message upon completion of the action.

This action does not delete the permission definitions for all vectors for this user, only the one displayed in the **Vectors** field.

# About administering access to VDN data

Vector Directory Number (VDN) permissions allow users to view data for VDN reports, view VDN configuration information, and change VDN configurations. It is also used to configure which users receive exception notifications.

This feature is not available if the Vectoring product has not been purchased, installed, and enabled on the corresponding ACD.

## Before administering access to VDN data

The following items should be read and understood before working with VDN permissions:

- A CMS user ID must be created through the User Data feature before it can be assigned VDN permissions.
- When a new user ID is created through the User Data feature, VDN permission definitions for that user are not created. This is done to conserve disk space. When a VDN permissions definition does not exist for a user ID, CMS denies "read" and "write" access to VDNs.
- A user ID must first have permissions for the ACD on which the VDN resides before VDN permissions can be assigned. If a user ID is assigned VDN permissions and does not have the appropriate ACD permissions, Supervisor an error message.
- When the permissions definition for a user is added or modified, the VDN permissions do not take effect until the user logs off and back on again.

- A user ID cannot be assigned the "write" permission without first having the "read" permission.
- Assigning only those permissions that are necessary for each user ID ensures the best system performance.
- A user must be given the "exceptions" permission in order to be notified of VDN exceptions that occur.
- The wildcard characters "\*" and "?" cannot be used.
- The tenant user cannot be given permissions to VDNs unless the VDNs are assigned to the tenant to which the tenant user is assigned.
- The tenant user must have the permissions for the tenant to which the VDNs belong.
- The permissions for the VDNs cannot be greater than the permissions given to the tenant to which the VDNs belong.

## Permissions required to administer access to VDN data

Depending on the procedure that you want to do, you need the following permissions:

- To view VDN user permissions, the user ID must have "read" permission for the User Permissions subsystem.
- To add, delete, or modify VDN user permissions, the user ID must have "write" permission for the User Permissions subsystem.

## Viewing VDN data user permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > VDN Access.

CMS Supervisor displays the list of administered users and their current VDN data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDN data user permissions.

CMS Supervisor displays the list of administered users and their current VDN data and exception access permissions for the selected ACD.

## Adding VDN data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > VDN Access.

CMS Supervisor displays the list of administered users and their current VDN data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDN data user permissions.

CMS Supervisor displays the list of administered users and their current VDN data and exception access permissions for the selected ACD.

3. Click Add VDN Access.

CMS Supervisor displays the Add VDN Access window.

- 4. Administer the following options:
  - In the **User ID** field, select, search, or enter the user ID to which you want to add access to VDN data or to exceptions.
  - In the **VDNs** field, enter the VDN names or IDs to which you want the user to have access. Use the **Search Results** windows to select multiple vectors.
  - Select the Read, Write, and Exceptions options as required.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

# Modifying VDN data user permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > VDN Access.

CMS Supervisor displays the list of administered users and their current VDN data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer VDN data user permissions.

CMS Supervisor displays the list of administered users and their current VDN data and exception access permissions for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Select the **Read**, **Write**, and **Exceptions** options as required. You cannot change any other options.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

## Deleting VDN data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Vector Access.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer vector data user permissions.

CMS Supervisor displays the list of administered users and their current vector data and exception access permissions for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click Yes to continue with the change. Click No to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

## Viewing VDN data user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools** > **User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **VDN Access**.
- 3. In the **ACD** field, select the ACD containing the VDN for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions VDN Access window.

- 5. In the **User ID** field, enter the name of the user for which the VDN permissions definition is to be viewed.
- 6. If the specific VDN to view for this user is known, enter the name or number of the VDN in the **VDNs** field. To have all VDNs returned for this user ID, leave this field blank.

This field can accept multiple VDNs. Multiple entries must be separated by a semicolon (;).

7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID is displayed in the status bar.

## Listing all VDN data user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **VDN Access**.
- 3. In the **ACD** field, select the ACD containing the VDN for which all permission definitions will be shown.
- 4. Click OK.

Supervisor displays the User Permissions VDN Access window.

5. From the menu bar, select **Actions > List all**.

Supervisor displays a secondary window listing all user permissions for VDNs on the specified ACD.

A filter can be created when listing all user VDN permission definitions. This filter is based on any information contained in the **User ID** and **VDNs** fields on this dialog box when the **List all** action is performed.

For example, to view all of the user permission definitions for VDN 10, enter 10 in the **VDNs** field before performing the **List all** action. This will cause only the user permission definitions for VDN 10 to display. If more information is entered into the other fields of this dialog box, the results will be more restricted. If information for the user ID, VDNs, and permissions are entered, the **List all** command will only return those permission definitions which match all of the information.

## Adding VDN data user permissions using the PC Client

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **VDN Access**.
- 3. In the **ACD** field, select the ACD containing the VDN for which the user will be given permissions.
- 4. Click **OK**.

Supervisor displays the User Permissions VDN Access window.

- 5. In the **User ID** field, enter the name of the user who will be assigned VDN permissions.
- 6. In the **VDNs** field, enter the name or number of the VDN for which the user will have permissions assigned.

This field can accept multiple VDNs. Multiple entries must be separated by a semicolon (;).

- 7. Place a check mark in the permissions that will be assigned to this user:
  - **Read** User can view but not modify information for the specified VDNs including reports.
  - Write User can modify information on the specified VDNs. This permission requires that the user also have the "read" permission.
  - **Exceptions** User will receive notification of exceptions occurring on the specified VDNs.

Only the VDN exceptions made active through the **Exceptions** feature will provide notification to the user. See <u>Chapter 9: Administering exceptions</u> on page 271 for more information.

8. After assigning the necessary permissions, select **Actions > Add** from the menu bar.

The VDN permissions for this user are saved.

It is possible to add permission definitions for multiple VDNs at one time. To do so, enter multiple VDNs in the **VDNs** field and separate them with semicolons (;).

## Modifying VDN data user permissions using the PC Client Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **VDN Access**.
- 3. In the **ACD** field, select the ACD containing the VDN for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions VDN Access window.

- 5. In the **User ID** field, enter the name of the user for which the VDN permissions definition is to be modified.
- 6. If the specific VDN to view for this user is known, enter the name or number of the VDN in the **VDNs** field.

To have all VDNs returned for this user ID, leave this field blank.

This field can accept multiple VDNs. Multiple entries must be separated by a semicolon (;).

7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID displays in the status bar. The first match found populates the fields of this dialog box.

If multiple matches are found, use the **Next** and **Previous** items found under the **Actions** menu to navigate to the correct VDN.

- 8. Change the permissions for the user on this VDN as needed:
  - **Read** User can view but not modify information for the specified VDNs including reports.
  - Write User can modify information on the specified VDNs. This permission requires that the user also have the "read" permission.
  - **Exceptions** User will receive notification of exceptions occurring on the specified VDNs.

Only the VDN exceptions made active through the **Exceptions** feature will provide notification to the user. See <u>Chapter 9: Administering exceptions</u> on page 271 for more information.

9. After the necessary permission changes have been completed, select **Actions** > **Modify** from the menu bar.

The permissions definition for this user ID and VDN is updated. The status bar displays a <code>Successful</code> message upon completion.

# Deleting VDN data user permissions using the PC Client

#### About this task

This section provides the procedure for deleting the VDN permissions definition for a CMS user.

#### Procedure

1. From the Controller window, select **Tools > User Permissions**.

CMS Supervisor displays the User Permissions window.

- 2. In the **Operations** list, highlight **VDN Access**.
- 3. In the **ACD** field, select the ACD containing the VDN for which the user has a permissions definition.
- 4. Click OK.

Supervisor displays the User Permissions VDN Access window.

- 5. In the **User ID** field, enter the name of the user for which the VDN permissions definition is to be deleted.
- 6. If the specific VDN to view for this user is known, enter the name or number of the VDN in the **VDNs** field. To return all VDNs for this user ID, leave this field blank.
- 7. From the menu bar, select **Actions > Find one**.

The database is queried and the number of matches found for this user ID displays in the status bar. The first match found populates the fields of this dialog box.

If multiple matches are found, use the **Next** and **Previous** items found under the **Actions** menu to navigate to the correct VDN.

8. From the menu bar, select **Actions > Delete**.

The permissions definition for this user ID and the associated VDN is deleted. The status bar displays a Successful message upon completion of the action.

This action does not delete the permission definitions for all VDN for this user, only the one displayed in the **VDNs** field.

# About administering access to tenant data

Tenant permissions allow users to view data for view tenant configuration information and change tenant configurations. It is also used to configure which users receive exception notifications.

This feature is not available if the Tenant feature package has not been licensed and installed.

## Before administering access to tenant data

The following items should be read and understood before working with tenant permissions:

- A CMS user ID must be created through the User Data feature before it can be assigned tenant permissions.
- When a new user ID is created through the User Data feature, tenant permission definitions for that user are not created. This is done to conserve disk space. When a tenant permissions definition does not exist for a user ID, CMS will deny "read" and "write" access to tenants.
- A user ID must first have permissions for the ACD on which the tenant resides before tenant permissions can be assigned. If a user ID is assigned tenant permissions and does not have the appropriate ACD permissions, Supervisor displays an error message.
- When the permissions definition for a user is added or modified, the change does not take effect until the user logs off and back on again.
- If a user does not have corresponding ACD permissions for the permissions set for them on the tenant, Supervisor displays an error message.
- A user ID cannot be assigned the "write" permission without first having the "read" permission.
- Assigning only those permissions that are necessary for each user ID ensures the best system performance.

- A user must be given the "Exceptions" permission in order to be notified of tenant exceptions that occur.
- The wildcard characters "\*" and "?" cannot be used.
- The tenant user cannot be given permissions to tenants unless the tenants are assigned to the tenant to which the tenant user is assigned.
- The tenant user must have the permissions for the tenant to which the tenants belong.

#### Permissions required to administer access to tenant data

Depending on the procedure that you want to do, you need the following permissions:

- To view tenant user permissions, the user ID must have "read" permission for the User Permissions subsystem.
- To add, delete, or modify tenant user permissions, the user ID must have "write" permission for the User Permissions subsystem.

# Viewing tenant data user permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > Tenant Access.

CMS Supervisor displays the list of administered users and their current tenant data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer tenant data user permissions.

CMS Supervisor displays the list of administered users and their current tenant data and exception access permissions for the selected ACD.

# Adding tenant data user permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > Tenant Access.

CMS Supervisor displays the list of administered users and their current tenant data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer tenant data user permissions.

CMS Supervisor displays the list of administered users and their current tenant data and exception access permissions for the selected ACD.

3. Click Add Tenant Access.

CMS Supervisor displays the Add Tenant Access window.

- 4. Administer the following options:
  - In the **User ID** field, select, search, or enter the user ID to which you want to add access to tenant data or to exceptions.
  - In the **Tenants** field, enter the tenant names or IDs to which you want the user to have access. Use the **Search Results** windows to select multiple tenants.
  - Select the Read, Write, and Exceptions options as required.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

## Modifying tenant data user permissions using the Web Client

#### Procedure

1. Navigate to Administration > User Permissions > Tenant Access.

CMS Supervisor displays the list of administered users and their current tenant data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer tenant data user permissions.

CMS Supervisor displays the list of administered users and their current tenant data and exception access permissions for the selected ACD.

3. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 4. Select the **Read**, **Write**, and **Exceptions** options as required. You cannot change any other options.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click **OK**.

CMS Supervisor displays an updated list of items.

## Deleting tenant data user permissions using the Web Client Procedure

1. Navigate to Administration > User Permissions > Tenant Access.

CMS Supervisor displays the list of administered users and their current tenant data and exception access permissions for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer tenant data user permissions.

CMS Supervisor displays the list of administered users and their current tenant data and exception access permissions for the selected ACD.

3. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

4. Click **Yes** to continue with the change. Click **No** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

## Administering access to tenant data using the PC Client

Use **Tools** > **User Permissions** to go to the **Tenant Access** menu item under the **Operations** list. Administrators must use **Tenant Access** to assign tenant permissions to users.

Tenant permissions have the following implications:

- For administrators and normal users, specific tenant permissions combined with tenant and dictionary feature permissions control the following:
  - whether the user can read and write tenant assignments for the specified tenant number.
  - whether the user can read and write the tenant dictionary name for the specified tenant number.
- For tenant users, specific tenant permissions combined with tenant and dictionary feature permissions control the following:
  - whether the user can read tenant assignments for the specified tenant number. It should be noted that tenant users are not allowed to have write permission for the Tenant feature and thus will never be able to add/delete tenant assignments.
  - When VDN, split/skill, and trunk group permissions are administered for a tenant user, the permissions for the associated tenant is checked to ensure that the tenant user has proper permissions for the associated tenant.
  - A tenant user can only access agents and tenant agent groups when the tenant user has proper permissions for the associated tenant for the agents/agent groups.

The Tenant Access window includes the following fields:

- User ID is the user's operating system (Linux) login identification.
- Tenant Number must be between 1 and 250.

• Read, Write, or Exceptions fields only allow y or n.

## **Tenant access operations using the PC Client**

The Tenant Access window provides an action list containing the following actions:

Field	Description
Add	Adds the User id with the specified permissions on the current user window to the database. If an entry already exists, the system displays Already exists on the window status line. The user must have write permission for the User Permissions feature.
Delete	Removes the User Id and the associated permissions on the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the User Permissions feature. When a tenant permission record is deleted for a tenant user, all the permissions of the tenant user for the tenant's associated splits/skills, trunk groups, and VDNs are also deleted.
Find one	Finds an entry in the database that matches all the field values on the current window. The status line for the current window indicates the total number of matches found. The user must have read permission for the User Permissions feature.
Modify	Modifies the permissions of the user id entered in the current user window. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the User Permissions feature. When a tenant permission record is modified to be more restricted for a tenant user, the restriction is propagated down to all the user's permissions for the tenant's associated splits/skills, trunk groups, and VDNs.
List all	Lists all entries that match all the field values currently present in the Tenant Access window . The user must have read permission for the User Permissions feature.
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.

# **Chapter 8: Administering exceptions**

# About administering exceptions

This section provides the procedures for administering exceptions, running the Real-time Exception Log report, and running other exception reports for the following exception areas:

- Agent
- · Split or skill
- Trunk group
- VDN
- Vector
- Data Collection
- · Malicious call trace
- · Real-time exceptions log

# About exceptions

An exception is a type of activity in the ACD that falls outside the limits that have been defined and could indicate unacceptable performance. Exceptions are gathered on agents, splits, skills, trunk groups, VDNs, vectors, and unusual events such as Malicious Call Trace and disruptions in data collection. This section describes the operations, prerequisites, and rules for administering exceptions and the different types of exception reports that are available.

You can administer exceptions and generate reports for VDNs and vectors if your company has purchased the Call Vectoring feature.

You can administer exceptions and generate reports for skills if your company has purchased the Expert Agent Selection (EAS) feature.

## Types of exceptions

An exception can be one of three types:

- Peg count
- Agent timed
- Other timed exceptions

#### **Peg count exceptions**

A peg count exception occurs when the number of occurrences of an ACD activity exceeds an occurrence threshold that is defined for your call center in the current interval.

The current interval is a set number of either 15, 30, or 60 minutes. Many CMS exceptions are measured based on this interval.

Most exception conditions apply to ACD events that occur within the current interval that is defined for your call center. When the current interval changes, ACD event occurrences are cleared and CMS begins to count event occurrences again. Therefore, your exception conditions should realistically reflect what you want to trigger an exception within your current interval.

#### Agent timed exceptions

Agent timed exceptions are tracked from the time that the agent logs in until the agent logs out. These exceptions can occur many times during the login period and within an interval. The exception count is cleared when the agent leaves the state that triggered the exception.

For example, an agent timed exception could be configured to occur whenever an agent spends more than 5 minutes in the AUX work mode. Then, when an agent spends longer than 5 minutes in the AUX work mode, an exception is triggered for that agent. When the agent changes to another state, such as AVAIL, the exception is reset so that it can occur again when the agent reenters the AUX work mode.

#### Other timed exceptions

Other timed exceptions are triggered when the number of ACD activity occurrences exceeds the minimum or maximum time limits that are set for such activity.

For example, you may set the time limit at 20 seconds for any call to wait in queue before being answered. You may then define an occurrence boundary of three for the acceptable number of calls that can wait in the queue for 20 seconds. An exception occurs if more than three calls wait in the queue longer than 20 seconds within an interval.

Timed occurrence boundaries for this type of exception apply to ACD activity within the last interval. At the beginning of the next interval, the occurrence count for any timed exception type, except for agent timed exceptions, is cleared and starts again from zero. However, since the time limit for a timed exception type can be more than one hour, the duration of an exception activity is not cleared at the end of the intrahour interval. CMS continues to track the time that is spent on an exception activity that continues from one interval to the next for this type of exception.

Currently, the system sends the following data collection exceptions when the link is active:

- ACD <number>: data collection started
- ACD <number>: data collection started new translations

When the primary Communication Manager system starts collecting data the exceptions are generated. When the secondary Communication Manager system starts collecting the data, one of the following new exceptions is generated:

- ACD <number>: data collection to the secondary Communication Manager system started
- ACD <number>: data collection to the secondary Communication Manager system started new translations

All exceptions mentioned are displayed on **Exception**, **Real-time Exception Log and Exception**, **Historical Reports**, **Other Exceptions**, **Data Collection** screens.

## Notification when exceptions occur

The status bar of the CMS Supervisor window shows the current exception total for both the peg count and time exceptions. This exception total is for all of the ACDs for which you have permission to view exceptions. The exception count is cleared at the end of each interval and can display a maximum number of 9999.

By default, the PC on which CMS Supervisoris running is configured to beep each time an exception occurs if the user has the "exceptions" permission for the entity on which the exception occurred. You can change this default sound setting.

## **Exception capacities**

CMS requires that you define the storage space on the server to record the activities of the contact center. The recording of exceptions also uses this storage space. The limits for recording exceptions are provided in the *Avaya Aura*<sup>®</sup> *Communication Manager System Capacities Table*. The following items provide information on the way CMS handles recording of exceptions:

- CMS can store exception records of each element on all ACDs. There are exception records stored for elements like agents, split/skill, trunk groups, VDNs, and vectors across all ACDs.
- You can retrieve the stored exception records from ACDs. The exception retrieval capacity is the number of days in the past for which you can retrieve exceptions. This is determined by the following criteria:
  - The number of exception records that are allocated for storage in the **Data Storage** operation in the System Setup window.
  - The frequency with which exceptions are recorded each day. For example, if you allocate storage for 1000 exception records and approximately 100 exceptions occur each day, you can save exception records for nearly 10 days.

# Before using exceptions

The following items should be read and understood before you begin working with exceptions:

• If an ACD Group is selected as the current ACD in the Exceptions window, only those operations that are valid for the ACD Group will appear in the **Operations** list.

When exception thresholds are configured, the following rules must be followed:

- The occurrence threshold for any exception must be between 0 to 999.
- The time limit for timed exceptions must be between 0 to 28800 seconds.
- If a time limit is entered for an activity, an occurrence threshold for that activity must also be entered.
- When an exception is made active, CMS starts checking for the exception immediately as long as data collection is activated.
- When at least one exception is added to an entity, any future additions must be made by using the **Modify** item on the **Actions** menu.
- When exceptions are being modified, the **Find one** menu item should always be used to retrieve the current settings for the exception before any changes are made.
- The default setting for most exceptions is "off". However, the following exceptions are always active and cannot be stopped:
  - Malicious call trace
  - Data collection disruptions
  - Audio difficulty
  - Agent attempts to log in with more than one login ID

# Permissions required to administer exceptions

The following table describes the permission settings that are required in order for a user to access exception information:

Does the user have "read" permission for the Exceptions feature?	and "exceptions" permission for splits/skills, trunk groups, ACDs, vectors, and VDNs?	Then, the user can use the following exception information:
yes	yes	Exception reports
		<ul> <li>Messages in the Real-Time Exception Log</li> </ul>
		<ul> <li>Real-time notification of exceptions</li> </ul>
yes	no	<ul> <li>Exceptions reports</li> </ul>
no	yes	<ul> <li>Real-time notification of exceptions</li> </ul>
no	no	<ul> <li>No exceptions features available to this user</li> </ul>

Setting the exception permissions for these entities can be done through **Tools** > **User Permissions** on the CMS Supervisor Controller window.

#### Other permissions

To set up or change the method in which the system checks for exceptions, the user ID used to log in to this Supervisor session requires the "write" permission for the Exceptions feature.

To be notified of a malicious call exception, the user ID used to log in to this Supervisor session requires the "exception" permission for the appropriate call center entity.

# About administering exception notification using the PC Client

An exception notification is a beep that is sounded by the CMS Supervisor PC Client when an exception is encountered. By default, this occurs when the user who is currently logged in to CMS Supervisor has the "exceptions" permission for the entity on which the exception occurred. If you do not want CMS Supervisor to beep when an exception occurs, you can turn off notifications.

#### 😵 Note:

Exception notification administration is available only using the PC Client.

## Changing exception notification using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Options**.

Supervisor displays the Options window.

- 2. Select the **General** tab.
- 3. Perform one of the following actions:
  - To activate exception notification, select the **Use Sound** option.
  - To turn off exception notification, deselect the **Use Sound** option.
- 4. Select OK.

# About administering agent exceptions

Agent exceptions can occur for many different activities in relation to an agent. These can include the amount of time on a call or in a work state, the number of calls that an agent has in queue, and other activities. This section provides the procedure for configuring if and when these exceptions are checked by CMS.

## Before using agent exceptions

The following items should be read and understood before working with agent exceptions:

- Agent exceptions are assigned per split/skill and not for each agent. When an agent logs into a split/skill, any exceptions that are configured for that split/skill are applied to the agent.
- External outbound exceptions are a subset of outbound exceptions. If both types of exceptions are administered, the limit for external outbound covers external outbound calls and the limit for outbound covers only internal outbound calls.
- The agent exceptions record for a split/skill are not created by default in the CMS database when the split/skill is created. If a split/skill does not have agent exceptions, an **Add** action must be taken to create the associated agent exceptions record.

## Permissions required to administer agent exceptions

Depending on the procedure that you want to perform, you need the following permissions:

- To view agent exceptions, the user ID used to log in to this Supervisor session requires "read" permission for the Exceptions subsystem and all affected splits or skills as well as the "exceptions" permission for the affected splits or skills.
- To add, delete, or modify agent exceptions, the user ID used to log in to this Supervisor session requires "write" permission for the Exceptions subsystem and all affected splits or skills as well as the "exceptions" permission for the affected splits or skills.

# Administering agent exceptions using the Web Client

#### About this task

Use this procedure to add new exception types, modify options for existing exception types, and remove options for existing exception types.

#### Procedure

- 1. Navigate to one of the following agent exception menus:
  - Administration > Exceptions > Agent Exceptions
  - Administration > Exceptions > Agent Exceptions Reason Codes 0-49
  - Administration > Exceptions > Agent Exceptions Reason Codes 50-99

CMS Supervisor displays the Agent Exceptions window for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer an exception.

CMS Supervisor displays the Agent Exceptions window for the selected ACD.

3. In the **Split/Skill** field, enter the name or number of the split or skill for which an exception is to be created.

If the selected item has exceptions assigned, the system displays the exception assignments in the window. If exceptions are not assigned, the system displays a message that no exceptions were found.

- 4. (Optional) In the Select additional splits/skills (optional) field, enter the name or number of a split or skill to which you want to assign an exception. The field can accept multiple entries separated by semicolons (;) if you want to assign the same exceptions to several splits or skills. You can assign exceptions to as many as 32 splits or skills in one operation.
- 5. Use the plus and minus controls or click the split or skill names to move splits or skills between the Search Results and Selected Split(s)/Skill(s) panes. Repeat this step until the splits or skills to which you want to assign exceptions are in the Selected Split(s)/ Skill(s) pane.
- Administer the following options for each exception type you want to activate for the selected splits or skills. The exception types are described in <u>Agent exception</u> <u>definitions</u> on page 281.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this

activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.

- **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. Do one of the following operations:
  - Click Add when adding a new set of exceptions.
  - Click **Modify** when modifying settings for an existing set of exceptions.
  - Click **Remove** when you want to remove all administered exceptions.
  - Click **Clear** to clear any settings you have changed before doing an add, modify, or remove operation.

CMS Supervisor displays a confirmation message after doing an add, modify, or remove operation.

## Adding agent exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD for the split/skill where agent exceptions are to be created.
- 3. In the **Operations** list, highlight **Agent Exceptions**.

#### Note:

If you need to add agent exceptions for AUX reason codes 10 through 99, select the appropriate operation for **Agent Exceptions Reason Codes 0-49** and **Agent Exceptions Reason Codes 50-99**.

4. Click OK.

Supervisor displays the Agent Exceptions Administration window.

This window appears with all fields blank when first opened.

😵 Note:

This is a scrolling dialog box that contains more exceptions than those shown in the above graphic. Use the scroll bar on the right side of the dialog box to view the other exceptions.

5. In the **Split(s)/Skill(s)** field, enter the name or number of the split/skill for which an agent exceptions configuration is to be created.

The **Split(s)/Skill(s)** field can accept multiple entries. Each entry must be separated by a semicolon (;).

- Administer the following options for each exception type you want to activate for the selected splits or skills. The exception types are described in <u>Agent exception</u> <u>definitions</u> on page 281.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. When all necessary time limits and thresholds have been entered, select **Actions** > **Add** from the menu bar.

The exception configuration data will be saved for this split/skill and the status bar displays a "Successful" message.

## Modifying agent exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD on which the split/skill to modify for agent exceptions resides.
- 3. In the **Operations** list, highlight **Agent Exceptions**.

#### 😵 Note:

If you need to add agent exceptions for AUX reason codes 10 through 99, select the appropriate operation for **Agent Exceptions Reason Codes 0-49** and **Agent Exceptions Reason Codes 50-99**.

4. Click OK.

Supervisor displays the Agent Exceptions Administration window.

This window appears with all fields blank when first opened.

#### 😵 Note:

This is a scrolling dialog box that contains more exceptions than those shown in the above graphic. Use the scroll bar on the right side of the dialog box to view the other exceptions.

- 5. In the **Split(s)/Skill(s)** field, enter the name or number of the split/skill for which the agent exceptions configuration is to be modified.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor locates the agent exception configuration for the specified split/skill and displays the data in the appropriate fields. If the exception configuration data cannot be found, the status bar displays 0 matches found.

To return all splits/skills, leave the **Split(s)/Skill(s)** field blank before performing the **Find one** action. Supervisor will return all split(s)/skill(s) for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the splits/skills.

- Administer the following options for each exception type you want to activate for the selected splits or skills. The exception types are described in <u>Agent exception</u> <u>definitions</u> on page 281.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 8. When all necessary time limits and thresholds have been modified, select **Actions** > **Modify** from the menu bar.

Supervisor updates the data for this split/skill and displays a Successful message in the status bar.

## Deleting agent exceptions using the PC Client Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the ACD field, select the ACD on which the split/skill to delete resides.
- 3. In the **Operations** list, highlight **Agent Exceptions**.

#### Note:

If you need to add agent exceptions for AUX reason codes 10 through 99, select the appropriate operation for **Agent Exceptions Reason Codes 0-49** and **Agent Exceptions Reason Codes 50-99**.

4. Click OK.

Supervisor displays the Agent Exceptions Administration window.

#### 😵 Note:

This is a scrolling dialog that contains more exceptions than those shown in the above graphic. Use the scroll bar on the right side of the dialog to view the other exceptions.

- 5. In the **Split(s)/Skill(s)** field, enter the name or number of the split/skill for which an agent exceptions configuration is to be deleted.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor locates the agent exception configuration for the specified split/skill and displays the data in the appropriate fields. If exception configuration data cannot be found, the status bar displays 0 matches found.

To return all splits/skills, leave the **Split(s)/Skill(s)** field blank before performing the **Find one** action. Supervisor will return all split(s)/skill(s) for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the splits/skills.

7. From the menu bar, select **Actions > Delete**.

Supervisor deletes the agent exception configuration for this split/skill from the CMS database and displays a Successful message in the status bar.

## Agent exception definitions

The following table provides the definitions for the different agent exceptions:

Exception	Definition
Time Available	The time that an agent spends in AVAIL (this is idle time).
Time on inbound ACD call (min)	The minimum time that an agent spends on an ACD call.
Time on inbound ACD call (max)	The maximum time that an agent spends on an ACD call.
Time in after call work	The maximum time that an agent spends on after-call work.

Table continues...

Exception	Definition
Time on inbound ACW call	The maximum time that an agent spends on an inbound call during after-call work.
Number of inbound ACW calls/agent	The total number of inbound calls that an agent can receive during after-call work. This exception can only be triggered once per interval.
Time on outbound ACW call	The maximum time that an agent spends on an outbound call during after-call work.
Number of outbound ACW calls/agent	The total number of outbound calls that an agent can make during after-call work. This exception can only be triggered once per interval.
Time in AUX work	The maximum time that an agent spends doing auxiliary work.
Time on inbound AUX call	The maximum time that an agent spends on an inbound call during auxiliary work.
Number of inbound AUX calls/agent	The total number of inbound calls that an agent can receive during auxiliary work. This exception can only be triggered once per interval.
Time on outbound AUX call	The maximum time that an agent spends on an outbound call during auxiliary work.
Number of outbound AUX calls/agent	The total number of outbound calls that an agent can place during auxiliary work. This exception can only be triggered once per interval.
Time in AUX with Reason Code X	The maximum time that agents can spend doing auxiliary work with Reason Code X (X is from 0 to 99). Note that the user interface has these screens divided between codes 0 to 49 and 50 to 99.
Login identification	Select <b>Active</b> to receive a notification of a login violation. A violation occurs when an agent attempts to log in with an ID that is not in the Dictionary or if an agent tries to log in with more than one ID at the same terminal. If you deactivate this exception, you are not notified if an agent logs in with an ID that is not in the Dictionary, but you still are notified if an agent tries to log in with more than one ID.
Time on outbound ACD call (min)	The minimum time that an agent spends on an outbound ACD call.
Time on outbound ACD call (max)	The maximum time that an agent spends on an outbound ACD call.
Number calls transferred	The maximum number of calls that an agent can transfer.
Time ACD call spent on hold	The maximum time that an agent can put an ACD call on hold. This time value is cumulative for each call. If an agent removes a call from hold and places it back on hold again, this value is not reset.

Table continues...

Exception	Definition
Number ACD calls placed on hold	The maximum number of ACD calls that an agent can put on hold. This exception can only be triggered once per interval.
Number ACD calls abandoned while on hold	The maximum number of calls that are abandoned after being put on hold by an agent. This exception can only be triggered once per interval.
Time ACD call spends ringing	The maximum time that a split/skill or direct agent ACD call can ring at agent's voice terminal before an exception is triggered.
Ringing call automatically redirected from agent	Select <b>Active</b> to be notified when an agent lets an ACD call ring at the voice terminal long enough for the switch to automatically redirect the call. You must have the Redirection on No Answer feature activated on the Communication Manager system to use this exception.
Time on direct agent call	The maximum number of seconds that an agent spends on a direct agent ACD call.
Number calls in direct agent queue	The maximum number of direct agent ACD calls that an agent can have waiting in queue.
Time call waited in direct agent queue	The maximum time that any call waits in the direct agent queue.
Number calls abandoned from direct agent queue	The maximum number of direct agent ACD calls that can leave the direct agent queue by abandoning before an exception is triggered. This exception can only be triggered once per interval.
Number calls outflowed from direct agent queue (maximum)	The maximum number of direct agent calls that outflow from the direct agent queue. This exception can only be triggered once per interval.
Time on external outbound ACW call	The maximum number of seconds that an agent spends on an external outbound call during after-call work.
Number external outbound ACW calls/ agent	The maximum number of external outbound calls that an agent can make while in after-call work. This exception can only be triggered once per interval.
Time on external outbound AUX call	The maximum number of seconds an agent spends on an external outbound call during auxiliary work.
Number external outbound AUX calls/ agent	The maximum number of external outbound calls that an agent can make during auxiliary work. This exception can only be triggered once per interval.
Agent logged out with active/held calls	Select <b>Active</b> to be notified when an agent logs out with active or held calls on the voice terminal.
Logout attempt without valid reason code	The acceptable number of times that an agent can enter an invalid reason code when trying to log out. This exception can only be triggered once per interval.

Table continues...

Exception	Definition
AUX attempt without valid reason code	The acceptable number of times that an agent can enter an invalid AUX reason code. This exception can only be triggered once per interval.
Agent entered invalid call work code Agent entered invalid call work codes	An exception that is pegged for CWC 0 (an agent types an unadministered call work code). This exception should be turned off if you are collecting call work codes in call records only.

# About administering split or skill exceptions

Using split or skill exceptions can help identify those splits or skills that need to be adjusted to achieve more efficiency in the call center.

Split or skill exceptions can assist you in the identification of problems in the following areas:

- · The length of time that calls wait for different handling options
- The number of calls that are directed through different handling options
- The average speed with which the calls are being answered

## Before using split or skill exceptions

The following items should be read and understood before working with split or skill exceptions:

- To administer exceptions for skills, your company must have purchased Expert Agent Selection (EAS). However, this feature is not needed to administer exceptions for splits.
- The split or skill exceptions configuration is not created by default in the CMS database when the split or skill is created. You must add exceptions to a split or skill, if required.

## Permissions required to administer split or skill exceptions

Depending on the procedure that you want to perform, you need the following permissions:

- To view split or skill exceptions, the user ID used to log in to this Supervisor session requires "read" permission for the Exceptions subsystem and all affected splits or skills as well as the "exceptions" permission for all affected splits or skills.
- To add, delete, or modify split or skill exceptions, the user ID used to log in to this Supervisor session requires "write" permission for the Exceptions subsystem and all affected splits or skills as well as the "exceptions" permission for all affected splits or skills

# Administering split or skill exceptions using the Web Client

#### About this task

Use this procedure to add new exception types, modify options for existing exception types, and remove options for existing exception types.

#### Procedure

1. Navigate to Administration > Exceptions > Split/Skill Exceptions.

CMS Supervisor displays the Split/Skill Exceptions window for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer an exception.

CMS Supervisor displays the Split/Skill Exceptions window for the selected ACD.

3. In the **Split/Skill** field, enter the name or number of the split or skill for which an exception is to be created.

If the selected item has exceptions assigned, the system displays the exception assignments in the window. If exceptions are not assigned, the system displays a message that no exceptions were found.

- 4. **(Optional)** In the **Select additional splits/skills (optional)** field, enter the name or number of a split or skill to which you want to assign an exception. The field can accept multiple entries separated by semicolons (;) if you want to assign the same exceptions to several splits or skills. You can assign exceptions to as many as 32 splits or skills in one operation.
- 5. Use the plus and minus controls or click the split or skill names to move splits or skills between the Search Results and Selected Split(s)/Skill(s) panes. Repeat this step until the splits or skills to which you want to assign exceptions are in the Selected Split(s)/ Skill(s) pane.
- Administer the following options for each exception type you want to activate for the selected splits or skills. The exception types are described in <u>Split or skill exception</u> <u>definitions</u> on page 288.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.

- **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. Do one of the following operations:
  - Click Add when adding a new set of exceptions.
  - Click **Modify** when modifying settings for an existing set of exceptions.
  - Click **Remove** when you want to remove all administered exceptions.
  - Click **Clear** to clear any settings you have changed before doing an add, modify, or remove operation.

CMS Supervisor displays a confirmation message after doing an add, modify, or remove operation.

## Adding split or skill exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the split/skill to receive the new exception configuration.
- 3. In the **Operations** list, highlight **Split/Skill Exceptions**.
- 4. Click OK.

Supervisor displays the Split/Skill Exception Administration window.

- 5. In the **Split(s)/Skill(s)** field, enter the name or number of the split/skill for which an exceptions configuration is to be created.
- Administer the following options for each exception type you want to activate for the selected splits or skills. The exception types are described in <u>Split or skill exception</u> <u>definitions</u> on page 288.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.

- **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. When all necessary time limits and thresholds have been entered, select **Actions** > **Add** from the menu bar.

Supervisor saves the data for this split/skill and the status bar displays a Successful message.

## Modifying split or skill exceptions using the PC Client Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD**field, select the ACD that contains the split/skill and its exception configuration.
- 3. In the **Operations** list, highlight **Split/Skill Exceptions**.
- 4. Click OK.

Supervisor displays the Split/Skill Exception Administration window.

- 5. In the **Split(s)/Skill(s)** field, enter the name or number of the split/skill for which its exceptions configuration is to be modified.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor locates the exception configuration for the specified split/skill and the displays the data in the appropriate fields. If exception configuration data cannot be found, the status bar displays 0 matches found.

To have all splits/skills returned in this step, leave the **Split(s)/Skill(s)** field blank before performing the **Find one** action. Supervisor will return all split(s)/skill(s) for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the splits/skills.

- Administer the following options for each exception type you want to activate for the selected splits or skills. The exception types are described in <u>Split or skill exception</u> <u>definitions</u> on page 288.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this

activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.

- **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 8. When all necessary time limits and thresholds have been entered, select **Actions** > **Modify** from the menu bar.

Supervisor saves the data for this split/skill and the status bar displays a Successful message.

## Deleting split or skill exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the split/skill and its exception configuration.
- 3. In the **Operations** list, highlight **Split/Skill Exceptions**.
- 4. Click OK.

Supervisor displays the Split/Skill Exception Administration window.

- 5. In the **Split(s)/Skill(s)** field, enter the name or number of the split/skill for which the exception configuration is to be deleted.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor locates the exception configuration for the specified split/skill and the displays the data in the appropriate fields. If exception configuration data cannot be found, the status bar displays 0 matches found.

To have all splits/skills returned in this step, leave the **Split(s)/Skill(s)** field blank before performing the **Find one** action. Supervisor will return all split(s)/skill(s) for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the splits/skills.

7. From the menu bar, select **Actions > Delete**.

Supervisor deletes the exception configuration for this split/skill from the CMS database and a displays a Successful message in the status bar.

## Split or skill exception definitions

The following table provides the definitions for the different split/skill exceptions.

Field	Description
Time call has waited in queue	The total acceptable amount of time any call in queue remains unanswered before an occurrence is counted against the threshold limit.
Number calls waiting	The maximum number of calls waiting in queue at any one time.
Number calls abandoned	The total number of acceptable abandoned calls. This exception can only be triggered once per interval.
Average speed of answer (seconds)	The maximum acceptable amount of time in seconds that a call waits in that split/skill queue before an agent answers. This exception can only be triggered once per interval.
Number intraflowed-out calls	The maximum acceptable number of calls that intraflow out from or in to a split or skill. This exception can only be triggered once per interval.
Number intraflowed-in calls	The acceptable number of calls that can intraflow in to the split or skill before an occurrence is counted against the threshold limit. This exception can only be triggered once per interval.
Number interflowed-out calls	The acceptable number of calls that can interflow out of the split or skill. This exception can only be triggered once per interval.
Number calls handled as backup	The acceptable number of calls that this split or skill can handle as a backup for another split or skill. This exception can only be triggered once per interval.
Number calls transferred	The acceptable number of calls that can be transferred from this split or skill. This exception can only be triggered once per interval.
Number calls offered while queue full	The acceptable number of calls that can be offered to the split or skill while the queue is full. This exception can only be triggered once per interval.
Expected Wait Time (pri Top) exceeds threshold	The maximum acceptable time in seconds that a call is expected to wait at <b>TOP</b> priority before connecting to an agent. This exception can only be triggered once per interval.
Expected Wait Time (pri High) exceeds threshold	The maximum acceptable time in seconds that a call is expected to wait at <b>HIGH</b> priority before connecting to an agent. This exception can only be triggered once per interval.
Expected Wait Time (pri Medium) exceeds threshold	The maximum acceptable time in seconds that a call is expected to wait at <b>MED</b> priority before connecting to an agent. This exception can only be triggered once per interval.
Expected Wait Time (pri Low)	The maximum acceptable time in seconds that a call is expected to wait at <b>LOW</b> priority before connecting to an agent. This exception can only be triggered once per interval.

Table continues...

Field	Description
Rolling Average Speed of Answer (seconds)	The maximum acceptable amount of time in seconds that is calculated for the rolling average speed of answer (ASA) for a split/ skill. This exception can only be triggered once per interval. The ASA for the measured split/skill is sent to CMS by way of the ASA message. An occurrence is counted (in seconds) when CMS receives an ASA that exceeds the time limit that is specified for a split/skill. An exception is triggered when the threshold is exceeded.

## About administering trunk group exceptions

Trunk group exceptions are used to identify performance and capacity issues for the trunk groups in the call center.

## Before using trunk group exceptions

The following items should be read and understood before working with trunk group exceptions:

• An Audio Difficulty exception is associated with each trunk group. This exception is always provided for all Communication Manager systems that support event counts and it cannot be disabled. For this reason, this exception is not available on the Trunk Group Exception Administration window.

## Permissions required to administer trunk group exceptions

Depending on the procedure that you want to perform, you need the following permissions:

- To view trunk group exceptions, the user ID used to log in to this Supervisor session requires "read" permission for the Exceptions subsystem and all affected trunk groups as well as the "exceptions" permission for all affected trunk groups.
- To add, delete, or change trunk group exceptions, the user ID used to log in to this Supervisor session requires "write" permission for the Exceptions subsystem and all affected trunk groups as well as the "exceptions" permission for all affected trunk groups.

## Administering trunk group exceptions using the Web Client

#### About this task

Use this procedure to add new exception types, modify options for existing exception types, and remove options for existing exception types.

#### Procedure

1. Navigate to Administration > Exceptions > Trunk Group Exceptions.

CMS Supervisor displays the Trunk Group Exceptions window for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer an exception.

CMS Supervisor displays the Trunk Group Exceptions window for the selected ACD.

3. In the **Trunk Groups** field, enter the name or ID of the trunk group for which an exception is to be created.

If the selected item has exceptions assigned, the system displays the exception assignments in the window. If exceptions are not assigned, the system displays a message that no exceptions were found.

- 4. **(Optional)** In the **Select additional trunk groups (optional)** field, enter the name or ID of a trunk group to which you want to assign an exception. The field can accept multiple entries separated by semicolons (;) if you want to assign the same exceptions to several trunk groups. You can assign exceptions to as many as 32 trunk groups in one operation.
- 5. Use the plus and minus controls or click the trunk group name or ID to move trunk groups between the Search Results and Selected Trunk Group(s) panes. Repeat this step until the trunk groups to which you want to assign exceptions are in the Selected Trunk Group(s) pane.
- Administer the following options for each exception type you want to activate for the selected trunk groups. The exception types are described in <u>Trunk group exception</u> <u>definitions</u> on page 294.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. Do one of the following operations:
  - Click Add when adding a new set of exceptions.
  - Click **Modify** when modifying settings for an existing set of exceptions.

- Click **Remove** when you want to remove all administered exceptions.
- Click **Clear** to clear any settings you have changed before doing an add, modify, or remove operation.

CMS Supervisor displays a confirmation message after doing an add, modify, or remove operation.

## Adding trunk group exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD for the trunk group that will receive the new exceptions configuration.
- 3. In the **Operations** list, highlight **Trunk Group Exceptions**.
- 4. Click OK.

Supervisor displays the Trunk Group Exception Administration window.

- 5. In the **Trunk Groups** field, enter the name or number of the trunk group for which an exceptions configuration is to be created.
- Administer the following options for each exception type you want to activate for the selected trunk groups. The exception types are described in <u>Trunk group exception</u> <u>definitions</u> on page 294.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. When all necessary time limits and thresholds have been entered, select **Actions** > **Add** from the menu bar.

Supervisor saves the data for this trunk group and the status bar displays a Successful message.

## Modifying trunk group exceptions using the PC Client Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the trunk group and its exception configuration.
- 3. In the **Operations** list, highlight **Trunk Group Exceptions**.
- 4. Click OK.

Supervisor displays the Trunk Group Exception Administration window.

- 5. In the **Trunk Groups** field, enter the name or number of the trunk group for which exception configuration is to be modified.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor locates the exception configuration data for the specified trunk group and displays it in the appropriate fields. If data cannot be found for this trunk group, the status bar displays 0 matches found.

To return all trunk groups, leave the **Trunk Groups** field blank before performing the **Find one** action. Supervisor will return all trunk groups for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the trunk groups.

- Administer the following options for each exception type you want to activate for the selected trunk groups. The exception types are described in <u>Trunk group exception</u> <u>definitions</u> on page 294.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 8. When all necessary time limits and thresholds have been entered, select **Actions** > **Modify** from the menu bar.

Supervisor updates the data for this trunk group and the status bar displays a <code>Successful</code> message.

## Deleting trunk group exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the trunk group and its exception configuration.
- 3. In the **Operations** list, highlight **Trunk Group Exceptions**.
- 4. Click OK.

Supervisor displays the Trunk Group Exception Administration window.

- 5. In the **Trunk Groups** field, enter the name or number of the trunk group for which the exception configuration is to be deleted.
- 6. From the menu bar, select **Actions > Find one**.

The exception configuration is found for the specified trunk group and the data displays in the appropriate fields. If exception configuration data cannot be found, the status bar will display 0 matches found.

To return all trunk groups, leave the **VDNs** field blank before performing the **Find one** action. Supervisor will return all trunk groups for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the trunk groups.

7. From the menu bar, select **Actions > Delete**.

The exception configuration for this trunk group is deleted from the CMS database and a Successful message displays in the status bar.

## Trunk group exception definitions

The following table provides the definitions for the different trunk group exceptions:

Field	Description
Time trunk in use (min)	The minimum acceptable time in seconds that a trunk in the trunk group can be in use. This exception can only be triggered once per interval for the same trunk.
Time trunk in use (max)	The maximum acceptable time in seconds that a trunk in the trunk group can be in use. This exception can only be triggered once per interval for the same trunk.

Table continues...

Field	Description
Time any trunk maintenance busy	The maximum acceptable time in seconds that a trunk in the trunk group can be in the maintenance busy state.
Length of time all trunks busy	The maximum acceptable time that all trunks in the trunk group can be busy at once. This exception can only be triggered once per interval.
Number trunk failures in group	The maximum acceptable number of trunk failures that can occur in the trunk group. An exception is reached each time the allowed number of failures exceeds the threshold within the interval.
Number of trunks in use	The maximum acceptable number of trunks that can be in use at the same time in the trunk group. An exception is reached each time the allowed number of trunks in use exceeds the threshold within the interval.
Number of trunks maintenance busy	The maximum acceptable number of trunks that can be in the maintenance busy state in the trunk group. An exception is reached each time the allowed number of trunk that are in the maintenance busy state exceeds the threshold within the interval.
Number of failures on a single trunk	The maximum acceptable number of failures that can occur in a single trunk. An exception is reached each time the allowed number of failures exceeds the threshold within the interval.

## About administering VDN exceptions

Use Vector Directory Number (VDN) exceptions to assist in the identification of problems in the following areas:

- The amount of time calls that remain in the vector or at an agent
- The number of calls that reach specific states, such as disconnected, busy, and abandoned
- The number of calls that are routed in or out of the VDN and if they are successful

## **Before using VDN exceptions**

The following items should be read and understood before working with VDN exceptions:

- To administer VDN exceptions, your company must have purchased and installed the Call Vectoring feature.
- Because of the routing that is permitted by the go to vector command, the **Time in Vector** exception may include the time that a call spends in more than one vector.
- CMS begins to monitor for VDN exceptions when a call connects to the VDN and stops when the call is disconnected, sent to another VDN, sent to an external destination, or transferred. The call remains connected to the VDN if one of the following circumstances is encountered:
  - The call routes to another vector through a go to vector step.

- The call is sent through a route to or adjunct routing step to a non-VDN extension that is internal to the local Communication Manager system.
- If a large number of VDNs exist in the Dictionary (over 2000), there can be lengthy waiting periods when you browse for VDNs through Supervisor.
- Some exception types require that an appropriate step exists in the vector to which the VDN is assigned. For example, to get exceptions on unsuccessful **Lookahead Interflow Attempts**, the vector for the VDN must have at least one route to step that routes calls to a vector on a remote switch.

## Permissions required to administer VDN exceptions

Depending on the procedure that you want to perform, you need the following permissions:

- To view VDN exceptions, the user ID used to log in to this Supervisor session requires "read" permission for the Exceptions subsystem and all affected VDNs as well as the "exceptions" permission for all affected VDNs.
- To add, delete, or change VDN exceptions, the user ID used to log in to this Supervisor session requires "write" permission for the Exceptions subsystem and all affected VDNs as well as the "exceptions" permissions for all affected VDNs.

## Administering VDN exceptions using the Web Client

#### About this task

Use this procedure to add new exception types, modify options for existing exception types, and remove options for existing exception types.

#### Procedure

1. Navigate to Administration > Exceptions > VDN Exceptions.

CMS Supervisor displays the VDN Exceptions window for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer an exception.

CMS Supervisor displays the VDN Exceptions window for the selected ACD.

3. In the **VDNs** field, enter the name or ID of the VDN for which an exception is to be created.

If the selected item has exceptions assigned, the system displays the exception assignments in the window. If exceptions are not assigned, the system displays a message that no exceptions were found.

4. **(Optional)** In the **Select additional VDNs (optional)** field, enter the name or ID of a VDN to which you want to assign an exception. The field can accept multiple entries separated by semicolons (;) if you want to assign the same exceptions to several VDNs. You can assign exceptions to as many as 32 VDNs in one operation.

- Use the plus and minus controls or click the VDN name or ID to move VDNs between the Search Results and Selected VDN(s) panes. Repeat this step until the VDNs to which you want to assign exceptions are in the Selected VDN(s) pane.
- Administer the following options for each exception type you want to activate for the selected VDNs. The exception types are described in <u>VDN exception definitions</u> on page 300.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. Do one of the following operations:
  - Click Add when adding a new set of exceptions.
  - Click **Modify** when modifying settings for an existing set of exceptions.
  - Click **Remove** when you want to remove all administered exceptions.
  - Click **Clear** to clear any settings you have changed before doing an add, modify, or remove operation.

CMS Supervisor displays a confirmation message after doing an add, modify, or remove operation.

## Adding VDN exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the VDN that will receive the new exceptions configuration.
- 3. In the **Operations** list, highlight **VDN Exceptions**.
- 4. Click OK.

Supervisor displays the VDN Exception Administration window.

- 5. In the **VDNs** field, enter the name or number of the VDN for which the exceptions configuration is to be created.
- Administer the following options for each exception type you want to activate for the selected VDNs. The exception types are described in <u>VDN exception definitions</u> on page 300.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. When all necessary time limits and thresholds have been entered, select **Actions** > **Add** from the menu bar.

Supervisor saves the data for this VDN exception configuration and the status bar displays a Successful message.

## Modifying VDN exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the VDN and its exception configuration.
- 3. In the **Operations** list, highlight **VDNs**.
- 4. Click OK.

Supervisor displays the VDN Exception Administration window.

- 5. In the **VDNs** field, enter the name or number of the VDN for which exception configuration is to be modified.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor locates the exception configuration data for the specified VDN and displays it in the appropriate fields. If exception configuration data cannot be found for this VDN, the status bar displays 0 matches found.

To have all VDNs returned in this step, leave the **VDNs** field blank before performing the **Find one** action. Supervisor will return all VDNs for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the VDNs.

- Administer the following options for each exception type you want to activate for the selected VDNs. The exception types are described in <u>VDN exception definitions</u> on page 300.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 8. When all necessary time limits and thresholds have been entered, select **Actions** > **Modify** from the menu bar.

Supervisor updates the exception configuration data for this VDN and the status bar displays a Successful message.

## **Deleting VDN exceptions using the PC Client**

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the VDN and its exception configuration.
- 3. In the **Operations** list, highlight **VDN Exceptions**.
- 4. Click OK.

Supervisor displays the VDN Exception Administration window.

- 5. In the **VDNs** field, enter the name or number of the VDN for which the exception configuration is to be deleted.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor locates the exception configuration for the specified VDN and the data displays in the appropriate fields. If exception configuration data cannot be found, the status bar displays 0 matches found.

To have all VDNs returned through this step, leave the **VDNs** field blank. Supervisor displays the total number of matches in the status bar. The VDNs can then be navigated by using the **Next** and **Previous** actions.

7. From the menu bar, select **Actions** > **Delete**.

Supervisor deletes the exception configuration for this VDN from the CMS database and displays a Successful message in the status bar.

## **VDN** exception definitions

Name	Description
Time in vector (max)	The maximum acceptable time in seconds that a call should spend in vector processing. This exception can only be triggered once per interval.
Time at agent (min)	The minimum acceptable time in seconds that a call to this VDN is connected to an agent. This exception can only be triggered once per interval.
Time at agent (max)	The maximum acceptable time in seconds that a call to this VDN is connected to an agent. This exception can only be triggered once per interval.
Number calls abandoned while in vector	The maximum acceptable number of calls to this VDN that are abandoned before being answered during an interval. This exception can only be triggered once per interval.
Number calls forced busy	The maximum acceptable number of calls to this VDN that receive a busy signal from the switch during an interval. This exception can only be triggered once per interval.
Number calls disconnected	The maximum acceptable number of calls that are disconnected during vector processing during an interval. Disconnects can be caused by the disconnect vector command, by the vector disconnect timer, or because a call reached the end of vector processing without being queued. Calls that are disconnected after receiving a busy signal from the busy command are not included. This exception can only be triggered once per interval.
Number calls in ACD split queue	The maximum acceptable number of call to this VDN that are in a split/skill queue.

The following table provides the definitions for the different VDN exceptions:

Table continues...

Name	Description
Number calls that flowed into VDN	The maximum number of calls during an interval that enter this VDN by a route-to or adjunct routing link vector step, or a transfer from a local extension. This exception can only be triggered once per interval.
Number calls that flowed out of VDN	The maximum acceptable number of calls that are routed from this VDN during an interval to another VDN or external destination. This exception can only be triggered once per interval.
Number calls interflowed out of VDN	The maximum acceptable number of calls that are routed from this VDN to an external destination during an interval. This exception can only be triggered once per interval.
Number calls handled by backup split	The maximum acceptable number of calls to this VDN that are connected to a backup split/skill during an interval. A check backup split, check backup skill, messaging split, or messaging skill vector command causes a call to be handled by a backup split/skill. This exception cannot trigger more than once per interval.
Number unsuccessful look ahead interflow attempts	The maximum acceptable number of calls to this VDN that fail to interflow to another Communication Manager system during an interval. The route-to vector command causes a call to interflow. This exception can only be triggered once per interval.
Number unsuccessful adjunct routing attempts	The maximum acceptable number of failures of a call to this VDN to connect to an adjunct host computer during an interval. The failure of an adjunct route link vector command causes an unsuccessful adjunct routing attempt. The failure can occur because the connection to the adjunct is out of service or busy, or because the adjunct software rejects control. This exception can only be triggered once per interval.
Rolling Average Speed of Answer (seconds)	The acceptable amount of time, in seconds, that is calculated for the rolling average speed of answer for a VDN. This exception can only be triggered once per interval.

## About administering vector exceptions

When vector exceptions are configured and activated, CMS monitors for these exceptions when a call enters the vector and continues monitoring until the call connects to an agent, is abandoned, or is routed to another destination.

Vector exceptions can assist in the identification of problems in the following areas:

- The amount of time that a call waits in a vector
- The number of calls that are abandoned, disconnected, or forced busy while in the vector
- Numerous unsuccessful routing attempts

## Before using vector exceptions

The following items should be read and understood before working with vector exceptions:

- Calls may generate some exceptions for a vector, even after the vector has given routing control to the adjunct by an adjunct routing vector command.
- Some exception types require that an appropriate step exists in the vector. For example, to get exceptions on unsuccessful Look Ahead Interflow attempts, the vector must have at least one route to step which routes calls to a remote Communication Manager system.

## Permissions required to administer vector exceptions

Depending on the procedure that you want to perform, you need the following permissions:

- To view vector exceptions, the user ID used to log in to this Supervisor session requires "read" permission for the Exceptions subsystem and all affected vectors as well as the "exceptions" permission for the affected vectors.
- To add, delete, or change vector exceptions, the user ID used to log in to this Supervisor session requires "write" permission for the Exceptions subsystem and all affected vectors as well as the "exceptions" permission for the affected vectors.

## Administering vector exceptions using the Web Client

#### About this task

Use this procedure to add new exception types, modify options for existing exception types, and remove options for existing exception types.

#### Procedure

1. Navigate to Administration > Exceptions > Vector Exceptions.

CMS Supervisor displays the Vector Exceptions window for the current ACD.

2. In the **Current ACD** drop-down list, select the active ACD for which you want to administer an exception.

CMS Supervisor displays the Vector Exceptions window for the selected ACD.

3. In the **Vectors** field, enter the name or ID of the vector for which an exception is to be created.

If the selected item has exceptions assigned, the system displays the exception assignments in the window. If exceptions are not assigned, the system displays a message that no exceptions were found.

4. **(Optional)** In the **Select additional vectors (optional)** field, enter the name or ID of a vector to which you want to assign an exception. The field can accept multiple entries

separated by semicolons (;) if you want to assign the same exceptions to several vectors. You can assign exceptions to as many as 32 vectors in one operation.

- 5. Use the plus and minus controls or click the vector name or ID to move vectors between the Search Results and Selected Vector(s) panes. Repeat this step until the vectors to which you want to assign exceptions are in the Selected Vector(s) pane.
- Administer the following options for each exception type you want to activate for the selected vectors. The exception types are described in <u>Vector exception definitions</u> on page 306.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. Do one of the following operations:
  - Click Add when adding a new set of exceptions.
  - Click **Modify** when modifying settings for an existing set of exceptions.
  - Click **Remove** when you want to remove all administered exceptions.
  - Click **Clear** to clear any settings you have changed before doing an add, modify, or remove operation.

CMS Supervisor displays a confirmation message after doing an add, modify, or remove operation.

## Adding vector exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the vector that will receive the new exceptions configuration.
- 3. In the **Operations** list, highlight **Vector Exceptions**.

4. Click OK.

Supervisor displays the Vector Exceptions Administration window.

- 5. In the **Vectors** field, enter the name or number of the vector for which an exceptions configuration is to be created.
- Administer the following options for each exception type you want to activate for the selected vectors. The exception types are described in <u>Vector exception definitions</u> on page 306.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 7. When all necessary time limits and thresholds have been entered, select **Actions** > **Add** from the menu bar.

Supervisor saves the data for this vector exception configuration and the displays a <code>Successful</code> message in the status bar.

## Modifying vector exceptions using the PC Client

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the vector and its exception configuration.
- 3. In the **Operations** list, highlight **Vector Exceptions**.
- 4. Click OK.

Supervisor displays the Vector Exceptions Administration window.

- 5. In the **Vectors** field, enter the name or number of the vector for which the exception configuration is to be modified.
- 6. From the menu bar, select **Actions** > **Find one**.

Supervisor locates the agent exception configuration for the specified split/skill and displays the data in the appropriate fields. If the exception configuration data cannot be found, the status bar displays 0 matches found.

To have all vectors returned when performing this step, leave the **Vectors** field blank before performing the **Find one** action. Supervisor will return all vectors for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the vectors.

- Administer the following options for each exception type you want to activate for the selected vectors. The exception types are described in <u>Vector exception definitions</u> on page 306.
  - Active Select this check box to enable the exception and allow it to run and adhere to the parameters that are given in the other options. Leaving this check box blank disables the exception and CMS will not attempt to track the activity for this exception, but the time limits and thresholds you have entered are saved for later activation. All exception types use this option.
  - **Time Limit** Enter the time limit in seconds (0 to 28800) for those exception types that use a time limit. This value is used as the minimum or maximum amount of time for an activity depending on the type of exception. If this limit is surpassed, CMS counts this activity and compares it against the **Threshold** field. This option requires an entry and cannot be left blank.
  - **Threshold** Enter the number of acceptable occurrences of this activity (0 to 999) for those exception types that use a threshold. Any occurrences beyond this number will generate an exception. If you want CMS to create an exception on the very first instance, enter 0 in this field. This field requires an entry and cannot be left blank.
- 8. When all necessary time limits and thresholds have been entered, select **Actions** > **Modify** from the menu bar.

Supervisor updates the exception configuration data for this vector and the status bar displays a <code>Successful</code> message.

## **Deleting vector exceptions using the PC Client**

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. In the **ACD** field, select the ACD that contains the vector and its exception configuration.
- 3. In the **Operations** list, highlight **Vector Exceptions**.
- 4. Click **OK**.

Supervisor displays the Vector Exceptions Administration window.

- 5. In the **Vectors** field, enter the name or number of the vector for which the exception configuration is to be deleted.
- 6. From the menu bar, select **Actions > Find one**.

Supervisor locates the agent exception configuration for the specified split/skill and displays the data in the appropriate fields. If the exception configuration data cannot be found, the status bar displays 0 matches found.

To have all vectors returned in this step, leave **Vectors** field blank before performing the **Find one** action. Supervisor will return all vectors for which you have the "read" permission. You can then use the **Next** and **Previous** menu actions to cycle through the vectors.

7. From the menu bar, select **Actions > Delete**.

Supervisor deletes the exception configuration for this vector from the database and displays a Successful message in the status bar.

## **Vector exception definitions**

Name	Description
Time in vector (max)	The maximum acceptable time in seconds that a call is in vector processing. This exception cannot trigger more than once per interval.
Number calls abandoned while in vector	The maximum acceptable number of calls that are abandoned during vector processing in an interval. This exception cannot trigger more than once within an interval.
Number calls forced busy	The maximum acceptable number of calls that encountered a forced busy step in a vector during an interval. This exception cannot trigger more than once per interval.
Number calls disconnected	The maximum acceptable number of calls that are disconnected during vector processing during an interval. Disconnects can be caused by the disconnect vector command, by the vector disconnect timer, or because a call reached the end of vector processing without being queued. This exception cannot be triggered more than once per interval.
Number calls in ACD split queue	The maximum acceptable number of calls to this vector that are in a split/skill queue.
Number unsuccessful look ahead interflow attempts	The maximum acceptable number of calls to this vector that fail to interflow to another Communication Manager system during an interval. The route-to vector command causes a call to interflow. This exception cannot trigger more than once per interval.

The following table provides the definitions for the different vector exceptions:

Table continues...

Name	Description
Number unsuccessful adjunct routing attempts	The maximum acceptable number of failures for a call in this vector to connect to an adjunct host computer during an interval. The failure of an adjunct route link vector command causes an unsuccessful adjunct routing attempt. This exception cannot trigger more than one exception per interval.

Supervisor sends the malicious call trace report to the specified output method.

## About the real-time exceptions log

The real-time exception log lists the last ten exceptions that have occurred on the system. The log displays all types of exceptions for which the user has the "exception" permission, such as agent, split, skill, trunk group, VDN, or vector.

## Before using the real-time exceptions log

When the log is first viewed, the oldest exception is shown first. As long as the window remains open, the log automatically scrolls to display each new exception record. If the scroll bar is used to view the older records at the top of the log, automatic scrolling for new exceptions stops until the user scrolls back to the bottom of the log.

Each exception record in the log supplies the following information:

- The date and time that the exception occurred
- The name of the ACD for which the exception occurred
- The ACD element, such as a specific agent, split/skill, or VDN that was involved in the exception.

If names for these elements were assigned in the Dictionary, these will display instead. If the names are longer than the space that is allowed in the exception record, the names will be truncated.

For a peg count exception, the exception record shows the occurrence threshold that you set, even though the number of occurrences may be substantially greater. For a timed exception, the exception record shows the time limit that you set, not the actual duration of an occurrence.

The real-time exception log can hold a maximum of 100 records. If a new exception occurs when the log is full, the oldest exception is deleted so that the new exception can be recorded.

## Viewing the real-time exceptions log using the Web Client Procedure

Navigate to Administration > Exceptions > Real-Time Exception Log.

CMS Supervisor displays the list of the ten most recent exceptions that have occurred on the system.

## Viewing the real-time exceptions log using the PC Client Procedure

- From the Controller window, select Commands > Exceptions on the menu bar. CMS Supervisor displays the Exceptions window.
- 2. In the **ACD** field, select the ACD for which exceptions will be shown.
- 3. In the Operations list, highlight Real-Time Exception Log.
- 4. Click OK.

Supervisor displays the Real-time Exception Log window.

## **Chapter 9: Administering tenant features**

## About the CMS Tenancy feature

The CMS Tenancy feature provides an extension to the current CMS user data access management feature to enable customers to restrict user access to CMS reporting data and functionality within their call center. The new tenant level access for users introduces restricted data access permissions for the following call center resources: agents, call work codes, split/ skills, trunk groups, VDNs, and vectors.

Each tenant partition is assigned call center resources which are isolated from resources in the other tenant partitions. A tenant partition can be assigned a subset of call center resources, but not all call center resources must be assigned to a tenant partition. Some call center resources can be assigned across all tenants.

A user with tenant level access has permissions to access only those CMS resources which are assigned to the tenant partition. A user can be assigned permission to access more than one tenant.

Customers must install the Tenancy feature package to use the CMS Tenancy feature. Using this feature, customers can partition a subset of the ACD resources and assign the resources to tenants. A tenant or tenant partition enforces restricted access for CMS Supervisor users. Within a tenant, each tenant user can have access to a restricted set of call center resources and data based on their tenant assignments with that tenant.

The CMS tenancy feature and the Communication Manager Tenancy feature are unrelated. All the administrative and tenant user actions for CMS Tenancy are carried out independent of Communication Manager Tenancy. However, you must perform careful Communication Manager administration to achieve effective CMS tenant partitioning and tenant reporting.

Communication Manager tenant partitioning is administered on the Communication Manager system and CMS tenant partitioning administration does not modify or impact Communication Manager tenant partitioning administration. Tenant feature administration on CMS assigns resources such as agents, VDNs, and skills to a CMS tenant and defines how CMS tenant users can access call data that is stored in the CMS database.

CMS does not control the actual call operation or call delivery to agents and skills. Only Communication Manager administration controls how calls are handled and delivered to agents. Therefore, Communication Manager administration impacts data in CMS tenant reports, despite the restrictions imposed by CMS tenant administration.

For example, the administrator could create CMS tenant 1 and assign agent 1 and skill 1 to CMS tenant 1, and create CMS tenant 2 and assign agent 2 and skill 2 to CMS tenant 2. If agent 1 logs into skill 2 and receives calls for skill 2, the tenant 1 users will see the skill 2 call data in reports run for agent 1.

Thus, while the tenant user is restricted to running reports only for agents assigned to tenant 1, CMS will display all the call data for agent 1. This implies that the tenant user will see call data for skills assigned to a different tenant. CMS must display all the data for an agent or the summary data will be incomplete.

Therefore, you must plan tenant administration on both Communication Manager and CMS very carefully prior to any implementation of tenancy.

The resources shared between tenants must be mutually exclusive. Thus, customers cannot assign the same call center resource to different tenants. This means that different tenants on an ACD cannot share an agent, call work code, split/skill, trunk group, VDN, and vector.

There are three types of users:

- Administrator: An administrator is a user who has access to all the functions of CMS, all CMS reports, and all CMS data. Administrators can provide admin level access, normal user access, or tenant level access to other users. Administrators have the added capability to create and administer tenant users.
- Normal user: A normal user has functionality similar to the earlier releases of CMS. A normal user is given read, write, and exception permissions by the administrator for ACDs, splits/ skills, trunk groups, VDNs, and vectors.
- Tenant user: This user has tenant level access which can span multiple tenant partitions. This user has permissions for viewing or working with CMS resources within the tenant partitions to which the user is assigned.

😵 Note:

A tenant user is also assigned permission to access the split/skills, trunk groups, VDNs, and vectors within the tenant partition. Thus, additional restrictions within a tenant can be assigned to each individual tenant user.

Note:

A tenant user can create custom reports or can design reports which are accessible only to the tenant user.

#### Examples of Tenancy usage

- Service Providers can use Tenancy to partition their ACDs so that CMS can be used by multiple tenants or customers within the same ACD, but without access to each other's data.
- A call center with multiple departments or business units that have separate independent functions can create tenants to allocate each business unit a different set of tenant partitions.
- Customers that have a hierarchical reporting structure can use tenancy to enable supervisors and report users to manage only a subset of the call center resources.

## **Tenant user access restrictions**

Review the following user access restrictions before you administer tenant features:

• Special Agent/Agent Group restriction: Tenant users can only access agents and tenant specific agent groups pertaining to the tenant for which the user has permissions.

- Special Call Work Code (CWC) restriction: Tenant users can only access the CWCs pertaining to the tenant for which the user has permissions.
- Reports restriction: The report data is restricted to show only data for ACDs for which the tenant user has permissions.
- Dictionary restriction: Dictionary menu items and screens corresponding to Agent Groups and ACD Groups are not accessible by tenant users since tenant users are only allowed to access permissible tenant partitions of a single ACD.
- Call Center Administration restriction: Tenant users cannot access Call Center Administration for vector contents. Tenant user access to Call Center Administration for ACD Groups is filtered based on the permissions assigned.
- Tenant Administration restriction: Even if a tenant user is granted write permission for the Tenant feature, the tenant user is not allowed to write actions such as add and delete for the tenant assignments.
- User Permissions restriction: Tenant users cannot have write permissions to the User Permissions feature. Tenant users cannot view permission information for other users. Tenant users can only see permission information for themselves.

For tenant users, administrators must use the **Tenant Access Permissions** menu instead of the **User Permissions** menu.

The Tenant Access Permissions window provides the tenant user with the following administrative functions:

- Access Permissions Tenant Access: This screen provides access to options for the tenant user for determining the tenant access permissions assigned to the user.
- Access Permissions Tenant Vector Access: This screen provides access to options for the tenant user for determining the vector access permissions assigned to the user.
- Access Permissions Tenant ACD Access: This screen provides access to options for the tenant user for determining the ACD access permissions assigned to the user.
- Access Permissions Tenant Trunk Group Access: This screen provides access to options for the tenant user for determining the trunk group access permissions assigned to the user.
- Access Permissions Tenant VDN Access: This screen provides access to options for the tenant user for determining the VDN access permissions assigned to the user.
- Access Permissions Tenant Split/Skill Access: This screen provides access to options for the tenant user for determining the split/skill access permissions assigned to the user.
- Access Permissions Tenant User Data: This screen provides the user data information about the tenant user.
- Access Permissions Tenant Feature Access: This screen provides the feature access information about the tenant user.
- Access Permissions Tenant Main Menu Addition Access: This screen provides the main menu addition access information about the tenant user.

## Administering tenant features using the PC Client

## About administering tenant features

Using the PC Client, use the **Tenant Administration** item in the **Commands** menu or the toolbar button of CMS Supervisor to administer tenants in the call center. If you do not install the Tenancy feature, the **Tenant Administration** item and the toolbar button do not display in CMS Supervisor.

## Administering tenant features

#### About this task

This procedure provides a high level step-by-step description of administering tenant features, including the use of the **cmssvc** command, the **cmsadm** command, and the CMS Supervisor administrative interface.

#### Procedure

1. Authorize the Tenancy feature using **cmssvc** and install the tenancy feature on the CMS server using the **cmsadm** administrative tool.

#### Note:

The customer can perform this step.

- 2. Log in to the CMS server using CMS Supervisor as a user with administrative permissions and no tenant access restrictions.
- 3. Add a tenant to an ACD by going to **Commands** > **Dictionary** and selecting the desired ACD from the list box.
- 4. Open the Tenants screen to add the tenant number.
- 5. From Tenant Administration, add associated entities like Agent, Split/Skill, VDN, Trunk, or CWC to a tenant.

For example, to assign an Agent "agent1" to the tenant "Tenant 1" in ACD "acd1", use **Tenant Administration > Assignments > Agent**.

- 6. Add a tenant user by going to User Permissions > User Data and selecting Tenant user.
  - 😵 Note:

Upon the creation of a userid, the userid will automatically have read/write permissions for the specified Login ACD on the CMS server. You do not need to use **User Permissions > ACD Access** unless the access permissions of the tenant user need to change.

- 7. Provide the tenant user access to Tenants by using **User Permissions > Tenant Access**.
- 8. Give the tenant user access to the entities assigned to the tenant.

For example, to assign a Split/Skill belonging to the tenant to a tenant user, use **User Permissions > Split/Skill Access**.

#### 😵 Note:

Permissions for agents and call work codes are inferred from the tenant assignments and cannot be assigned using **User Permissions**.

#### 😵 Note:

The tenant user can be restricted further for accessing data within a tenant. These restrictions are imposed by the second level of permissions assigned by the administrator for agents, skills, VDNs, vectors, and trunk groups as in earlier CMS releases.

## PC Client tenant administration sub-menus

Using the PC Client, you can click **Commands** > **Tenant Administration** to navigate to the Tenant Admin sub menu window. The **Operations** tab in the Tenant Admin sub menu window include the following menu items:

- Tenant Agent Assignment
- Tenant Agent Groups
- Tenant Call Work Code Assignment
- Tenant Split/Skill Assignment
- Tenant Trunk Group Assignment
- Tenant VDN Assignment
- Tenant Vector Assignment

#### 😵 Note:

Tenant login IDs have read access only to Tenant Agent, VDN, Vector, Trunk Group, CWC, and Split/skill assignments. Tenant users have read/write access to Tenant Agent Groups.

#### Note:

You can use synonyms in the fields of all the tenant assignment screens.

#### **Tenant Agent Assignment administrative operations**

#### Important:

- A tenant number has to be between 1 and 250.
- Agents can have up to 16 digits based on Communication Manager releases.

The PC Client Tenant Admin Agent Assignment window consists of an action list which is described in the following table:

Field	Description
Add	Adds the entry for a tenant and the associated agent in the current user window to the database. If an entry already exists, the system displays Already exists on the window status line. The user must have write permission for the Tenant feature and write permission for the tenant number.
Delete	Removes the agent belonging to the tenant entry in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the Tenant feature and write permission for the tenant number. When agents are removed from a tenant, the agents will also be automatically removed from agent groups pertaining to the tenant.
Find one	Finds an entry in the database that matches the tenant and agent fields. The status line for the current window indicates the total number of matches found. The user must have read permission for the Tenant feature and read permission for the tenant number.
List all	Lists all tenant and agent entries in the database that match with the values entered in the fields of the current user window. The user must have read permission for the Tenant feature and read permission for the tenant number.
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.

## **Tenant Agent Groups administrative operations**

Use the Tenant Admin Agent Groups Assignment window to build tenant specific agent groups. The tenant specific agent groups created using this window are different from the agent groups built using **Dictionary > Agent Groups**. The agent groups created using **Dictionary > Agent Groups** can contain any agents from the ACDs. The Tenant specific agent groups are limited to agents within a specific tenant partition. Tenant users can only access tenant agent groups pertaining to permissible tenants. Tenant users are not allowed to use the non-tenant specific agent groups.

#### Important:

- A tenant number has to be between 1 and 250.
- An agent group name must begin with an alphabetic character and can be up to 20 characters long.

The PC Client Tenant Admin Agent Groups Assignment window consists of an action list which is described in the following table:

Field	Description
Add	Adds the entry for a tenant and the associated agent group in the current user window to the database. If an entry already exists, the system displays Already exists on the window status line. The user must have write permission for the Tenant feature and write permission for the tenant number.
Delete	Removes the agent group belonging to the tenant entry in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the Tenant feature and write permission for the tenant number.
Find one	Finds an entry in the database that matches the tenant and agent group fields. The status line for the current window indicates the total number of matches found. The user must have read permission for the Tenant feature and read permission for the tenant number.
List all	Lists all tenant and agent group entries in the database that match with the values entered in the fields of the current user window. The user must have read permission for the Tenant feature and read permission for the tenant number.
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.
Сору	Copies the contents of the specified tenant agent group to the new agent group. If an entry already exists, the system displays Already exists on the window status line. Use the Tenant Admin Agent Groups Assignment window to enter the agent group to copy from. The user must have write permission for the Tenant feature and write permission for the tenant number.
Get contents	Use this option to manipulate the contents of the agent group. Use the login ID field in this window to add, delete, or list agents for the tenant specific agent group.

## Tenant Call Work Code Assignment administrative operations

#### Important:

- A tenant number has to be between 1 and 250.
- Each Call Work Code (CWC) can have up to 16 digits.

The PC Client Tenant Admin Call Work Code Assignment window consists of an action list which is described in the following table:

Field	Description
Add	Adds the entry for a tenant and the associated CWC in the current user window to the database. If an entry already exists, the system displays Already exists on the window status line. The user must have write permission for the Tenant feature and write permission for the tenant number.
Delete	Removes the CWC belonging to the tenant entry in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the Tenant feature and write permission for the tenant number.
Find one	Finds an entry in the database that matches the tenant and CWC fields. The status line for the current window indicates the total number of matches found. The user must have read permission for the Tenant feature and read permission for the tenant number.
List all	Lists all tenant and CWC entries in the database that match with the values entered in the fields of the current user window. The user must have read permission for the Tenant feature and read permission for the tenant number.
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.

#### Tenant split/skill assignment

#### Important:

- A tenant number has to be between 1 and 250.
- Split/Skills numbers are between 1 and up to 8000 depending on Communication Manager releases.

The Tenant Admin Split/Skill Assignment window consists of an action list which is described in the following table:

Field	Description
Add	Adds the entry for a tenant and the associated split/skill in the current user window to the database. If an entry already exists, the system displays Already exists on the window status line. The user must have write permission for the Tenant feature and write permission for the tenant number.
Delete	Removes the split/skill belonging to the tenant entry in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the Tenant feature and write permission for the tenant number.

Table continues...

Field	Description	
Find one	Finds an entry in the database that matches the tenant and split/skill fields. The status line for the current window indicates the total number of matches found. The user must have read permission for the Tenant feature and read permission for the tenant number.	
List all	Lists all tenant and split/skill entries in the database that match with the values entered in the fields of the current user window. The user must have read permission for the Tenant feature and read permission for the tenant number.	
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.	
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.	

## Tenant Trunk Group Assignment administrative operations

#### Important:

- A tenant number has to be between 1 and 250.
- Trunk Group numbers are between 1 and up to 2000 depending on Communication Manager releases.

The PC Client Tenant Admin Trunk Group Assignment window consists of an action list which is described in the following table:

Field	Description	
Add	Adds the entry for a tenant and the associated trunk group in the current user window to the database. If an entry already exists, the system displays Already exists on the window status line. The user must have write permission for the Tenant feature and write permission for the tenant number.	
Delete	Removes the trunk group belonging to the tenant entry in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the Tenant feature and write permission for the tenant number.	
Find one	Finds an entry in the database that matches the tenant and trunk group fields. The status line for the current window indicates the total number of matches found. The user must have read permission for the Tenant feature and read permission for the tenant number.	
List all	Lists all tenant and trunk group entries in the database that match with the values entered in the fields of the current user window. The user must have read permission for the Tenant feature and read permission for the tenant number.	
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.	

Table continues...

Field	Description	
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.	

## **Tenant VDN Assignment administrative operations**

#### Important:

- A tenant number has to be between 1 and 250.
- VDNs can have up to 16 digits based on Communication Manager releases.

The PC Client Tenant Admin VDN Assignment window consists of an action list which is described in the following table:

Field	Description	
Add	Adds the entry for a tenant and the associated VDN in the current user window to the database. If an entry already exists, the system displays Already exists on the window status line. The user must have write permission for the Tenant feature and write permission for the tenant number.	
Delete	Removes the VDN belonging to the tenant entry in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the Tenant feature and write permission for the tenant number.	
Find one	Finds an entry in the database that matches the tenant and VDN fields. The status line for the current window indicates the total number of matches found. The user must have read permission for the Tenant feature and read permission for the tenant number.	
List all	Lists all tenant and VDN entries in the database that match with the values entered in the fields of the current user window. The user must have read permission for the Tenant feature and read permission for the tenant number.	
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.	
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.	

## **Tenant Vector Assignment administrative operations**

#### Important:

- A tenant number must be between 1 and 250.
- Vector numbers are between 1 and 8000.

The PC Client Tenant Admin Vector Assignment window consists of an action list which is described in the following table:

Field	Description	
Add	Adds the entry for a tenant and the associated vector in the current user window to the database. If an entry already exists, the system displays Already exists on the window status line. The user must have write permission for the Tenant feature and write permission for the tenant number.	
Delete	Removes the vector belonging to the tenant entry in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line. The user must have write permission for the Tenant feature and write permission for the tenant number.	
Find one	Finds an entry in the database that matches the tenant and vector fields. The status line for the current window indicates the total number of matches found. The user must have read permission for the Tenant feature and read permission for the tenant number	
List all	Lists all tenant and vector entries in the database that match with the values entered in the fields of the current user window. The user must have read permission for the Tenant feature and read permission for the tenant number.	
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.	
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.	

# Chapter 10: Configuring CMS system settings

## About administering system settings

This section provides procedures on viewing and changing the setup of CMS that was configured during the initial installation. These configuration values are used in adjusting the state of the system and the collection, storage, and retrieval of data. Making changes to these configuration settings can affect system performance, disk space usage, and data collection.

#### 😒 Note:

When using the PC Client, if an ACD Group is selected as the current ACD in the System Setup window, only those operations that are valid for the ACD Group will appear in the **Operations** list.

## Before configuring CMS system settings

If an ACD Group is selected as the current ACD in the System Setup window, only those operations that are valid for the ACD Group will appear in the **Operations** list.

## About viewing Switch Setup data

Use Switch Setup to view the following information:

- Communication Manager system information: ACD number and name, release, and activated features, such as Call Vectoring, Call Prompting, and Expert Agent Selection (EAS)
- · CMS software information release, version, and load

😵 Note:

In the Web Client, this information is found under **Help > About**.

· Phantom abandon call timer values

## **Before using Switch Setup**

The following items should be read and understood before working with Switch Setup:

- Switch Setup only displays real ACDs. Pseudo-ACDs are not displayed.
- Switch Setup is only used to view information. You cannot make modifications to the ACD using Switch Setup.
- The phantom abandon call timer is used to determine which calls to count as abandoned calls rather than ACD calls. If the call lasts less than the number of seconds specified, the Communication Manager system considers it an abandoned call. The feature is useful in areas where the central office or mobile network does not provide disconnect supervision on trunks.
- To display an ACD name in Switch Setup, the ACD must first have its name assigned in the Dictionary. See <u>About administering ACD names in the Dictionary</u> on page 45 for more information on this procedure.

## Permissions required to use Switch Setup

Depending on the procedure that you want to perform, you need the following permissions:

• To view ACDs in Switch Setup, the user must have "read" permission for the feature.

## Viewing Switch Setup data using the Web Client

#### Procedure

Navigate to Administration > System Setup > Switch Setup.

CMS Supervisor displays all ACDs and their associated settings.

## Viewing Switch Setup data using the PC Client

#### Procedure

- From the Controller window, select Tools > System Setup.
   CMS Supervisor displays the System Setup window.
- 2. In the **Operations** list, highlight **Switch Setup**.
- 3. Click OK.

CMS Supervisor displays the Switch Setup window.

4. In the ACD field, enter the name or number of the ACD to display.

To have all ACDs returned from the query so that you can cycle through them in this dialog, leave this field blank and proceed to the next step.

5. From the menu bar, select **Actions > Find one**.

CMS Supervisor displays the setup information for the specified ACD. If more than one match was found, use the **Next** and **Previous** items found under the **Actions** menu to cycle through them.

## Listing all Switch Setup data using the PC Client

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Switch Setup**.
- 3. Click OK.

CMS Supervisor displays the Switch Setup window.

4. From the menu bar, select **Actions > List all**.

CMS Supervisor displays a secondary window listing all ACDs and their associated settings.

## About administering pseudo-ACDs

A pseudo-ACD is an area created on the CMS server to store previously backed-up ACD data. A pseudo-ACD is not a real ACD and does not communicate with any Communication Manager system.

Pseudo-ACDs are used to store data which can then be viewed in reports. This could be useful in the following scenarios:

- Storing data from an off-site call center for the purposes of reporting in conjunction with an on-site CMS .
- Storing data for archival purposes. This data can no longer be deleted by the Data Storage Allocation feature and can be used to generate reports on older data for comparison with more recent ACD data.

## Before administering pseudo-ACDs

The following items should be read and understood before working with pseudo-ACDs:

- Each pseudo-ACD is given a number from 9 through 26. Numbers 1 through 8 are reserved for eight real ACDs connected to the CMS server.
- In order to load the pseudo-ACD data, the CMS server must have enough free space available. Use Free Space Allocation to see how much space is required for the existing ACDs and how much is available for the pseudo-ACD data.
- Use Data Storage Allocation to define how much historical data will be stored for the pseudo-ACD. Enter storage values equal to or greater than those used from the ACD which originally held the data.
- Use Storage Intervals to set storage intervals for the pseudo-ACD data to match the interval size and data collection times of the ACD from which the data was taken.
- The Data Collection feature can be running when modifications are made in Data Storage Allocation or Storage Intervals for a pseudo-ACD, but CMS must be in single-user mode.
- If the pseudo-ACD has the separately purchased Forecast feature on it, Forecast Data Storage Allocation parameters can require changes in order to match those of the pseudo-ACD. This is not the same as the Data Storage Allocation normally used in CMS.
- In order for users to access the pseudo-ACD, permissions must be granted using ACD Access in User Permissions.
- Creation of a pseudo-ACD using CMS Supervisor while users are logged in requires that the users log out and back in before they can see the new pseudo-ACD.
- Before deleting a pseudo-ACD, turn off permissions to it so that users will not be working in the pseudo-ACD when it is deleted.
- · CMS does not automatically summarize pseudo-ACD data.
- The following menu items are applicable to a pseudo-ACD:

Reports	CMS System Setup	Maintenance
Historical	Data Storage Allocation	Archiving Status
Dictionary — all submenu	Data Summarizing	Backup/Restore Devices
items	Free Space Allocation	Printer Administration
Forecast — all submenu items	Load Pseudo-ACD	
Custom Reports — all submenu items	Pseudo-ACD Setup	
<b>User Permissions</b> — all submenu items		

## Permissions required to administer pseudo-ACDs

Depending on the procedure that you want to perform, you need the following permissions:

- To view the Pseudo-ACD Setup window, you must have "read" permission for the CMS System Setup feature.
- To add or delete pseudo-ACDs, you must have "write" permission for the CMS System Setup feature.

## Viewing pseudo-ACDs using the Web Client Procedure

Navigate to **System Setup > Pseudo-ACD Setup**.

CMS Supervisor displays the list of administered pseudo-ACDs.

## Adding pseudo-ACDs using the Web Client

#### Procedure

1. Navigate to System Setup > Pseudo-ACD Setup.

CMS Supervisor displays the list of administered pseudo-ACDs.

2. Click Add Pseudo-ACD Setup.

CMS Supervisor displays the Add Pseudo-ACD Setup window.

- 3. In the **ACD Number** field, enter an unused number from 9 to 26 to correspond with the new pseudo-ACD.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

## **Deleting pseudo-ACDs using the Web Client**

#### Procedure

1. Navigate to **System Setup > Pseudo-ACD Setup**.

CMS Supervisor displays the list of administered pseudo-ACDs.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

3. Click **Yes** to continue with the change. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

4. Click OK.

CMS Supervisor displays an updated list of items.

## Viewing pseudo-ACDs using the PC Client

#### Procedure

1. From the Controller window, select **Tools** > **System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Pseudo-ACD Setup**.
- 3. Click OK.

CMS Supervisor displays the Pseudo-ACD Setup window.

4. From the menu bar, select **Actions > List all**.

CMS Supervisor displays a secondary window listing all ACDs. The status bar displays the total number of pseudo-ACDs on the CMS server. Only those ACDs for which you have "read" permission are displayed.

## Adding a pseudo-ACD using the PC Client

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Pseudo-ACD Setup**.
- 3. Click OK.

Supervisor displays the Pseudo-ACD Setup window.

- 4. In the **ACD** field, enter the number or the name of the pseudo-ACD. The number can range from 9 to 26. This field requires a number to be entered if a name for this pseudo-ACD has not been defined in the Dictionary.
- 5. From the menu bar, select **Actions > Add**.

CMS creates the pseudo-ACD.

- 6. Log out of Supervisor and log in again to acquire permission to the newly created pseudo-ACD.
- 7. From the Controller window, select **Tools > System Setup**.

Supervisor displays the CMS System Setup window.

8. In the **Operations** list, highlight **CMS State**.

Supervisor displays the CMS State window.

- 9. Select option **Single-user mode**.
- 10. From the menu bar, select Actions > Modify.
- 11. Close the CMS State window.
- 12. Turn off data collection as described in <u>Turning data collection on and off using the PC</u> <u>Client</u> on page 358.
- 13. In the **Operations** list, highlight **Data Storage Allocation**.
- 14. In the **ACD** list, highlight the appropriate pseudo-acd.
- 15. Select OK.

Supervisor displays the Data Storage Allocation window.

- 16. Enter storage values equal to or greater than the values used for the ACD which originally stored the data.
- 17. From the menu bar, select **Actions > Modify**.

Supervisor displays the following message:

You may have increased or decreased the amount of storage. Do you want to continue?

- 18. Select YES.
- 19. Close the Data Storage Allocation window.
- 20. In the Operations list, highlight Storage Intervals.
- 21. In the **ACD** list, highlight the appropriate pseudo-acd.
- 22. Select OK.

Supervisor displays the Storage Intervals window.

- 23. Enter storage values equal to the values used for the ACD which originally stored the data.
- 24. From the menu bar, select **Actions > Modify**.

Supervisor displays a message if changes are made to the Intrahour interval.

For example, if you change a 30 minute Intrahour interval to a 15 minute Intrahour interval, the system displays the following:

```
Data will be migrated to the new interval. The data will be divided by 2. Do you want to continue?
```

- If you want to continue with these settings, select **YES**.
- If you do not want to continue with these settings, select **NO**. Change any incorrect fields until the form entries are correct.

- 25. Close the Storage Intervals window.
- 26. Turn on data collection as described in <u>Turning data collection on and off using the PC</u> <u>Client</u> on page 358.
- 27. In the **Operations** list, highlight **CMS State**.

Supervisor displays the CMS State window.

- 28. Select the option Multi-user mode.
- 29. From the menu bar, select **Actions > Modify**.
- 30. Close the CMS State window.
- 31. Do one of the following:
  - If you want to create a Dictionary name for the pseudo-ACD just created, continue with Step <u>29</u> on page 327.
  - If you do not want to create a Dictionary name for the pseudo-ACD just created, continue with <u>Viewing pseudo-ACDs using the PC Client</u> on page 325.
- 32. From the menu bar, select **Commands > Dictionary**.

#### 😵 Note:

A pseudo-ACD must exist before a dictionary name for the pseudo-ACD can be created.

Supervisor displays the Dictionary window.

- 33. In the **Operations** list, highlight **ACDs**.
- 34. Select OK.

Supervisor displays the Dictionary ACDs window.

- 35. In the ACD Name field, enter the name for the pseudo-ACD.
- 36. In the ACD Number field, enter the number for the pseudo-ACD from Step 4.
- 37. In the **Description** field, a description for the pseudo-ACD. The origin of the data can be useful information in the description field.
- 38. From the menu bar, select **Actions** > **Add**.

Supervisor adds the pseudo-ACD name to the dictionary.

😵 Note:

After creating a dictionary name for a pseudo-ACD, you must log out of Supervisor and log in again to see the dictionary name of the pseudo-ACD displayed in drop down lists.

39. Continue with <u>Viewing pseudo-ACDs using the PC Client</u> on page 325.

## **Deleting a pseudo-ACD using the PC Client**

#### About this task

This section provides the procedure for deleting a pseudo-ACD on a CMS server.

#### Procedure

- From the Controller window, select **Tools** > **System Setup**.
   CMS Supervisor displays the System Setup window.
- 2. In the **Operations** list, highlight **Pseudo-ACD Setup**.
- 3. Click OK.

Supervisor displays the Pseudo-ACD Setup window.

- 4. In the ACD field, enter the name or number of a pseudo-ACD to delete.
- 5. From the menu bar, select **Actions > Find one**.

The status bar displays whether a match was found for the specified pseudo-ACD.

6. From the menu bar, select **Actions > Delete**.

CMS deletes the pseudo-ACD, the associated data, and returns any associated disk space to the database. When the operation completes, Supervisor displays a <code>Successful</code> message in the status bar.

# About backing up data from a real ACD to load on a pseudo-ACD

This section provides the procedure for backing up historical data archived from an existing real ACD, to be used when loading data on a pseudo-ACD.

## Before backing up data from a real ACD to load on a pseudo-ACD

The following items should be read and understood before backing up real ACD data for a pseudo-ACD:

- Data used for a pseudo-ACD must have been archived from an existing ACD on a CMS server.
- Since the pseudo-ACD accepts any data on a backup volume, the data from a full backup may be more than needed. Loading a pseudo-ACD with a full backup creates the possibility of disk space problems. To eliminate this problem, it is suggested that you do a **Specific**

**tables** backup when creating the ACD data to load into a pseudo-ACD. For more information, see <u>Backing up specific tables to load on a pseudo-ACD</u> on page 330.

- The pseudo-ACD Data Storage Allocation must match or be greater than the ACD where the data was archived. Document the values in the Data Storage Allocation table for the ACD where the data was archived. Verify that the pseudo-ACD configuration matches or is greater than the documented values. If these settings are incorrect, loading the data into the pseudo-ACD can fail.
- The pseudo-ACD Storage Intervals must match the ACD where the data was archived. Document the values in the Storage Intervals table for the ACD where the data was archived. Verify that the pseudo-ACD configuration matches the documented values. If these settings are incorrect, loading the data into the pseudo-ACD can fail.
- CMS supports CMS data backups to tape, NFS mount points, and USB storage devices. The backup path must be defined in Maintenance > Backup/Restore Devices. Refer to Maintaining and Troubleshooting Avaya Call Management System to administer a Backup/ Restore Device for a network mount point or a USB storage device. Refer to Maintaining and Troubleshooting Avaya Call Management System to perform a tapeless migration.

# Scenario for backing up data from a real ACD to load on a pseudo-ACD

#### About this task

The CMS feature, Load pseudo-ACD Data, loads data from the latest CMS maintenance backup that exists in the Backup/Restore Device path. Use the following procedure if the Backup/Restore Device is a network mount point or USB storage device, and the pseudo-ACD data is only a set of specific tables.

#### Procedure

- 1. Create a directory only for the pseudo-ACD data.
- Create a Backup/Restore Device pointing to the specific directory for the pseudo-ACD data.
- 3. Perform a backup of the desired data for the pseudo-ACD using the Backup/Restore Device just created.
- 4. Load the pseudo-ACD data using the same Backup/Restore Device name in the Loading Pseudo-ACD Data form as used in the Backup Data form.

This process ensures that correct data is loaded into the pseudo-ACD since the only data that exists in the directory of the Backup/Restore Device path is the data specifically backed up for the pseudo-ACD.

# Permissions required to back up data from a real ACD to load on a pseudo-ACD

You must have write permission for the Maintenance feature as well as the Back Up Data feature.

## Backing up specific tables to load on a pseudo-ACD

#### Procedure

- 1. Document the entries in the Data Storage Allocation form for the ACD that will be used to load data into the pseudo-acd.
- 2. Document the entries in the Storage Intervals form for the ACD that will be used to load data into the pseudo-acd.
- 3. From the Controller window, select **Tools > Maintenance**.

Supervisor displays the CMS Maintenance window.

- 4. In the **Operations** list, highlight **Backup Data**.
- 5. In the **ACD** list, highlight the ACD that contains the data to be backed up for the pseudo-ACD.
- 6. Select OK.

Supervisor displays the Backup Data window.

- 7. In the **Device name** field, enter the Backup/Restore device name to use to backup the ACD data.
- 8. If the backup device is not a tape storage device, clear the **Verify tape can be read after backup?** option.
- 9. From the ACD(s) to back up options, select Current ACD.
  - If all the tables from the current ACD are being backed up, continue with Step <u>15</u> on page 331.
  - If only specific tables from the current ACD are being backed up, continue with Step <u>10</u> on page 330.
- 10. From the menu bar, select **Actions > Select tables**.

Supervisor displays the Backup Data - Select Tables window.

- 11. Click inside the box for selecting all the tables to be backed up.
- 12. From the menu bar, select **Actions** > **Modify**.

Supervisor saves the tables selected for the back up.

13. From the menu bar, select **Actions > Exit**.

Supervisor displays the Backup Data window and checks the **Specific tables** option under **Data to back up**.

- 14. From the **Data to back up** options, clear the **System**, **ACD-specific administration data**, **Historical**, and **Non-CMS data** data options. When **Specific tables** is selected, no other type of data can be selected.
- 15. To start the backup, select **Actions > Run**.

Supervisor displays the following message:

The backup is estimated to be xxxxxx kbytes.

16. Select **OK**.

Supervisor displays the following message if the backup device already contains CMS data:

Mounted volume might belong to CMS data archive. Enter yes to overwrite it or no to mount another volume.

- If you are not sure whether or not to overwrite the data, enter No.
  - If the backup device is a tape storage device, replace the tape and repeat Steps 1-14.
  - If the backup device is a network mount point or USB storage device, repeat Steps 1-14 but choose a different backup device in Step 7.
- If you are sure it is safe to overwrite the CMS data, enter Yes.

CMS begins backing up the data for the current ACD. The **Status** field at the top of the window displays events in the backup process. The **Errors** field displays any problems encountered during the backup process.

Cancelling the backup process before it is finished causes the backup to be incomplete.

#### Result

If the backup is to a network mount point or a USB storage device, the backup filename can be found under the path defined for the Backup/Restore Device name used for the backup.

An example of a CMS data backup filename is:

CMS-130417-04-XXXX-04-F-01-04-igor0000000000

#### Important:

The data backup filename must be in the format as shown in the example or CMS fails to detect the file as a data backup file.

The data backup file name identifies the following:

- Type of backup: CMS Data
- Date of the backup: 130417 (yymmdd)
- Number of CMS data backups completed for the day: 04
- Type of data backed up: XXXX (specific tables only)

LSAC (System, ACD-specific, Historical and Non-CMS data)

LSMC (System and ACD-specific data)

• ACD Number: 04

ACD 4, this value is 00 if all ACDs are being backed up.

• Type of back up: F-01

F (Full Maintenance backup)

I (Incremental Maintenance backup)

- Number of characters in hostname: 04 (igor)
- · CMS hostname: igor

This field is 15 characters long. The number of trailing zeros in this example is 11 so that the total number of letters in the hostname is 15.

## About loading pseudo-ACD data

This section provides the procedures for loading historical data archived from an existing ACD into a pseudo-ACD. After the pseudo-ACD receives the data, historical reports can be run with this information.

## Before loading pseudo-ACD data

The following items should be read and understood before loading data into a pseudo-ACD:

- A pseudo-ACD must have been created in order for data to be loaded into it. For more information, see <u>About administering pseudo-ACDs</u> on page 322.
- Loading data into a pseudo-ACD requires a backup of data archived from an existing ACD on a CMS server. For more information, see <u>About backing up data from a real ACD to load on a pseudo-ACD</u> on page 328.
- Set the pseudo-ACD as the current ACD before attempting to load data into it.
- Since the pseudo-ACD accepts any data on a backup volume, the data from a full backup may be more than needed. Loading a pseudo-ACD with a full backup creates the possibility of disk space problems. To eliminate this problem, it is suggested that you do a **Specific tables** backup when creating the ACD data to load into a pseudo-ACD. For more information, see <u>Backing up specific tables to load on a pseudo-ACD</u> on page 330.
- Loading a pseudo-ACD with data automatically overwrites any existing data currently used by the pseudo-ACD.
- When created, a new pseudo-ACD has historical data storage parameters set to 0 (zero). To load data into the pseudo-ACD, the historical data storage parameters must be set to those of the ACD from which the data was archived, if not greater. Change these settings through the Data Storage Allocation window.

• The **Storage Intervals** and **Data Collection** settings for the pseudo-ACD require configuration in order to match those of the ACD supplying the data. If these settings are incorrect, loading the data into the pseudo-ACD fails.

## Permissions required to load pseudo-ACD data

To load data into a pseudo-ACD, you must have "write" permission for the CMS System Setup feature.

## Verifying that the backup data can be read

#### About this task

Before you load data onto a pseudo-ACD, it is suggested that you verify that the backup data can be read.

#### Before you begin

Create the pseudo-ACD as described in <u>About administering pseudo-ACDs</u> on page 322.

#### Procedure

1. Log on as root to the CMS server.

#### Important:

You cannot directly log on as root from a remote connection. You must log on using an administered CMS user ID, then use su - root to log on with root privileges.

2. Verify that the data on the media is from the desired source. Enter:

#### /cms/bin/br\_check

The system displays the following message:

```
Enter device type ['q' for qtape, 'f' for floppy, 'n' for nfs/usb]:
```

3. Depending on the type of backup media containing the data, enter q, f, or n.

The system displays the following message:

Enter device path:

4. Enter the device path.

The system displays the **br\_check** information found on the device. The following example is for backup data on an NFS backup:

```
Opening the volume...
Label: CMS-200603-01-LSAC-00-F-01
CMS Database Version: r19fa.f.2
Machine name: cmstestsystem
forecasting: n
```

```
global dictionary/ACD groups: y
multi-tenancy: y
Dual IP: n
LDAP authentication: y
ACD(s) backed up on the volume:
ACD Switch EAS Vectoring
1 R8 y y
2 R7 y y
```

- Enter 'l' to list the tables or 'v' to also verify the volume:
- 5. Enter  ${\rm v}$  to verify the backup data. The verification might take a few minutes.
- 6. Review the **br\_check** output.
  - If the backup data is valid, continue with loading pseudo-ACD data.
  - If the backup data is not valid, replace the tape or path with the correct backup data information. Repeat the validation process.

## Loading pseudo-ACD data using the Web Client

#### Procedure

1. Navigate to Administration > System Setup > Load Pseudo-ACD Data.

CMS Supervisor displays the Load Pseudo-ACD Data window.

- 2. Administer the following options:
  - In the **From ACD** field, enter the number of the source ACD, which is the ACD used to make the data backup, or the number of the ACD to migrate data from the full maintenance backup.
  - In the ACD field, select the pseudo-ACD that will receive the data.
  - In the **Device name** field, select the device that has the backup volume loaded.

#### **Caution**:

The Loading Pseudo-ACD Data feature loads data from the latest CMS maintenance backup that exists in the path defined in the Backup/Restore Device name entered. Ensure that the latest CMS data backup under the Backup/Restore Device name contains the data you want loaded into the pseudo-ACD. For more information, see <u>Verifying that the backup data can be read</u> on page 333.

- In the **Start date** field, enter the date representing the first day of historical data to load into the pseudo-ACD. CMS searches the data backup for this date which serves as the starting point for loading data.
- In the **Start time** field, enter the time from which CMS will start loading data. The default time is 12:00AM.
- In the **Stop date** field, enter the last date of historical data that CMS will load into the pseudo-ACD.

• In the **Stop time** field, enter the time at which CMS will stop loading data from the data backup. The default is 12:00AM.



To restore all the data for the selected ACD, you can leave the **Start date** blank and enter a future date for the **Device name** in the backup file.

3. Click Run to load the pseudo-ACD data. Click Reset to clear the option fields.

CMS begins loading data from the backup into the pseudo-ACD. The **Errors** field displays any problems encountered during the loading process.

Cancelling the load process before it is finished causes the pseudo-ACD to have partial data.

## Loading pseudo-ACD data using the PC Client

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

Supervisor displays the CMS System Setup window.

- 2. In the **Operations** list, highlight **Load Pseudo-ACD**.
- 3. In the **ACD** field, select the pseudo-ACD that will receive the data.
- 4. Select OK.

Supervisor displays the Load Pseudo-ACD Data window.

- 5. In the **From ACD** field, enter the number of the source ACD, which is the ACD used to make the data backup, or the number of the ACD to migrate data from the full maintenance backup tape.
- 6. In the **Device name** field, enter the name of the device that has the backup volume loaded.

To list all the devices on the CMS server, select **Actions** > **List devices** from the menu bar.

#### ▲ Caution:

The Loading Pseudo-ACD Data feature loads data from the latest CMS maintenance backup that exists in the path defined in the Backup/Restore Device name entered. Ensure that the latest CMS data backup under the Backup/Restore Device name contains the data you want loaded into the pseudo-ACD. For more information, see <u>Verifying that the backup data can be read</u> on page 333.

7. In the **Start date** field, enter the date representing the first day of historical data to load into the pseudo-ACD. CMS searches the data backup for this date which serves as the starting point for loading data.

- 8. In the **Start time** field, enter the time of the **Start time** for which CMS will start loading data. The default is 12:00AM.
- 9. In the **Stop date** field, enter the last date of historical data that CMS will load into the pseudo-ACD.
- 10. In the **Stop time** field, enter the time of the **Stop time** for which CMS will stop loading data from the data backup. The default is 12:00AM.

😵 Note:

To restore all the data, for the selected ACD, you can leave the **Start date** blank and enter a future date for the **Device name** in the backup file.

11. From the menu bar, select **Actions** > **Run**.

CMS begins loading data from the backup into the pseudo-ACD. The **Status** field at the top of the window displays events in the loading process. The **Errors** field displays any problems encountered during the loading process.

Cancelling the load process before it is finished causes the pseudo-ACD to have partial data.

When the data has been loaded, Supervisor displays the Load Pseudo-ACD Data - Acknowledge window.

- If there is no other volume of data to load, select **Actions > Stop**.
- If there are more volumes to load data from, select Actions > Continue.
- 12. When you select the **Stop** option in the Load Pseudo-ACD Data Acknowledge window, Supervisor updates the **Status** field at the top of the Load Pseudo-ACD Data window with the timestamp during which the loading of the pseudo-ACD data was completed.

#### 😵 Note:

If the you log out of CMS before the Load Pseudo ACD Data action is finished, it will continue to run in the background. You may check the status of the load action later by logging back in and running Load Pseudo ACD Data. Check the Status on the screen for completion information.

## About administering Data Storage Allocation

The Data Storage Allocation window is used to specify the amount of historical data saved by CMS and the duration for which it is saved. The amount of data saved and the duration for which it is saved affects disk space on the server and is limited by the configuration of the system. Data storage parameters are initially set during installation.

## **Before using Data Storage Allocation**

The following items should be read and understood before working with Data Storage Allocation:

- A full maintenance backup should be performed before changing the Data Storage Allocation configuration.
- If changes to the Communication Manager system are made through the swsetup command on the CMS console, the settings for Data Storage Allocation should be checked to ensure that storage is set for any new or modified entities. For example, enable the Call Vectoring feature requires data storage space for VDNs and vectors. Changing the release of the Communication Manager system may change the number of measured entities allowed and affect the storage allocation for each entity.
- Disable data collection for all real ACDs before making modifications through Data Storage Allocation.
- Set the CMS state to single-user mode before making modifications through Data Storage Allocation.
- When determining the amount of storage space needed, remember that future growth of items, such as trunk groups or splits/skills, need to be taken into account.
- For reference, print out the Data Storage Allocation window before modifications are made.
- If a Data Storage Allocation window is modifying data, do not open a second Data Storage Allocation window. Wait for the first window to finish the modifications as performing simultaneous modifications through two Data Storage Allocation windows can result in damage to data tables.
- Activating a feature such as vectoring requires not only changing switch parameters but also requires the allocation of space for VDNs and vectors which did not have space previously allocated.
- The amount of free space available on the server limits the maximum amount of storage space usable through Data Storage Allocation. Use the Free Space Allocation window to view the utilization of disk space before making changes to Data Storage Allocation. If changes are made to the Data Storage Allocation settings, free space is automatically adjusted.
- The length of the intrahour interval affects the amount of disk space required to store intrahour data. For example, an intrahour interval of 30 minutes requires twice the amount of disk space than an intrahour interval of 60 minutes.
- If the Call Vectoring feature has not been purchased and installed, the fields corresponding to call work codes, vectors, and VDNs are not displayed.
- The data storage values determine how much data is available for running historical reports. For example, if weekly and monthly data is not saved, weekly or monthly reports display no data.

- Disk space affects the amount of historical data that can be stored. The following list provides the maximum durations possible when storing historical data:
  - Intrahour 370 days
  - Daily 1825 days (5 years)
  - Weekly 520 weeks (10 years)
  - Monthly 120 months (10 years)

## Permissions required to administer Data Storage Allocation

Depending on the procedure that you want to perform, you need the following permissions:

- To view Data Storage Allocation settings, you must have "read" permission for the CMS System Setup feature.
- To modify Data Storage Allocation settings, you must have "write" permission for the CMS System Setup feature.

## Viewing Data Storage Allocation using the Web Client

#### Procedure

Navigate to Administration > System Setup > Data Storage Allocation

CMS Supervisor displays the current values administered for Data Storage Allocation.

2. To change the Data Storage Allocation values, see <u>About modifying Data Storage</u> <u>Allocation</u> on page 339.

## Viewing Data Storage Allocation using the PC Client

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Data Storage Allocation**.
- 3. In the **ACD** field, select the ACD for which the data storage settings will be viewed.
- 4. Click OK.

CMS Supervisor displays the Data Storage Allocation window.

5. To change the Data Storage Allocation values, see <u>About modifying Data Storage</u> <u>Allocation</u> on page 339.

## About modifying Data Storage Allocation

This section provides the definitions of the fields displayed in the Data Storage Allocation window and suggestions for determining the necessary values. The data storage configuration is done on a per-ACD basis. In a multi-ACD environment, data storage allocation should not be set too high as it can exceed disk capacity for storing information for the other ACDs.

Data storage allocation needs vary among installations. Base your CMS data storage needs on these criteria:

- The available disk space on your CMS system
- The number of real and pseudo-ACDs on the CMS system
- The size of the real ACDs and all pseudo-ACDs, such as number of agents, trunks, and so forth.
- The length of time for data to be stored. For example, 30 days versus 100 days versus two years.

#### Before modifying data storage allocation

Before modifying the configuration of the Data Storage Allocation window, the following must occur:

- Data collection for all real ACDs must be disabled.
- The CMS state must be set to single-user mode.
- A full maintenance backup should be performed before changing the Data Storage Allocation configuration.
- Print the current Data Storage Allocation values in case you must go back to the original values.

## **Data Storage Allocation field definitions**

The following table lists the fields found on the Data Storage Allocation window. Several of these data storage parameter limits are documented in *Avaya Aura*<sup>®</sup> *Communication Manager System Capacities Table*.

Name	Description
Data Item	Lists the data items for which you can set Data Storage Allocation values.
# of Items	The amount of data storage space that is allocated for each of the Data Items. You cannot administer a value for Agents.
	These value you allocate should include expected growth. For example, a 30 in the <b>Split(s)/Skill(s)</b> field indicates that storage space is allocated for 30 splits or skills. The system may have only 25 splits or skills in existence, but this number allows for future growth.

Table continues...

Name	Description
Days of Intrahour	The number of days where the system stores intrahour data for the Data Items.
	A zero value in this field causes the system to discard intrahour data, which also means that no daily, weekly, or monthly data can be collected.
	When data collection reaches the end of the length of time specified, the data is combined, archived, and appended into daily information.
Days of Daily	The number of days for which the system stores daily data for the Data Items.
	A zero value in this field causes the system to discard daily data which also means that no daily or weekly data can be collected.
	When data collection reaches the end of the length of time specified, the data is combined, archived, and appended into weekly information.
Weeks of Weekly	The number of weeks for which the system stores weekly data for the Data items.
	A zero value in this field causes the system to discard weekly data.
	When data collection reaches the end of the length of time specified, the data is combined, archived, and appended into monthly information.
Months of Monthly	The number of months for which the system stores monthly data for the Data Items.
	A zero value in this field causes the system to discard monthly data.
	When data collection reaches the end of the length of time specified, the data is deleted.
Total split/skill members, summed over all splits/ skills	The maximum number of agents or extensions across all splits or skills that are measured or logged in at any one time.
	This number should include those agents or extensions that are members of multiple splits or skills. For this field, each split or skill the agent belongs to counts as a split or skill member. Using this method of determining members results in a higher number than the number of agents.
	This value represents the maximum agent/skill pairs (skill members) that are logged in.

Table continues...

Name	Description
Number of agent login/ logout records	The number of agent login/logout records stored by the system. Each time an agent logs in, the system creates a login/logout record. The subsequent logout of the agent also uses this same record. If, at a later time, the agent logs in again, another login/logout record is created.
	The following equation demonstrates how this number is calculated:
	(Number of agents) x (Number of times each agent logs in each day) = Number of agent login/logout records
	If there are 200 agents and each agent logs in three times per day, using the equation above would result in 600 agent login/logout records for this field.
	When skills for an agent are changed, a new login/logout record is generated if the agent is currently logged in to the system.
Number of agent trace records	The number of agent trace records for the currently specified ACD. This number is not representative of all ACDs.
Number of unmeasured	The number of trunks not measured by the CMS system.
trunk facilities	An unmeasured trunk facilities are used for:
	<ul> <li>Internal calls (intraswitch) to a measured split or agent</li> </ul>
	Internal calls to VDNs
	<ul> <li>Calls made by agents to internal destinations or using a trunk group that is not measured</li> </ul>
	Transfers and conferences until the transfer/conference is complete
	This number should be set high enough to handle the traffic expected over these unmeasured trunks, but cannot exceed the maximum number of trunks minus the number of measured trunks. The default value for this field is 300.
Number of exception records	The total number of exceptions stored for CMS. This total is for each type of exception, such as agents, splits/skills, VDNs, and so forth.
Number of call records	The number of call records the system stores for a selected ACD.
	If the Avaya CMS Call History Interface product has been purchased and installed, another computer can be used for storage and analysis of the call records. This field then represents the amount of buffer space set aside on the CMS server that is used to collect the call records prior to transmission to the other system.

## About viewing Free Space Allocation

The Free Space Allocation window is used to view the current storage statistics and disk usage for the call center data collected through CMS .

If at any time you modify the Data Storage Allocation configuration, Free Space Allocation will automatically adjust the amount of required space.

## **Before viewing Free Space Allocation**

The following items should be read and understood before working with the Free Space Allocation feature:

- When any of the CMS data storage parameters are altered, the change is reflected (for information purposes only) in the Free Space Allocation window. For example, if the number of splits/skills on your system is increased in the Data Storage Allocation window, the Free Space Allocation window will then display the new number as well as the approximate amount of disk space required to handle the data storage for splits/skills.
- The IDS dbspaces used in the Free Space Allocation window are created during installation.
- Be aware that creating custom tables causes CMS to use more disk space. If dbspace is used to store custom tables nears capacity, you are presented with a warning message during login.
- Values entered in the CMS System Setup features of Data Storage Allocation, Storage Intervals, and Call Work Codes directly affect usage of disk space. Check **Free Space Allocation** when any of these features are modified.
- Values entered in the Data Storage Allocation window of Forecast Administration also affect storage space.

## Permissions required to view Free Space Allocation

To view the Free Space Allocation window, you must have "read" permission for the CMS System Setup features.

## Viewing Free Space Allocation using the Web Client

#### Procedure

1. Navigate to Administration > System Setup > Free Space Allocation.

CMS Supervisor displays the Free Space Allocation values for the current ACD.

- 2. In the **ACD** drop-down list, select the ACD or pseudo-ACD for which you want to view the Free Space Allocation.
- 3. To view the detailed Free Space Allocation usage, click **Group Contents** on the ACD or pseudo-ACD.

CMS Supervisor displays the detailed allocated sizes for the ACD or pseudo-ACD.

4. Click **OK** to close the detailed allocated size window.

# Viewing Free Space Allocation using the PC Client

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Free Space Allocation**.
- 3. Click OK.

Supervisor displays the Free Space Allocation input window for each ACDs:

- ACD Name The name assigned to this ACD.
- Allocated Size The amount of space needed to store data based on the settings in the Data Storage Allocation window
- Space used to Date The amount of data actually stored at this time

The window may take a few minutes to open as CMS is calculating the current free space and other values on the system before the window can be displayed.

## Viewing Free Space Allocation detailed values using the PC Client

#### About this task

This section provides the procedure for viewing the allocations for each call center entity within an ACD.

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Free Space Allocation**.
- 3. Click **OK**.

CMS Supervisor displays the Free Space Allocation input window.

#### 😵 Note:

The window make take a few minutes to open as CMS is calculating the current free space before the window can be displayed.

- 4. In the **ACD** field, enter the name or number of the ACD to view.
- 5. From the menu bar, select **Actions** > **Get contents**.

CMS Supervisor displays a secondary window showing the amount of data currently in use by each call center entity.

## About administering storage intervals

The Storage Intervals window allows changes to be made to CMS which affect how and when data for the call center is stored. You can adjust the following storage interval options:

- Intrahour Interval
- Data summarizing time
- Switch time zone offset
- Day of week start day
- Day of week end day
- · Daily start time
- · Daily stop time

It is recommended that you configure these settings during installation and not change them because changes will affect data storage and report data coverage.

## Before administering storage intervals

The following items should be read and understood before working with the Storage Intervals window:

- CMS must be in single-user mode and data collection must be off before modifications to these settings can be made.
- For the PC Client, do not open another Storage Intervals window if one is already being used to alter these settings. Loss of data tables can result if multiple Storage Intervals windows are used.
- Free space allocation, data storage allocation, and storage intervals closely tied. A change in storage intervals may require adjustment of data storage or storage times in the Data Storage Allocation window. The more frequently CMS archives data, the more storage space is required.

## Permissions required to administer storage intervals

Depending on the procedure that you want to do, you need the following permissions:

- To view settings in the Storage Intervals window, you must have "read" permission for the CMS System Setup feature.
- To modify settings in the Storage Intervals window, you must have "write" permission for the CMS System Setup feature.

## Viewing storage interval settings using the Web Client Procedure

Navigate to Administration > System Setup > Storage Intervals.

CMS Supervisor displays the Storage Intervals window.

## Viewing storage interval settings using the PC Client

#### About this task

This section provides the procedure for viewing the Storage Intervals settings for call center data.

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Storage Intervals**.
- 3. In the **ACD** field, select the ACD for which settings will be viewed.
- 4. Click OK.

CMS Supervisor displays the Storage Intervals window.

## About modifying the intrahour interval

This section provides the procedure for changing the rate at which CMS archives data within a one-hour time period. You can set the interval for 15, 30, or 60 minutes.

#### Before modifying the intrahour interval

The following items should be read and understood before changing the intrahour interval setting:

- Changing the intrahour interval can result in a lengthy process as CMS must make modifications to all previously collected data.
- Increasing the frequency of the intrahour interval results in the call center data taking more storage space. This can require changes to the length of time for which CMS stores call center data. To change the length of time which data is stored, use the Data Storage Allocation window.
- Perform a full backup of historical data before making changes to the intrahour interval or data collection times or dates. After the changes are made, perform another full backup of historical data.
- Real-time reports use the intrahour interval when displaying data. Cumulative data is reset to zero at the beginning of each intrahour interval.

### Modifying the intrahour interval using the Web Client Procedure

- Navigate to Administration > System Setup > Storage Intervals.
   CMS Supervisor displays the Storage Intervals window.
- 2. Select a value for the Intrahour interval option.
- Click Modify to save the change. Click Reset to reset the values of the fields.
   CMS Supervisor displays the window with the updated values.

## Modifying the intrahour interval using the PC Client Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Storage Intervals**.
- 3. In the **ACD** field, select the ACD for which the intrahour interval will be changed.
- 4. Click OK.

CMS Supervisor displays the Storage Intervals window.

5. In the **Intrahour interval (select one)** group, select the option for the rate at which CMS archives call center data.

#### ▲ Caution:

Do not open another **Storage Intervals** window and attempt to change other settings during the following step. Doing so can result in the loss of database tables.

6. From the menu bar, select **Actions > Modify**.

CMS records the setting change and alters all previously recorded data to match this setting. This update process is lengthy and must not be interrupted. The status bar will display a Successful message when the operation completes.

7. Restart data collection.

See <u>Turning data collection on and off using the PC Client</u> on page 358 for information on this procedure.

8. Return CMS to multi-user mode.

See the <u>Changing the CMS operational state using the PC Client</u> on page 355 for information on this procedure.

## About modifying the switch time zone

This section provides the procedure to modify the time zone settings for an ACD so that it matches the time zone of the CMS server. Use this feature if you want the CMS title bar to show the time where the CMS is located instead of the master ACD time. If you do not use this feature, the CMS title bar will automatically display the master ACD time.

This procedure is only necessary for those configurations where an ACD resides in a different time zone than that of the CMS server, but you want the title bar to display the CMS time.

#### Before modifying the switch time zone

The following items should be read and understood before modifying the time zone for an ACD:

- CMS must be in single-user mode and the data collection must be off before modifications to these settings can be made.
- If an ACD is connected to a CMS server in the same time zone, the **Switch time zone offset** field should be set to **0**.
- This procedure does not affect the time stamps on the CMS reports, real time or historical.
- This procedure does *not* affect the timetable schedule for timetables set to run at local times for a specific ACD.

#### Modifying the switch time zone using the Web Client

#### Procedure

1. Navigate to Administration > System Setup > Storage Intervals.

CMS Supervisor displays the Storage Intervals window.

2. For the **Switch time zone offset (-23 to +23)** option, enter the number of hours that will convert the time zone of the ACD so that it matches the time zone of the CMS server.

If the ACD time is ahead of the CMS server time, you must enter a plus sign (+) followed by the number of hours the ACD is ahead. If the ACD time is behind the CMS server time, you must enter a minus sign (-) followed by the number of hours the ACD is behind.

For example, if the master ACD is in New York City and the CMS server is in Los Angeles, you would enter +3 because the ACD is 3 hours ahead of the CMS server time. The time zone offset does not affect the time stamps that are used with historical data.

3. Click **Modify** to save the change. Click **Reset** to reset the values of the fields.

CMS Supervisor displays the window with the updated values.

#### Modifying the switch time zone using the PC Client Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the Operations list, highlight Storage Intervals.
- 3. In the **ACD** field, select the ACD which will have its time zone offset changed.
- 4. Click OK.

Supervisor displays the Storage Intervals window.

5. In the **Switch time zone offset (-23 to +23)** field, enter the number of hours that will convert the time zone of the ACD so that it matches the time zone of the CMS server.

If the ACD time is ahead of the CMS server time, you must enter a plus sign (+) followed by the number of hours the ACD is ahead. If the ACD time is behind the CMS server time, you must enter a minus sign (-) followed by the number of hours the ACD is behind.

For example, if the master ACD is in New York City and the CMS server is in Los Angeles, you would enter +3 because the ACD is 3 hours ahead of the CMS server time. The time zone offset does not affect the time stamps that are used with historical data.

6. From the menu bar, select Actions > Modify.

CMS adjusts the time setting of the ACD by the value specified. The status bar will display a Successful message when the operation is complete.

😵 Note:

The CMS time reverts to the operating system (Linux) clock if the link to the ACD that is designated as the master clock stops functioning. Even if the link begins to function normally, the only way CMS will reset back to the master clock is to either turn CMS off and then on or reboot the server.

7. Restart data collection.

See <u>Turning data collection on and off using the PC Client</u> on page 358 for information on this procedure.

8. Return CMS to multi-user mode.

See <u>Changing the CMS operational state using the PC Client</u> on page 355 for information on this procedure.

## About modifying the data summarizing time settings

This section provides the procedure for modifying the times and days for which call center data is recorded and summarized.

#### Before modifying the data summarizing time settings

The following items should be read and understood before modifying data summarizing settings:

• CMS must be in single-user mode and the data collection must be off before modifications to these settings can be made.

- Perform a full backup of historical data before making changes to the data collection times or dates. After the changes are made, perform another full backup of historical data.
- When a weekly report is requested, the date entered must correspond to the day of the week specified in the **Week start day** field.

#### ▲ Caution:

On the PC Client, do not open another Storage Intervals window and attempt to change other settings while modifying these settings. Doing so can result in the loss of database tables.

### Modifying the data summarizing time settings using the Web Client Procedure

1. Navigate to Administration > System Setup > Storage Intervals.

CMS Supervisor displays the Storage Intervals window.

- 2. Administer the following options:
  - In the **Data summarizing time** field, enter the time when CMS should summarize data for the previous day, week, and month. The time must be entered in one of the following formats:
    - HH:MM PM For example, 12:35 AM
    - 24-hour format For example, 00:35

If you do not wish to change this field, proceed to the next option.

The time entered in this field must be equal to or greater to intrahour interval in order to allow CMS to finish archiving data. The default time for this field is 12:35 AM.

Weekly summaries are started on the day following the day specified in the **Week stop day** field. Monthly summaries are started on the first day of the next month. For example, the monthly summary for January is done on the first day of February.

To run data summarizing on the day for which data was collected, the **Data** summarizing time field must be set for 15 minutes after the **Daily stop time** and prior to midnight. For example, the **Data summarizing time** field can be set to 11:59 PM or 23:59. This would require that the **Daily stop time** field be set to 11:44 PM or 23:44.

• In the **Week start day** group, select the day that represents the start of the work week for the call center.

If you do not wish to change this field, proceed to the next option.

The default value for this field is **Sunday**.

• In the **Week stop day** group, select the day that represents the end of the work week for the call center.

If you do not wish to change this field, proceed to the next option.

The default value for this field is **Saturday**. Data through the end of the stop day is collected and included in the weekly summary.

When the start or stop day is changed for the week, the data from the old start day through the new stop day for the week is archived.

If possible, make any changes to the **Week start day** and **Week stop day** after CMS performs the weekly archive. This change is not possible for a seven-day week. When the start and stop day for the week are changed, the current week will contain the data item, INCOMPLETE, to indicate that the data for this week is peculiar since the definition of that week was changed.

If the **Week start day** and **Week stop day** are identical, data for only one day will be collected for that week.

- In the **Daily start time** field, enter the time at which data collection should start. Enter the time in one of the following formats:
  - HH:MM PM For example, 12:00 AM
  - 24-hour format For example, 00:00

If you do not wish to change this field, proceed to the next option.

The default value for this field is 12:00 AM (midnight).

• In the **Daily stop time** field, enter the time at which data collection should stop. Enter the time in one of the formats specified in the previous step.

The default value for this field is 11:59 PM. Data is collected through the end of the minute specified.

Do not enter the same time in this field as in the **Daily start time** field. Doing so will result in data being collected for only one minute per day.

3. Click **Modify** to save the change. Click **Reset** to reset the values of the fields.

CMS Supervisor displays the window with the updated values.

#### Modifying the data summarizing time settings using the PC Client Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Storage Intervals**.
- 3. In the **ACD** field, select the ACD which will have its data summarizing settings changed.
- 4. Click OK.

CMS Supervisor displays the Storage Intervals window.

- 5. In the **Data summarizing time** field, enter the time when CMS should summarize data for the previous day, week, and month. The time must be entered in one of the following formats:
  - HH:MM PM For example, 12:35 AM

• 24-hour format - For example, 00:35

If you do not wish to change this field, skip this step and proceed to the next.

The time entered in this field must be equal to or greater to intrahour interval in order to allow CMS to finish archiving data. The default time for this field is 12:35 AM.

Weekly summaries are started on the day following the day specified in the **Week stop day** field. Monthly summaries are started on the first day of the next month. For example, the monthly summary for January is done on the first day of February.

To run data summarizing on the day for which data was collected, the **Data summarizing time** field must be set for 15 minutes after the **Daily stop time** and prior to midnight. For example, the **Data summarizing time** field can be set to 11:59 PM or 23:59. This would require that the **Daily stop time** field be set to 11:44 PM or 23:44.

6. In the **Week start day** group, select the day that represents the start of the work week for the call center.

If you do not wish to change this field, skip this step and proceed to the next.

The default value for this field is **Sunday**.

7. In the **Week stop day** group, select the day that represents the end of the work week for the call center.

If you do not wish to change this field, skip this step and proceed to the next.

The default value for this field is **Saturday**. Data through the end of the stop day is collected and included in the weekly summary.

When the start or stop day is changed for the week, the data from the old start day through the new stop day for the week is archived.

If possible, make any changes to the **Week start day** and **Week stop day** after CMS performs the weekly archive. This change is not possible for a seven-day week. When the start and stop day for the week are changed, the current week will contain the data item, INCOMPLETE, to indicate that the data for this week is peculiar since the definition of that week was changed.

If the **Week start day** and **Week stop day** are identical, data for only one day will be collected for that week.

- 8. In the **Daily start time** field, enter the time at which data collection should start. Enter the time in one of the following formats:
  - HH:MM PM For example, 12:00 AM
  - 24-hour format For example, 00:00

If you do not wish to change this field, skip this step and proceed to the next.

The default value for this field is 12:00 AM (midnight).

9. In the **Daily stop time** field, enter the time at which data collection should stop. Enter the time in one of the formats specified in the previous step.

If you do not wish to change this field, skip this step and proceed to the next.

The default value for this field is 11:59 PM. Data is collected through the end of the minute specified.

Do not enter the same time in this field as in the **Daily start time** field. Doing so will result in data being collected for only one minute per day.

10. From the menu bar, select **Actions > Modify**.

CMS updates the data summarizing parameters as specified. A Successful message appears in the status bar when CMS completes the operation.

11. Restart data collection.

See <u>Turning data collection on and off using the PC Client</u> on page 358 for information on this procedure.

12. Return CMS to multi-user mode.

See <u>Changing the CMS operational state using the PC Client</u> on page 355 for information on this procedure.

## About administering custom menu items

Custom menu items are created through the Main Menu Addition feature which is located in the System Setup screen from the Web Client or the CMS ASCII interface.

These menu items cannot be created through the PC Client.

The custom menu items display on the CMS Main Menu which is seen through either Terminal Emulator, a telnet session to the CMS server, or the CMS console. The custom menu items do not display in the CMS Supervisor user interface.

## Viewing custom menu items using the Web Client Procedure

Navigate to Administration > System Setup > Main Menu Addition.

CMS Supervisor displays the Main Menu Addition window.

## Adding custom menu items using the Web Client

#### Procedure

1. Navigate to Administration > System Setup > Main Menu Addition.

CMS Supervisor displays the Main Menu Addition window.

#### 2. Click Add Main Menu Addition.

CMS Supervisor displays the Add Main Menu Addition window.

- 3. Administer the following options:
  - In Menu Item Name, enter the name for the menu item being added.
  - In **Description**, enter a purpose for the menu item.
  - In **Full Path Name**, enter the path to the executable command installed on the CMS server.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

## Modifying custom menu items using the Web Client Procedure

1. Navigate to Administration > System Setup > Main Menu Addition.

CMS Supervisor displays the Main Menu Addition window.

2. Click **Modify** for the menu item you want to change.

CMS Supervisor displays the Modify Item window.

- 3. Change any of the following options:
  - In Menu Item Name, enter the name for the menu item being added.
  - In **Description**, enter a purpose for the menu item.
  - In **Full Path Name**, enter the path to the executable command installed on the CMS server.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

## Deleting custom menu items using the Web Client Procedure

1. Navigate to Administration > System Setup > Main Menu Addition.

CMS Supervisor displays the Main Menu Addition window.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

- Click Yes to continue with the change. Click Cancel to cancel the operation.
   CMS Supervisor displays a confirmation message.
- 4. Click OK.

CMS Supervisor displays an updated list of items.

## **About CMS operational states**

CMS can run in two operational states:

- Multi-user mode Any defined user can log on to CMS .
- Single-user mode Only one user can be logged on to the CMS server at a time.

The single-user mode is necessary when changes must be made to the following systems and procedures:

- Change Master ACD
- Administer ACD groups
- Data storage allocation
- Storage intervals
- · Restore specific types of data
- Migrate specific types of data

The CMS State window can be used to select which ACD serves as the master for time synchronization. The time displayed on the Controller window originates from the master ACD.

## Before changing the CMS operational state

The following items should be read and understood before changing the CMS state:

- Viewing data in the Data Storage Allocation, Storage Intervals, and Restore Data windows can be done through both the multi-user and single-user modes.
- To add to or modify configuration settings for the Data Storage Allocation, Storage Intervals, and Restore Data windows requires that the CMS state is set to single-user mode.
- If a log out is performed while CMS is still in the single-user state, at least ten seconds must pass before a logon can be performed.
- When in single-user mode, CMS continues to collect data for all ACDs with the data collection feature enabled.

## Permissions required to change CMS operational states

Depending on the procedure that you want to perform, you need the following permissions:

- To view the CMS state or the master ACD, you must have "read" permission for the CMS System Setup feature.
- To modify the CMS state or the master ACD, you must have "write" permission for the CMS System Setup feature.

## Changing the CMS operational state using the Web Client

#### Procedure

1. Navigate to Administration > System Setup > CMS State.

CMS Supervisor displays the CMS State window.

- 2. Under CMS user mode , select one of the following options:
  - Single-user mode Specifies that the CMS state is being set to single-user mode. When CMS is set to single-user mode, a message box displays to all users indicating that CMS will be brought down in one minute. Users are automatically logged off after one minute.
  - **Multi-user mode** Specifies that the CMS state is being set to allow multiple users to log on to CMS.
- 3. Click Modify to save the change. Click Reset to reset the values of the fields.

If the CMS user mode is set to single-user, all CMS users are notified to log off. If the CMS user mode is set to multi-user, CMS users can again log on to the system.

#### Changing the CMS operational state using the PC Client Procedure

1. From the Controller window, select **Tools** > **System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **CMS State**.
- 3. Click OK.

Supervisor displays the CMS State window.

- 4. Under CMS user mode , select one of the following options:
  - **Single-user mode** Specifies that the CMS state is being set to single-user mode. When CMS is set to single-user mode, a message box displays to all users indicating

that CMS will be brought down in one minute. Users are automatically logged off after one minute.

- **Multi-user mode** Specifies that the CMS state is being set to allow multiple users to log on to CMS.
- 5. After selecting the CMS user mode, select **Actions > Modify** from the menu bar.

If the CMS user mode is set to single-user, all CMS users are notified to log off. If the CMS user mode is set to multi-user, CMS users can again log on to the system.

## Changing the master ACD using the Web Client

#### Before you begin

#### Important:

You must turn data collection off before you change the master ACD.

#### Procedure

1. Navigate to Administration > System Setup > CMS State.

CMS Supervisor displays the CMS State window.

- 2. In the **Master ACD for clock synchronization** field, select the ACD that will serve as the master for the synchronization of time for CMS.
- 3. Click **Modify** to save the change. Click **Reset** to reset the values of the fields.

CMS Supervisor displays the window with the updated values.

## Changing the master ACD using the PC Client

#### Before you begin

#### Important:

You must turn data collection off before you change the master ACD.

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **CMS State**.
- 3. Click OK.

Supervisor displays the CMS State window.

4. In the **Master ACD for clock synchronization** field, select the ACD that will serve as the master for the synchronization of time for CMS.

5. After selecting the master ACD, select **Actions** > **Modify** from the menu bar.

The selected ACD is set as the master for time synchronization and the status bar displays a Successful message.

## About turning data collection on and off

The Data Collection window is used to turn data collection on and off for real ACDs (not pseudo-ACDs). When data collection is turned off, no call center data is recorded during the current interval. Also, reports run to include this time period will not accurately reflect the activities in the call center.

## Before turning data collection on and off

The following items should be read and understood before working with the data collection feature:

- When data collection is turned on, the connection status of the link should be monitored to ensure data is being transferred. Use the Connection Status feature in the Maintenance subsystem to view this information.
- The data collection feature does not apply for pseudo-ACDs as they do not collect data.
- When changing the data collection status, each ACD must be administered separately.
- Data collection must be disabled when making changes to the following features:
  - Data Storage Allocation
  - Storage Intervals
  - Change Master ACD
  - Restore specific types of data
  - Migrate specific types of data

Viewing data through the features listed above can be done with data collection enabled.

- Data collection must be turned on for the current ACD in order to activate an agent trace or do any switch administration from CMS.
- When data collection is turned off, no new data is collected. If calls are in the system, the data they generate is not recorded in CMS. If data collection is to be turned off, it is best to wait for the current interval to be archived so that data loss is minimized.

## Permissions required to turn data collection on and off

Depending on the procedure that you want to do, you need the following permissions:

- To view Data Collection settings, you must have "read" permission for the CMS System Setup feature.
- To modify the Data Collection settings, you must have "write" permission for the CMS System Setup feature.

## Turning data collection on and off using the Web Client Procedure

1. Navigate to Administration > System Setup > Data Collection.

CMS Supervisor displays the Data Collection window.

- Click Modify for the ACD you want to turn data collection on or off.
   CMS Supervisor displays the Modify Item window.
- 3. In the Data Collection drop-down list, select either On or Off.
- Click **OK** to commit the operation. Click **Cancel** to cancel the operation. CMS Supervisor displays a confirmation message.
- 5. Click OK.

CMS Supervisor displays an updated list of items.

## Turning data collection on and off using the PC Client Procedure

- From the Controller window, select **Tools** > **System Setup**.
   CMS Supervisor displays the System Setup window.
- 2. In the **Operations** list, highlight **Data Collection**.
- 3. Click **OK**.

Supervisor displays the Data Collection window.

- 4. In the ACD field, select the ACD which will have data collection turned on or off.
- 5. Under **Data Collection**, select one of the following options:
  - On Enables data collection for the selected ACD.
  - Off Disables data collection for the selected ACD.

## About running data summarizing

Data is automatically archived based on the entries in the Storage Intervals window. Data Summarizing is used to manually archive data in the daily, weekly, and monthly tables of the historical database.

## Before running data summarizing

The following items should be read and understood before working with the Data Summarizing window.

#### Important:

Since data is automatically archived based on the entries in the Storage Intervals window, this tool *must not* be used unless an archive failed or did not occur.

- Using the Data Summarizing window causes the archiving to happen immediately.
- Automatic and manual data summarizing include time zone archiving when time zones are administered using System Setup Data Summarization Time Zone.
- Multiple data summarizing requests are queued and are run in the order requested.
- Automatic daily, weekly, and monthly data summaries are queued along with manual requests so that just one type of data summarizing occurs at a time.
- Adequate storage space must be made available through the Data Storage Allocation window before archiving can occur.
- Additional storage space is needed for time zone archiving. The maximum amount of additional storage space is twice the size of the storage space of the ACD without time zone archiving. Each ACD time zone requires twice the necessary storage for that ACD. Each tenant time zone occupies a smaller amount of storage space depending upon the resources that are assigned to that tenant. But this amount does not exceed the size of the storage space for the ACD without time zone archiving.
- You can optionally administer a second time zone for an ACD. For that second time zone, the Free Space Allocation feature automatically accounts for the second time zone. This is also true with tenancy. For more information, see About time zone archiving with additional time zones in *Maintaining and Troubleshooting Avaya Call Management System* and Free Space Allocation on page 341.
- A manual archive cannot be performed unless data exists in the daily, weekly, or monthly tables. If a day of data is missing within the period you are attempting to manually archive, the archive will fail.
- Results of daily, weekly, and monthly archives can be viewed through the Error Log Report or the Archiving Status window.
- If CMS is not operational when an automatic archive should occur, an error message is logged which indicates that a manual archive should be performed using the Data

Summarizing window. If time zone archiving has been administered, the result of each time zone archive is viewable.

- If an incomplete week or month is specified as a date, data summarizing will not occur. Partial weekly or monthly data cannot be summarized. A daily archive can run if the date is not in the future.
- For example, if a week is configured in the Storage Intervals window as being Monday through Friday, entering a date which falls on Saturday in the Data Summarizing window results in the week previous to the date specified being archived.

## Permissions required to run data summarizing

Depending on the procedure that you want to do, you need the following permissions:

- To view the Data Summarizing window, you must have "read" permission for the CMS System Setup feature.
- To use the Data Summarizing window to perform an archive of the system, you must have "write" permission for the CMS System Setup feature.

## Running data summarizing using the Web Client

#### Procedure

1. Navigate to Administration > System Setup > Data Summarizing.

CMS Supervisor displays the Data Summarizing window.

- 2. In the **ACD** drop-down list, select the ACD for which you want to archive data.
- 3. In the **Data type** field, select the appropriate option:
  - **Daily** Archives data for one day. A daily summary archives a partial day. Daily summaries must be complete for each day of the week or month before CMS archives the data for that week or month.
  - Weekly Archives data for one week. A weekly summary must be requested by entering a date that falls within a completed predefined week. See the weekly configuration in the Storage Intervals window.
  - **Monthly** Archives data for one month. Set any day during the month in a completed month for which monthly data should be summarized.
- 4. Click **Run** to start the data archiving. Click **Reset** to clear the option fields.

CMS Supervisor begins archiving data to the historical database tables.

## Running data summarizing using the PC Client

#### Procedure

1. From the Controller window, select **Tools** > **System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **Data Summarizing**.
- 3. Click OK.

Supervisor displays the Data Summarizing window.

- 4. In the ACD field, select the ACD for which you want to archive data.
- 5. In the **Data type** field, select the appropriate option:
  - **Daily** Archives data for one day. A daily summary archives a partial day. Daily summaries must be complete for each day of the week or month before CMS archives the data for that week or month.
  - Weekly Archives data for one week. A weekly summary must be requested by entering a date that falls within a completed predefined week. See the weekly configuration in the Storage Intervals window.
  - **Monthly** Archives data for one month. Set any day during the month in a completed month for which monthly data should be summarized.
- 6. From the menu bar, select **Actions** > **Run**.

Supervisor displays a warning message stating that data archiving is a lengthy process and cannot be cancelled. Through this window, it is possible to cancel the data archive, otherwise the process continues when the message box is dismissed.

Archiver started displays on the status line for the first request and Archiver request submitted displays if a data summary is currently in progress.

# Administering a data summarization time zone using the Web Client

#### About this task

To allow for alternative time zone reporting for daily, weekly, and monthly data, a second time zone can be defined to archive the data. This second time zone is in addition to the default ACD time zone, Doing this results in aggregating the data for two different time zones. Each time zone is aggregated based on the boundary of a day for the selected time zone. You can choose one time zone from the possible 600+ time zones to use as the second time zone for an ACD.

If tenant partitioning is installed, the user can define a time zone for each tenant within an ACD and choose from those time zones to have the data additionally aggregated. This results in storing the data in up to three different time zones. With the multi-tenancy feature installed, one time zone per tenant and one additional time zone for the ACD are supported.

In addition, the agent trace and exception data will be stored in UTC/GMT time enabling filtering and reporting of agent trace and exception data based on the time zone selected on CMS Supervisor.

#### 😵 Note:

The administration of time zones does not automatically create the time zone data in the daily, weekly, and monthly tables. The Archiver must run after the time zone is administered.

#### Before you begin

Change the system to single-user state before you do this task.

#### Procedure

1. Navigate to Administration > System Setup > Data Summarization Time Zone.

CMS Supervisor displays the Data Summarization Time Zone window.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to change the data summarization time zone.
- 3. Click Add Data Summarization Time Zone.

CMS Supervisor displays the Add Data Summarization Time Zone window.

- 4. Select the time zone to be used for this ACD.
- 5. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

6. Click OK.

CMS Supervisor displays an updated list of items.

# Administering a data summarization time zone using the PC Client

#### About this task

To allow for alternative time zone reporting for daily, weekly, and monthly data, a second time zone can be defined to archive the data. This second time zone is in addition to the default ACD time zone, Doing this results in aggregating the data for two different time zones. Each time zone is aggregated based on the boundary of a day for the selected time zone. You can choose one time zone from the possible 600+ time zones to use as the second time zone for an ACD.

If tenant partitioning is installed, the user can define a time zone for each tenant within an ACD and choose from those time zones to have the data additionally aggregated. This results in storing the data in up to three different time zones. With the multi-tenancy feature installed, one time zone per tenant and one additional time zone for the ACD are supported.

In addition, the agent trace and exception data will be stored in UTC/GMT time enabling filtering and reporting of agent trace and exception data based on the time zone selected on CMS Supervisor.

#### 😵 Note:

The administration of time zones does not automatically create the time zone data in the daily, weekly, and monthly tables. The Archiver must run after the time zone is administered.

#### Before you begin

Change the system to single-user state before you do this task.

#### Procedure

- 1. From the Controller window, select **Tools > System Setup**.
- 2. In the CMS System Setup window, select **Data Summarization Time Zone** in the **Operations** list.
- 3. In the System Setup Data Summarization Time Zone window, do any of the following operations as explained in the table below:

#### Note:

The System Setup Data Summarization Time Zone window displays the tenant option only if the customer has installed the tenancy feature.

Field	Description
Add	Adds the entry for the selected time zone and the associated ACD and tenant (if the tenancy feature is installed) in the current user window to the database. If an entry already exists, the system displays Already exists on the window status line.
Delete	Removes the entry for the selected time zone and the associated ACD and tenant (if the tenancy feature is installed) in the current window from the database. If the database entry does not exist, the system displays Does not exist on the status line.
Find one	Finds an entry in the database that matches the time zone and associated ACD and tenant (if the tenant feature is installed) in the current window. The status line for the current window indicates the total number of matches found.
List all	Lists all the ACDs, tenants and tenant users (if the tenancy feature is installed), and the time zones in the database that match with the values entered in the fields of the current user window.
Next	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the next match.
Previous	After doing a <b>Find one</b> search resulting in more than one match, this selection displays the previous match.

## **About External Application Status**

The External Application Status feature, a separately purchased option for CMS, sends real-time data to an external device or to an external program.

#### 😵 Note:

External Application Status feature administration is only available from the PC Client.

The types of external devices or programs used with the External Application Status feature can consist of the following:

- A wallboard This is a large display placed in a call center where all agents can view data. This data can consist of the number of calls in the queue, calls being handled by different splits/skills, and other information.
- An employee scheduler program This third-party software is used to compare the start and end times for agents with schedules created by management.
- A call center data consolidation program This third-party software is used to collect data from all call centers for reporting purposes.

## **Before using External Application Status**

The following items should be read and understood before working with the External Application Status feature:

• In the United States, external applications are designed and administered by the Avaya Professional Services Organization. For more information about external applications, call Avaya Contact Center CRM Solutions at 1-877-927-6662. For assistance outside the United States, contact your local Avaya distributor or representative.

## **Permissions for External Application Status**

Depending on the procedure that you want to perform, you need the following permissions:

- To view External Application Status data, the user ID used to log in to this Supervisor session requires "read" permission for the CMS System Setup feature.
- To enable or disable the External Application Status feature, and start or stop external applications, the user ID used to log in to this Supervisor session requires "write" permission for the CMS System Setup feature.

## Enabling or disabling the External Application Status feature

#### About this task

This section provides the procedure for enabling or disabling the External Application Status feature. This feature must be enabled before external applications can be started. Disabling this feature will cause CMS to stop sending data and the external applications cannot be viewed.

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the Operations list, highlight External Application Status.
- 3. Click OK.

Supervisor displays the External Application Status window.

- 4. In the External Application (Select one) group, select the External application feature (turns on/off all applications) option.
- 5. Select the appropriate option from the Application status (Select one) group:
  - Start This option will enable the External Application Status feature.
  - Stop This option will disable the External Application Status feature.
- 6. From the menu bar, select Actions > Modify.

The status bar displays a message indicating if the action succeeded or failed.

## Viewing the states of external applications

#### About this task

This section provides the procedure for viewing the state of one or more external applications through the External Application Status window.

#### Procedure

1. From the Controller window, select **Tools > System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **External Application Status**.
- 3. Click **OK**.

Supervisor displays the External Application Status window.

- 4. In the External Application (Select one) group, select the External application feature (turns on/off all applications) option.
- 5. From the menu bar, select **Actions > List all**.

Supervisor displays a secondary window displaying one or more applications, their names, and the associated states depending on which option was selected in the step above.

The status of an external application can be one of the following:

- Starting A request to start the external application has been made.
- Running The external application has started and is still running after ten seconds.
- Stopping A request to stop the external application has been made.
- Stopped All processes associated with the external application have stopped.
- Failed The external application has failed repeatedly and is no longer being restarted.

## Starting or stopping external applications

#### About this task

This section provides the procedure for starting and stopping external applications through the External Application Status window.

#### Procedure

1. From the Controller window, select **Tools** > **System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **External Application Status**.
- 3. Click OK.

Supervisor displays the External Application Status window.

- 4. Select the **Application name**: option and enter the name of the application to start or stop in the adjacent field.
- 5. In the **Application status (Select one)**: group, select the appropriate option:
  - Start Supervisor will attempt to start the specified external application.
  - Stop Supervisor will attempt to stop the specified external application.
- 6. From the menu bar, select **Actions > Modify**.

Supervisor attempts to carry out the specified action. The status bar displays the results of the action.

The information that displays in the status bar after this step can consist of the following.

- Starting A request to start the external application has been made.
- Running The external application has started and is still running after ten seconds.
- Stopping A request to stop the external application has been made.
- Stopped All processes associated with the external application have stopped.

• Failed - The external application has failed repeatedly and is no longer being restarted.

## About migrating data

This section provides the procedures and information involved in migrating data from one CMS server onto the database of another CMS server.

## Before migrating data

The following items should be read and understood before migrating data:



Attempting to migrate Agent and Call Center Administration data more than once might cause serious errors from which recovery is difficult. Performing the migration of this data a second time can result in the corruption of the password tables. To do a second migration of ACD administration data, do a second setup of the CMS software.

- To migrate System Administration data or Agent and Call Center Administration data, CMS must be in single-user mode.
- Migrations of system administration data cannot be done in phases. Migrating some user IDs at one time and others at a later time result in two separate sets of data. Only one set of data can be used and cannot be migrated into another set.
- When migrating or restoring a non-LDAP user from a maintenance backup, and the "logid" (logon ID) for a user does not exist in /etc/passwd, the user is created as a new logid. That logid requires password administration just as if the user was created as described in <u>About</u> administering users on page 214.

When this happens, the migration and restore logs contain messages similar to the following examples:

- /cms/maint/r3mig/mig.log

INFO: New UNIX user normusr1: name, room and telephone will not be migrated.

- /cms/maint/restore/rest.log

Created UNIX login 'normusr1'.

```
Warning: Name, Telephone, and Room will not be restored for normusr1.
```

## Permissions required to migrate data

To run data migration, you must have "write" permission for CMS System Setup.

## Migrating data using the Web Client

#### About this task

Use this procedure to migrate or merge data created using a previous version of CMS to the database of another CMS server using the same version of the software or a newer version of the software.

#### Before you begin

To migrate System Administration data or Agent and Call Center Administration data, CMS must be in single-user mode. For more information, see <u>About CMS operational states</u> on page 354.

#### Procedure

1. Navigate to Administration > System Setup > Migrate Data.

CMS Supervisor displays the Migrate Data window.

For a definition of the Migrate Data options, see <u>Migrate Data field descriptions</u> on page 370.

- 2. Select the backup device you want to use from the **Device name** drop-down list.
- 3. In the **Data type** group, select one of the following three options:

#### 🛕 Caution:

Attempting to migrate Agent and Call Center Administration data more than once might cause serious errors from which recovery is difficult. Performing the migration of this data a second time can result in the corruption of the password tables. To do a second migration of ACD administration data, do a second setup of the CMS software.

- System Administration data (single user required)
- Agent/Call Center Admin data (single user required)
- · Historical data
- 4. Enter a value in the Stop date field.
- 5. Enter a value in the **Stop time** field.
- 6. In the Specify ACD(s) to migrate group, select one of the following options:
  - All ACDs
  - Single ACD
- 7. Click **Run** to start the migration.

CMS Supervisor begins the migration process. The screen shows the following progress messages:

- The Status field shows which data is being migrated.
- The **Run** button displays a spinning icon, preventing you from clicking it again.

#### 😵 Note:

If you navigate away from the Migrate Data window while the migration is in progress, the migration continues. If you try to navigate back to the Migrate Data window, the system displays the message Cannot get to screen, meaning that the migration is still in progress and you cannot start another migration.

## Migrating data using the PC Client

#### About this task

Use this procedure to migrate or merge data created using a previous version of CMS to the database of another CMS server using the same version of the software or a newer version of the software.

#### Before you begin

To migrate System Administration data or Agent and Call Center Administration data, CMS must be in single-user mode. For more information, see <u>About CMS operational states</u> on page 354.

#### Procedure

1. From the Controller window, select **Tools** > **System Setup**.

CMS Supervisor displays the System Setup window.

- 2. In the **Operations** list, highlight **R3 Migrate Data**.
- 3. Click OK.

Supervisor displays the R3 Migrate Data window.

For a definition of the R3 Migrate Data options, see <u>Migrate Data field descriptions</u> on page 370.

4. Enter a value in the **Device name** field.

To list all devices on the system, select **Actions > List devices**.

5. In the **Data type** group, select one of the following three options:

#### A Caution:

Attempting to migrate Agent and Call Center Administration data more than once might cause serious errors from which recovery is difficult. Performing the migration of this data a second time can result in the corruption of the password tables. To do a second migration of ACD administration data, do a second setup of the CMS software.

• System Administration data (single user required)

- Agent/Call Center Admin data (single user required)
- Historical data
- 6. Enter a value in the **Stop date** field.
- 7. Enter a value in the **Stop time** field.
- 8. In the Specify ACD(s) to migrate group, select one of the following options:
  - All ACDs
  - Single ACD
- 9. From the menu bar, select **Actions** > **Run**. The **Run** menu item appears only if the settings for **Data Collection** and **CMS State** are appropriate for the type of migration selected.

CMS begins the migration process. The Status field reports the progress of the migration.

Name	Description					
Device name	The name of the backup device containing the data					
Data type: System	Migrated data:					
Administration data (single- user required)	Report GEM files (historical)					
acci icquiica,	Report GEM files (real-time)					
	Shortcut settings for CMS					
	CMS users					
	Timetable settings					
	Database items					
	Hypothetical data for the Forecast product					
	• Feature access settings, timetables, schedules, and associated tasks from the User Permissions subsystem					
	Historical and real-time custom reports					
	Menu and interface settings for the CMS terminal interface					
	Printer parameters for the CMS printer					

## **Migrate Data field descriptions**

Table continues...

Name	Description					
Data type: Agent/Call Center	Migrated data:					
Admin data (single user required)	ACD profiles - VDN profiles					
	<ul> <li>Agent trace - agents being traced, trace data</li> </ul>					
	Agents - shifts, groups					
	Dictionary - synonyms					
	<ul> <li>Exceptions - agent admin, link data, malicious call trace, split admin, splits, split profile, trunk group admin, VDN admin, vector admin</li> </ul>					
	<ul> <li>User permissions - ACD access, split/skill access, trunk groups access, VDN access, vector access</li> </ul>					
	<ul> <li>Forecast - current day report, current day configuration, call handling profiles, costs profiles, data storage allocation, special day admin, manager status, trunk group profiles</li> </ul>					
Data type: Historical data	Migrated data:					
	• Exceptions - agent data, split access, trunk groups, trunk group access, VDN data, vector data					
	<ul> <li>Historical reports - agent activity, agent login/logout, daily agent data, daily call work codes data, daily splits data, daily trunk groups data, daily trunk groups data, daily trunks data, daily VDN data, daily vector data, intrahour agent data, intrahour agent login-logout data, intrahour call work code data, intrahour split data, intrahour trunk group data, intrahour trunk data, intrahour VDN data, intrahour vector data, monthly agent data, monthly call work code data, monthly split data, monthly trunk group data, monthly trunk data, monthly VDN data, monthly vector data, weekly agent data, weekly call work code data, weekly split data, weekly trunk group data, weekly trunk data, weekly VDN data, weekly vector data</li> </ul>					
	<ul> <li>Forecast - daily split data, daily trunk group data, special day split data, interval split data, interval trunk group data</li> </ul>					
Stop date	The date through which you wish to record data for migration to the new CMS . The migration process does not migrate data collected after the date specified.					
Stop time	The time through which you wish to record data for migration to the new CMS . The migration process does not migrate data collected after the stop date and time specified.					
	If this field is left blank, the stop time defaults to 23:59.					
Specify ACD(s) to migrate: All ACDs	Data is migrated from the backup device to the hard disk on an ACD-by-ACD basis. Data for ACD1 on the backup device is used for ACD1 on the new CMS .					
	Table continues					

Table continues...

Name	Description
Specify ACD(s) to migrate: Single ACD	Historical data is migrated from the backup device to the hard disk for the ACDs specified in the <b>from</b> and <b>To</b> fields.
	For example, to migrate data from ACD1 on the backup device to ACD4 on the new CMS , place 1 in the <b>from</b> field, and 4 in the <b>To</b> field.

## **Chapter 11: Maintaining CMS**

## **About maintaining CMS**

Maintaining a CMS server consists of routine tasks such as backing up data, checking the status of the CMS connection to the switch, and viewing the maintenance error log.

#### 😵 Note:

Some CMS maintenance operations are done using the **cmsadm** or **cmssvc** commands, and some are available only when using the CMS Supervisor interface.

This chapter describes how to do the following tasks:

- · Reboot your CMS server regularly
- · Back up your data
- · Restore your data
- · Administer backup and restore devices
- · Administer printer names and options
- · Administer report properties
- · Monitor the data connection between the CMS server and the switch
- · View the measurement status of an ACD
- View the status of archiving
- · View the status of a firewall if administered
- · View the status of feature licensing
- Administer LDAP integration

#### Before using the Maintenance window

If an ACD Group is selected as the current ACD in the Maintenance window, only those operations that are valid for the ACD Group appears in the **Operations** list.

## **Rebooting your CMS server regularly**

Avaya recommends that you reboot your CMS server once every three months for preventative maintenance reasons. Rebooting your CMS server should not take longer than 10 minutes and should be done when the CMS server load is low.

Although rebooting your CMS server is not a requirement, periodically rebooting your CMS server is a recommended procedure targeted at minimizing the risk of a system failure. Rebooting your CMS server lessens the possibility of your system being adversely impacted by anomalies such as memory leaks, packet loss, unreleased file locks, data inconsistency, data corruption, and storage space fragmentation. These types of problems are known to occur in any computer system.

CMS has a High Availability (HA) solution if data loss from a server reboot is a concern. The CMS HA solution provides an uninterrupted data stream between the communication server and two CMS servers. If you use the HA solution, reboot each CMS server at a different time to prevent data loss.

Avaya support personnel who are doing system maintenance work may require you to reboot your CMS server. If Avaya support personnel require you to reboot your CMS server, they work with you to determine the best time to perform the reboot. Avaya support personnel attempts to determine the root cause of any problem that might require a reboot.

## About backing up data

There are two types of data backup available for CMS:

- CMSADM backup
- Maintenance backup

#### ▲ Caution:

If you do not do regular backups of your data and you have a system failure, data is lost and cannot be recovered. More frequent backups increase your chances of not losing data. It is up to you to determine how much data loss you can tolerate if you choose not to back up your data more frequently.

CMS supports backups to multiple backup devices. You cannot run simultaneous backups of any type, even if multiple backup device types are administered.

CMS can back up data and restore data while the data collection remains on. Backups help minimize data loss. However, once a CMSADM backup starts, new log on attempts using CMS Supervisor or the ASCII interface are blocked.

You must do CMSADM backups to save CMS data, such as the OS and CMS programs. Avaya recommends that you do CMSADM backups:

· After the CMS is provisioned

• After the CMS software is upgraded

CMS maintenance backups only save CMS data (administration and historical) and the CMS data for each ACD. You can do maintenance backups using CMS Supervisor. Avaya recommends that you do full maintenance backups weekly and incremental maintenance backups daily.

A maintenance restore of CMS System Administration data or ACD Administration data requires Avaya CMS to be in single-user mode.

The CMS LAN Backup feature is not available using CMS Supervisor. For more information about LAN Backup, see *Using Avaya Call Management System LAN Backup*.

## About CMSADM backups

The CMSADM backup saves all of the system data on the computer onto a tape or other device such as a USB drive or a network drive.

A CMSADM backup backs up the following data:

- · Operating system files and programs
- · CMS programs
- · Non-CMS customer data placed on the computer

#### ▲ Caution:

If you do not do regular backups of your data and you have a system failure, data is lost and cannot be recovered. More frequent backups increase your chances of not losing data. It is up to you to determine how much data loss you can tolerate if you choose not to back up your data more frequently.

The CMSADM backup does not save CMS database tables. For complete data recovery, both CMSADM and maintenance backups are required.

A CMSADM backup is done using special CMS commands using the Linux user interface. You cannot do a CMSADM backup using CMS Supervisor.

#### About maintenance backups

Maintenance backups are used to back up and restore CMS data, including database tables that are not backed up using the CMSADM backup.

#### ▲ Caution:

If you do not do regular backups of your data and you have a system failure, data is lost and cannot be recovered. More frequent backups increase your chances of not losing data. It is up to you to determine how much data loss you can tolerate if you choose not to back up your data more frequently.

To do a maintenance backup, you use the CMS Supervisor Maintenance window. You can do full and incremental backups of CMS historical and administration data.

## Tape drives and cartridges

The following table lists the models of tape drives that are supported.

Tape drive	Tape description
DAT 72	DDS compliant 170 meter 36/
	72-GB DAT cartridge 4 mm
LTO-4	820 meter 800 GB LTO cartridge 12.65 mm

## USB/network backup/restore devices

The screen containing Backup/Restore Devices now displays **Tape** and **Other** options to the user under the **Device name** field. The **Other** option may be either a USB storage device or network device, and does not include any location on the CMS disk itself. If the device chosen for a CMS Maintenance Backup is of type **Other**, the backup file is named using the tape label convention. This file is a compressed file. The CMSADM backup can also be performed on the USB or network devices. The backup file generated by CMSADM backup is labeled with a unique label that includes date, time, and machine name, and is not compressed.

## Considerations when backing up or restoring data

Avaya recommends that you back up your CMS system data monthly and you back up your CMS ACD data daily. If you are using tape, the backup tapes should be stored in a safe location, easily retrievable, correctly labeled, and replaced when worn out. Running system backups is not service affecting, but the backups impact the performance of the CMS system. It is recommended that you run backups when CMS system activity is low.

#### ▲ Caution:

If you do not do regular backups of your data and you have a system failure, data is lost and cannot be recovered. More frequent backups increase your chances of not losing data. It is up to you to determine how much data loss you can tolerate if you choose not to back up your data more frequently.

#### Note:

The **Maintenance** > **Restore** Data option is only used when the CMS version on the backup media is the same as the CMS version installed on the system. If the CMS versions are different then the data needs to be migrated using the **System Setup** > **R3 Migrate Data** option.

For example, if the CMS version on the backup media is r17ab.g and the CMS version installed on the system is r17ab.g then the data can be restored. If the CMS version on the backup media is r17ab.c and the CMS version installed on the system is r17ab.g then the data must be migrated.

This section presents several factors that impact the time it takes to back up or restore your data and presents options to reduce backup and restore times.

#### Factors that impact backup and restore times

The amount of time it takes to back up or restore data depends on the:

- Amount of data An increase in the amount of data causes an increase in the amount of time it takes to back up or restore the data. Some factors that increase the amount of data being stored are:
  - Number of items being measured More data is generated if you measure 100,000 agent skill pairs instead of 10,000.
  - Number of days information is stored The greater the data storage time, the greater the amount of data to be backed up or restored. When the CMS system reaches a predetermined threshold for data storage, the system deletes the oldest record to accommodate the newest record. You can store the data for 370 days.
  - Interval size Shorter intervals generate more data. A 15-minute interval generates significantly more data than a 60-minute interval.
- System load Processes that require a large number of system resources slow down the CMS system. Backing up data requires a large amount of system resources. Additional processes that require a large amount of system resources are:
  - Running reports Running a single large report or multiple smaller reports use a large amount of system resources.
  - Archiving data Archiving a large amount of data uses a large amount of system resources.
- Necessity for manually changing backup tapes If the amount of data exceeds the capacity of a single backup tape, someone must monitor the system and manually load additional tapes. A data backup or restore does not finish unless someone can load tapes into the tape device as needed.
- The device you are backing up to. If you are backing up to a USB storage device or a network mounted directory, the backup times is longer than the LTO tape device. You may want to consider a backup strategy of the following type:
  - Performing full backups only once a week
  - Performing incremental backups on three or four other days of the week

For example, you might want to perform your full backup on Saturday nights, and your incremental backups on Mondays, Wednesdays, and Fridays.

#### Reducing tape backup and restore times

If you do not take steps to optimize your CMS backup and restore times, you begin to experience performance issues. Your CMS system performance drops if the backup continues to run when

call center activity increases. With the increased CMS capacities that are now available, CMS backups and restores could take much longer to complete than they have in the past.

Due to the higher capacity limits and fewer database restrictions, the maintenance backup time can take longer with each new CMS release. In some cases, the extended amount of time might be unacceptable to customers. In rare extreme cases, maintenance backups could take more than 24 hours.

To reduce the amount of time it takes to backup or restore data, you can:

- Select the maximum interval time that meets your data collection needs.
- Select the minimum data storage times that meets your data collection needs for all the historical database tables.
- Run reports when the CMS system is not actively backing up or restoring data.
- Schedule each ACD to back up at a different time.
- Schedule routine backups to occur at a time that is different from data archiving.
- Schedule routine backups to occur when CMS system activity is low.
- Use binary backup.
- Reduce the amount of data being stored so only one backup tape is needed to store the data.
- Upgrade your CMS system to a more powerful hardware platform or add additional memory and CPUs.

#### Alternate methods for backing up and restoring data

#### LAN Backup

If you need a higher capacity process for backing up and restoring your data, you may want to use the CMS LAN Backup feature. The CMS LAN Backup feature provides an alternative to the traditional method of backing up and restoring data, which requires you to manage your tape library, your USB storage device(s), or your network file space. LAN Backup allows you to back up CMS data and system information over a local area network (LAN) to a storage manager, which manages the number of backups and their location. CMS supports the use of Tivoli Storage Manager and Symantec Netbackup storage managers.

The Using Avaya Call Management System LAN Backup provides information about using the CMS LAN backup feature, hardware requirements, software requirements, and support guidelines.

#### **Binary Backup**

To speed up the time it takes to run a backup, you can use the binary backup feature. The CMS binary backup procedure can write data to a tape drive, a USB storage device, or over the network. Similar to the LAN backup and restore processes, the binary backup does not support table level restore and data migration. A binary backup is a good alternative for disaster recovery. In general, a binary backup to a tape device or a USB storage device, of a fully-loaded CMS system takes approximately 30 minutes. A binary backup over a network varies depending upon the network bandwidth.

## Determining the duration of a typical CMS full maintenance backup to tape

#### About this task

To determine the duration to do a full maintenance backup to tape, you must determine the amount of used disk space on the system.

#### Procedure

1. Log on to the CMS server as a root user.

#### Important:

You cannot directly log on as root from a remote connection. You must log on using an administered CMS user ID, then use **su** - **root** to log on with root privileges.

- 2. Run cms > System Setup > Free Space Allocation.
- 3. Refer to the Space Used to Date column for each ACD that appears on the screen.
- 4. Sum the total space used for all ACDs (shown in kilobytes).
- 5. Divide the total space used by 1000 (approximate speed of backup to tape), then by 3600 (seconds in an hour).

#### Example

For example, if the total space used is 10,000,000 kilobytes (10 million kilobytes), use the calculation:

#### 1000000/1000/3600

This equals 2.78, or about 3 hours, which is the number of hours that a full maintenance backup to tape takes for all ACDs on the system. You can use this calculation on each ACD to determine the time to back up a single ACD.

#### Restoring or Migrating from a non-tape device

When your backup device is of type **Other**, it means that you have specified either a USB storage device or a network mount point as your chosen location for maintenance backups. It is your responsibility to manage this storage area. You must keep enough free space in your chosen "Other" device to allow for scheduled maintenance backups. This means that you must periodically check the network mount point or the USB storage device for available space, and remove older backup files to allow for more storage. If you do not wish to manage the non-tape storage area, you should consider the LAN Backup feature described above. If you are using a network directory, ensure that you include this directory in the system backups of your company's non-CMS servers.

You should keep in mind the following recommendations for the maintenance of your "Other" storage area:

 Do not store CMSADM backup files and Maintenance backup files on the same USB storage device or in the same network mount point. Keep a separate set of USB storage devices for your CMSADM backups (at least two), or create separate network directories for your CMSADM backups with adequate storage for at least two backups.

- Do not store more than one full Maintenance backup and 6 incremental backups on one USB storage device.
- Keep at least two full Maintenance backups and the accompanying week's worth of incremental backups on two separate USB storage devices. If you are using a network directory, allow enough storage for at least two full Maintenance backups and the accompanying week's worth of incremental backups. If you are backing up multiple servers, increase the storage accordingly.

When performing a Maintenance restore, if you check the **Restore from the latest backup?** box, the logic used to determine the latest backup is as follows:

- The backup file labeled with the latest full backup for the given server
- The backup file labeled with the next latest full backup if the latest cannot be found
- If no full backups can be located for the given server, the latest incremental backup is looked for

#### 😵 Note:

All the above steps are relative to the "Other" device location (USB storage device or network mount point).

You may wish to control which backup file is used for a restore or a migration. This is similar to mounting your chosen tape and performing the restore or migrate from that tape. If you wish to control which backup file is used for a restore, follow the steps below:

• On your "Other" storage device, create a file named restore\_list, which contains the names of the files you wish to restore from. These files must be ordered in the restore list beginning with the first backup you wish to restore from, to the last backup. For example, if your CMS maintenance backups on server "finch" begin on October 4, 2010 with a full backup and are followed by an incremental backup on October 6, October 8, and October 10, you would see the following files in your backup storage area or on your USB storage device by using the following command:

#### ls -rt \*finch\*

CMS-101004-02-LSAC-00-F-01-05-finch000000000 CMS-101006-02-LSAC-00-I-01-05-finch000000000 CMS-101008-02-LSAC-00-I-01-05-finch000000000 CMS-101010-02-LSAC-00-I-01-05-finch000000000

• To create a list of these file names in a file named " restore\_list ", run the following command:

ls -rt \*finch\* > restore\_list

 Once the restore list is created, you may begin your Maintenance restore. Do not check the Restore from the latest backup? box so that "restore\_list" is used. As each of the backups is restored, it is removed from the list. When you have restored all backups, you may choose Stop to end the restore.

## About doing a CMSADM backup

The CMSADM backup should be done at the following times:

- Once a month (This is always the customer's responsibility.)
- After the CMS is provisioned (If using tape, never use the original tapes made during provisioning.)
- Before and after the CMS software is upgraded
- After the system has been set up in the factory (performed by factory personnel).

This backup contains the default factory configuration. These tapes should be saved if the system must be reinstalled in the field.

😵 Note:

The factory will no longer provide a CMSADM backup as of R17.0.

Important:

If you are backing up to tape, use a new set of backup tapes for the monthly CMSADM backup. Do NOT use the original sets of factory backup tapes or provisioning backup tapes. Make sure that there are enough tapes for the new backup.

#### Before doing a CMSADM backup

The following items should be read and understood before starting a CMSADM backup:

- Before running a CMSADM backup, you should restart the CMS server.
- If you choose tape as your backup device, verify that you are using the correct tape for the tape drive on your system.
- If you choose a USB storage device as your backup device, verify that you are using a recommended USB device.
- Backup tapes and USB storage devices can wear out. Be sure to refresh your supply of backup devices at appropriate intervals.

#### Permissions required to do a CMSADM backup

To do a CMSADM backup, you must have "write" permission for the operating system subsystem. Only employees with administrative responsibilities should be given permissions and passwords.

#### Calculating data space requirements for CMSADM backups

#### Procedure

1. Log on as root to Linux.

#### Important:

You cannot directly log on as root from a remote connection. You must log on using an administered CMS user ID, then use **su** - **root** to log on with root privileges.

2. Run the following command:

df -Th

The system displays information similar to the following example:

Filesystem	Туре	Size	Used	Avail	Use%	Mounted on
devtmpfs	devtmpfs	7.8G	0	7.8G		/dev
tmpfs	tmpfs	7.8G	Ő	7.8G		/dev/shm
-	-					
tmpfs	tmpfs	7.8G	113M	7.7G	28	/run
tmpfs	tmpfs	7.8G	0	7.8G	0 %	/sys/fs/cgroup
/dev/sda2	ext4	9.8G	1.6G	7.7G	18%	/
/dev/sda1	ext4	546M	106M	400M	21%	/boot
/dev/sda6	ext4	87G	2.7G	80G	4%	/storage
/dev/sda9	ext4	16G	45M	15G	1%	/tmp
/dev/sda8	ext4	26G	240M	24G	1%	/var
/dev/dm-0	ext4	32G	49M	30G	1%	/export/home
/dev/dm-1	ext4	12G	1.8G	9.3G	16%	/opt
/dev/dm-2	ext4	9.8G	354M	8.9G	4%	/cms
tmpfs	tmpfs	1.6G	0	1.6G	0%	/run/user/0
cms-store:/store	nfs4	2.2T	1.5T	554G	74%	/nfsbu

3. Add the disk space from the Used column for all of the ext4 filesystems, except for the / storage or /tmp directories.

In this example, that would include the following directories:

- /
- /boot
- /var
- /export/home
- /opt
- /cms
- 4. Calculate the space you need, for example:

Directory	Used space
/	1.6 GB
/boot	106 MB
/var	240 MB
/export/home	49 MB
/opt	1.8 GB
/cms	354 MB
TOTAL	4.15 GB

#### 😵 Note:

The df -Th command gives a current snapshot of disk space usage of the CMS server. You must run additional checks periodically to see if your storage needs have changed to ensure you have enough backup space.

#### Doing a CMSADM backup

#### Procedure

1. Log in to the CMS system as root and open a terminal window.

See Logging in to CMS from the server console on page 495 for additional information.

- 2. Verify that the operating system of the computer is in a multi-user state (2 or 3). To check if you are in the multi-user state, enter who -r
- 3. Enter cmsadm and press the Enter key:

The Avaya Call Management System Administration Menu is displayed.

4. Enter the number associated with the backup option.

```
Choose a backup device:
1) Tape
2) Other
Enter choice (1-2):
```

Depending upon your preferences, choose your backup device. If you choose Tape, continue with step 5. If you choose Other, continue with step 9.

5. Press the Enter key.

The backup process begins.

If more than one tape is required, the program displays the following message:

```
End of medium on "output".
Please remove the current tape, number it,
insert tape number x, and press Enter
```

If you receive the message displayed above, insert the next tape and allow it to rewind. When it is properly positioned, press the Enter key.

- 6. When the backup is completed, the system displays information according to the number of tapes that are required for the backup:
  - If the number of tapes required is one, the system displays the following message:

```
xxxxxx blocks
Tape Verification
xxxxxx blocks
WARNING: A CMS Full Maintenance Backup in addition to this cmsadm
backup
must be done to have a complete backup of the system. . . .
Please label the backup tape(s) with the date and the current CMS
version
(Rxxxxx.x)
```

• If the number of tapes required is more than one, the system displays the following message:

```
xxxxxx blocks
Tape Verification
Insert the first tape
Press Return to proceed :
```

If you receive the message displayed above, insert the first tape used in the backup and press the Enter key. Wait for the tape drive light-emitting diode (LED) to stop blinking before you remove the tape. When prompted, repeat this process for any additional tapes generated by the backup process.

When the final tape is verified, CMS displays the following message:

```
xxxxxx blocks
Tape Verification
xxxxxx blocks
WARNING: A CMS Full Maintenance Backup in addition to this cmsadm backup
must be done to have a complete backup of the system. . . .
Please label the backup tape(s) with the date and the current CMS version
(Rxxxxx.x)
```

- 7. Label all tapes with the following information:
  - Tape number
  - · Date of backup
  - Current version of Avaya CMS
- 8. Set the tape write-protect switch to read-only and put the tapes in a safe location.

If you have problems performing a CMSADM backup to tape, see the document, *Maintaining and Troubleshooting Avaya Call Management System*.

The system displays the following message:

Enter backup path (must not be located on CMS disk):

9. Enter the directory of the network mounted file system that you wish to use for your backup, or the mount point of your USB storage device, and press the Enter key.

If the directory is accessible for the backup, CMS displays the following message:

Using file /sss/CMSADM-<CMS load name>-<date-time>-<machine name>

After the backup has been written, it is verified, and CMS displays the following message:

```
xxxxxx blocks
Backup Verification
xxxxxx blocks
WARNING: A CMS Full Maintenance Backup in addition to this cmsadm backup
must be done to have a complete backup of the system. . . .
Backup file is located at /xxx/CMSADM-<CMS load name>-<date-time>-<machine name>
```

## About doing a maintenance backup

Since new data is written every day of operation, you should frequently back up this data. Both the full and incremental backups can be scheduled to run automatically on a timetable when using the PC Client.

#### Before doing a maintenance backup

The following items should be read and understood before doing a maintenance backup:

- If you back up to tape, a sufficient supply of tapes should be available so that tapes can be rotated. One common plan is to keep seven tapes in stock and recycle them daily. A new tape is used each day of the week, and each week the sequence is repeated.
- Backups run in the background. You can exit the Backup Data window without affecting the backup.
- Running backups during archiving may cause performance problems. For best performance, run backups either before or after the archiving process.
- Currently supported tape drives can accommodate a full backup on one tape. Incremental backups may not be required. Full backups can be scheduled to run every day using the PC Client.

#### Important:

The maintenance backup does not back up the CMS software, operating system files or non- CMS customer data on the system. For complete data recovery, both CMSADM and maintenance backups are required. See <u>About doing a CMSADM backup</u> on page 381 for instructions on how to run a CMSADM backup.

#### Permissions required to do a maintenance backup

To run a maintenance backup, you must have "write" permission to the Maintenance subsystem.

#### Calculating data space requirements for CMS full maintenance backups Procedure

1. Log on as root to Linux.

#### Important:

You cannot directly log on as root from a remote connection. You must log on using an administered CMS user ID, then use su - root to log on with root privileges.

- 2. Set the Informix environment by entering the following command:
  - . /opt/informix/bin/setenv
- 3. Run the following command:

onstat -d

#### The system displays information similar to the following example:

IBM Informix Dynamic Server Version 12.10.FC11 -- On-Line -- Up 142 days 18:48:53 -- 8634236 Kbytes

Dbspaces address	number	flac	ıs	fchu	ınk	nchunk	s	pgsize	fl	aqs	0	wner
name 44c10028	1	- N¥40	)30001	1		1		2048	N	BA	i	nformix
rootdbs	1	UAIC	00001	Ŧ		1		2040	IN	DA	±.	IIIOIIIIIX
462e31f8	2	0x40	030001	2		1		2048	Ν	BA	i	nformix
physdbs 462e3438 logdbs	3	0x40	20001	3		1		2048	Ν	BA	i	nformix
462e3678	4	0x40	20001	4		1		8192	Ν	BA	i	nformix
dbtemp 462e38b8 cmsdbs	5	0x40	20001	5		1		8192	Ν	BA	i	nformix
5 active, 2047	maximum											
Chunks												
address pathname	chunk/	dbs	offse	t	siz	e	f	ree	bp	ages		flags
44c10268 B /cmsdisk	1	1	0		128	000	1(	07807				PO-
463dc028 B /cmsdisk	2	2	12800	0	327	680	0					PO-
463dd028	3	3	45568	0	655	36	0					PO-
B /cmsdisk 463de028	4	4	52121	6	655	360	65	55307				PO-
B /cmsdisk 463df028	5	5	31426	56	774	13632	7	7290429				PO-
B /cmsdisk 5 active, 32766	5 maximu	m										

NOTE: The values in the "size" and "free" columns for DBspace chunks are displayed in terms of "pgsize" of the DBspace to which they belong.

Expanded chunk capacity mode: always

4. Use the output generated from running this command and the formulas at the bottom of the following tables to calculate how much database space is required for a CMS full maintenance backup.

The data in this table is dynamic, and changes as database space is used.

Platform	pgsize	Full disk size of cmsdbs Dbspace	Total Disk cmsdbs Dbspace (Bytes)	Total Disk cmsdbs Dbspace (rounded in GB)	Total Full Maintenance Backup space Required if cmsdbs Dbspace is full (GB) <sup>1</sup>
Dell R630	8,192	32,861,440	269,200,916,480	250.71	8.36
Dell R730	8,192	179,072,256	1,466,959,921,152	1,366.21	45.54

Table continues...

<sup>&</sup>lt;sup>1</sup> If ontape is being used for binary backups this value must be multiplied by 30 since ontape does not compress data.

Platform	pgsize	Full disk size of cmsdbs Dbspace	Total Disk cmsdbs Dbspace (Bytes)	Total Disk cmsdbs Dbspace (rounded in GB)	Total Full Maintenance Backup space Required if cmsdbs Dbspace is full (GB) <sup>1</sup>
HP DL380P G9	8,192	179,072,256	1,466,959,921,152	1,366.21	45.54
HP DL20 G9	8,192	43,844,355	359,172,956,160	334.5	11.15

Bytes to GB conversion factor = 1,073,741,824

Full Maintenance Backup compression ratio = 30 (approximation)

#### 😵 Note:

The onstat -d command gives a current snapshot of disk space usage of the CMS server. You must run additional checks periodically to see if your storage needs have changed to ensure you have enough backup space.

#### Example

Dell R630 (300 GB) example:

Db spaces address	numbers	flags	fchunk	nchunks	pgsize	flags	owner	name
c64a5358	5	0x60001	5	1	8192	N B	informix	cmsdbs

Chunks address	chunk	dbs	offset	size	free	bpages	flags	pathname
c64a5ac0	5	5	31,426,56	34,679,882	29,584,364		PO-B-	/cmsdis

Full Dbspace size of cmsdbs = ((8,192 \* 34,679,882) / 1,073,741,824) = 264.59 GB

Full Dbspace size of cmsdbs available for Full maintenance backups = (((8192 \* 34,679,882) / 1,073,741,824) / 30) = 8.82 GB

Space required for backup = (((8,192 \* (34,679,882 - 29,584,364)) / 1,073,741,824) / 30) = 14.01 GB

## Doing a maintenance backup using the Web Client

#### Procedure

#### 1. Navigate to Administration > Maintenance > Back Up Data.

CMS Supervisor displays the Back Up Data window.

For a definition of the Back Up Data options, see <u>Back Up Data field descriptions</u> on page 390.

2. Select the backup device you want to use from the **Device name** drop-down list.

<sup>&</sup>lt;sup>1</sup> If ontape is being used for binary backups this value must be multiplied by 30 since ontape does not compress data.

3. If you are using tape backup, you can select the **Verify tape can be read after backup?** option.

It is recommended that you check the tape backup for readability. When the tape is verified, a message displays in the **Status** field. If the tape cannot be read, a message displays in the **Errors** field. See <u>Common backup and restore error messages</u> on page 391 for information on additional error messages you may receive.

😵 Note:

If your device is a non-tape device (USB storage device or network), the **Verify tape can be read after backup?** check box is ignored. However, you will get a Confirm Modify pop-up when you start the backup. Click **Yes** to continue.

- 4. In the **ACD(s) to back up** field, select one of the following options:
  - The All ACDs option backs up data from all real ACDs (that is, not pseudo-ACDs).
  - The Current ACD option backs up data from the current active ACD.
- 5. The **Data to back up** check boxes, by default, are all selected. If you do not want to back up all data types, clear the types of data you do not want to be backed up.
- 6. Do one of the following:
  - Click **Run** to start the backup.
  - Click Reset to clear all of your options.
  - Click **Cancel** to cancel the backup operation.

If you click **Run**, the backup process begins. The Back Up Data window shows the following progress messages:

- The system displays a Confirm Modify pop-up showing the estimated size of the backup. Click **OK** to continue.
- The Status field shows which data is being backed up.
- The **Run** button displays a spinning icon, preventing you from clicking it again.

#### 😒 Note:

If you navigate away from the Back Up Data window while the backup is in progress, the backup continues. If you try to navigate back to the Back Up Data window, the system displays the message Cannot get to screen, meaning that the backup is still in progress and you cannot start another backup.

If you select "Tape" as your backup device and your backup requires more than one tape, the system prompts you to mount additional tapes to complete the backup.

When the backup process is complete, CMS Supervisor displays an acknowledgment message.

7. When the backup completes, remove and label the tape(s) if your backup device is tape.

## Doing a maintenance backup using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Depending on if you want to back up a single ACD or all ACDs, choose one of the following steps:
  - To back up a single ACD, enter the ACD identification in the **ACD** field.
  - To back up all ACDs, make sure no ACDs are selected in the **ACD** field.
- 4. Select Backup Data in the Operations list.
- 5. Click OK.

Supervisor displays the Backup Data window.

For a definition of the Backup Data options, see <u>Back Up Data field descriptions</u> on page 390.

- 6. In the **Device name** field, verify that the correct backup device is displayed. If you need to select another device, select **List devices** from the **Actions** menu.
- 7. If your device is tape, ensure that the **Verify tape can be read after backup?** check box is selected.

It is recommended that you check the tape backup for readability. When the tape is verified, a message displays in the **Status** field. If the tape cannot be read, a message displays in the **Error name** field. See <u>Common backup and restore error messages</u> on page 391 for information on additional error messages you may receive. If your device is a non-tape device (USB storage device or network), this check box is ignored.

- 8. In the ACD(s) to back up field, select one of the following options:
  - The All ACDs option backs up data from all real ACDs (that is, not pseudo-ACDs).
  - The **Current ACD** option backs up data from the ACD that is displayed in the bottom right corner of the Backup Data window.
- 9. The **Data to back up** check boxes, by default, are all selected. If you do not want to back up all of these data types, clear the types of data you do not want to be backed up.
- 10. From the **Actions** menu, select **Run**.

The backup process begins. When the backup process is complete, CMS Supervisor displays an acknowledgment window.

If you have selected "Tape" as your backup device and your backup requires more than one tape, you receive a message telling you to mount another tape to complete the backup.

11. When the backup completes, remove and label the tape(s) if your backup device is tape.

## Back Up Data field descriptions

Name	Description	
Backups completed today	Shows the number of backups completed for the current day.	
Status	Shows the status of the current or most recent backup and what is currently being backed up.	
Errors	Shows any errors found in the backup.	
Device name	Displays the name of the backup device.	
Verify tape can be read after backup?	Check box to request that the data be reread to ensure that the data has been backed up properly. This check box applies to tape backups only.	
ACD(s) to back up	Options to perform a backup of all ACDs or a single ACD.	
Data to back up	Series of check boxes where you can select the types of data you want to back up.	
Local System administration data	Includes IP addresses, port numbers, and other data configured at installation.	
CMS System administration data	Includes user permissions, feature access permissions, <b>Main Menu</b> additional data, timetable, printer administration, default values, color choices, and custom report definitions (not the data associated with custom reports).	
ACD-specific administration data	Includes Forecast data (if the feature is active), call work code administration data, VDN administration data, data storage allocation data, exception administration data, agent trace data (historical list of agents traced), and ACD-specific Dictionary names.	
Historical data	Includes the historical data stored in the CMS database. There are two options for backing up historical data, Full and Incremental	
	Full: includes data for all the periods in the historical database. You must do a full backup before the first incremental backup. It is recommended that you periodically (for example, once a week) do a full backup of your system.	
	Incremental: includes the CMS data recorded since the last backup (incremental or full) was completed. Only the historical data can be stored incrementally; administration data is stored in full.	
Non-CMS data	Includes all data from Informix tables with names that start with "c_". The table definitions for non- CMS Informix tables are not backed up because a CMSADM backup captures non- CMS Informix tables.	
Specific tables	Allows you to back up data from specific data tables.	
	To back up specific tables, select <b>Actions</b> > <b>Select tables</b> . Supervisor then displays the Backup Data - Select Tables window. The Table name column shows the name of the data table, and the Description column shows the type of data in the table. Select the check boxes for the tables you want to back up. Close the window when finished.	

#### Common backup and restore error messages

Common error messages and their solutions are described as follows.

#### CMS cannot access the specified device

#### Solution

Enter a new device name.

#### The volume mounted is bad (corrupt)

#### Solution

If the mounted volume is corrupt, mount a new volume.

#### A volume tape is not mounted in the drive

#### Solution

Mount a volume.

#### The volume mounted contains CMS data that you might not want to overwrite

#### Solution

Mount a different volume if you do not want to overwrite the data on the volume in the drive.

#### The volume mounted is the last backup volume

#### Solution

Mount a different volume. CMS does not let you overwrite your last backup.

#### The volume mounted has errors

#### Solution

Mount another volume.

#### A table cannot be backed up

#### Solution

You must either skip the table and continue or cancel the backup.

#### Labeling the backup volume

After a successful backup, CMS generates backup volume labels depending on the rules that apply to the particular backup device being used. This is "Tape" or "Other" in the new CMS systems.

Depending on the circumstances, CMS provides the following information:

- An acknowledgment window displays the final backup information. If the backup was scheduled on a timetable, the information is recorded in the Maintenance Error Log.
- An acknowledgment window displays a message indicating when a backup can write to a previously used tape.

#### Example backup information format and interpretation

0001	CMS-	NNNNN	N-NN-	-LLL]	L-NN	-L-	-NN	J
0002	1		1					
0003	1	2	3	4	5	6	7	

The following table provides information on the labels of backup tapes.

Part #	Code	Meaning	
1	CMS	System name	
2	NNNNN	Year, month, and day of the backup (yymmdd)	
3	NN	Number of backups for this day	
4	LLLL	Type of data backed up:	
		A - ACD-specific administration data and historical data	
		C - custom data	
		H - historical data	
		L - local system administration data	
		M - ACD-specific administration data	
		S - CMS system data	
		X - no backup	
5	NN	Number of the ACD (00 means All ACDs were selected on the	
		Backup Data window)	
6	L	Backup mode (F for Full, I for Incremental)	
7	NN	The tape number if this tape was part of a multi-tape backup.	

If the device type is "Other", the file name for Maintenance backup has the same format as the tape label. For example, if you have performed a full Maintenance backup on your CMS server named sapsucker for all ACDs and all data types on September 18, 2020, the file name appears in the directory as CMS-200918-01-LSAC-00-F-01.

#### **Recovery kit**

The recovery kit is composed of the backup media that the Avaya services organization needs to restore service to your system if major problems occur. This kit should be stored in a secure location to minimize the time your system is out of service.

#### **Recovery kit contents**

The Recovery Kit contains the most recent:

- CMSADM backup tape (if your chosen backup device is tape)
- Full Maintenance backup tape and any Incremental backup tapes since the latest full backup (if your chosen backup device is tape)
- CMS Load DVD
- Patching DVDs

- If your chosen backup device is a USB storage device, then your Recovery Kit should contain the appropriate USB storage device containing your CMSADM backup, along with the USB storage device containing your Full Maintenance backup.
- If your chosen backup device is a network device, you must manage the location of the CMSADM and Maintenance backups yourself.

## About binary database backups

The binary backup procedure will backup the entire database in binary form. Similar to the LAN backup and restore process, this procedure does not allow System data, Call Center Administration data, or Historical data to be restored individually.

#### Important:

Unlike tape devices, USB storage devices and network mount points must be monitored to ensure they are accessible. Timetables and Backup/Restore devices using USB storage devices and network mount points must be able to access these media sources to function properly. Remember to remount all non-tape media sources used by CMS, after any reboot of the system.

- If the binary backup is to tape, continue with Binary backup of the database to tape.
- If the binary backup is to a USB storage device, continue with Binary backup of the database to a USB storage device.
- If the binary backup is to a network mount point, continue with Binary backup of the database to a network mount point.

#### Doing a binary database backup to tape

#### Procedure

1. Log in to the CMS server as root.

#### Important:

You cannot directly log on as root from a remote connection. You must log on using an administered CMS user ID, then use **su** - **root** to log on with root privileges.

- 2. Insert a blank tape into the tape drive.
- 3. Enter:

/cms/install/bin/db\_backup <tape\_device>

If a *tape\_device* is not entered, the default device will be /dev/rmt/0c.

😵 Note:

You can set up a cron job to run this command regularly.

## Doing a binary database backup to a USB storage device

#### About this task

#### Important:

USB storage device backups are considered permissive use. A procedure is supplied to facilitate USB storage device backups. You should set up and verify as Avaya does not support debugging and setup of USB storage device backups.

As an option, the CMS server can be configured to utilize a USB storage device for the binary backup and restore. The binary backup can write backup data to a USB storage device. This procedure requires knowledge and experience with configuring and mounting USB storage devices.

#### Important:

Unlike a backup to a tape drive, the speed of a USB storage device is determined by the speed of the USB interfaces and the USB storage device.

#### Procedure

1. Insert a USB storage device and create a mount point, then mount the USB storage device to the CMS server.

Refer to Configuring and Connecting a USB storage device in the *Avaya Software Installation, Maintenance, and Troubleshooting* document for more information.

2. Modify /etc/vfstab to make sure your USB storage device mount point can survive reboot.

However, if the USB storage device is moved to a different USB location, the /etc/vfstab entry fails to mount after a reboot.

#### Important:

Unlike tape devices, USB storage devices and network mount points must be monitored to make sure they are accessible. Timetables and Backup/Restore devices using the USB storage devices and network mount points must be able to access these media sources to function properly. Remember to remount all non-tape media sources used by CMS, after any reboot of the system.

3. Create an empty file using the touch command.

Example: touch /<USB\_path>/<binary\_backup\_filename>

4. Run the backup using the following command:

/cms/install/bin/db\_backup /<USB\_path>/<binary\_backup\_filename>

Avaya recommends that binary backup files written to USB storage devices be saved to another location for disaster recovery.

#### Doing a binary database backup to a network device

#### About this task

#### Important:

Network backups are considered permissive use. A new procedure is supplied to facilitate network backups. You should set up and verify as Avaya does not support debugging and set up of network backups.

As an option, the CMS server can be configured to utilize a network device for the binary backup and restore. The binary backup can write backup data to a network device. This procedure requires knowledge and experience with network file system mounts.

#### Important:

Unlike a backup to a tape drive, the speed of a network backup is determined by your network bandwidth.

#### Procedure

- 1. Create a mount point, then mount a network file system to the CMS server.
- 2. Modify /etc/vfstab to make sure your network file system can survive a reboot.
- 3. Create an empty file using the **touch** command.

Example: touch /<mount point path>/<binary backup filename>

4. Run the backup using the following command:

```
/cms/install/bin/db_backup /<mount_point_path>/
<binary backup filename>
```

#### Example

Example to mount nfs to a Linux<sup>®</sup> system:

```
mkdir /nfs
mount -o vers=3 <machine_name>:/cms_db_backup /nfs
touch /nfs/cms_db_backup
/cms/install/bin/db_backup /nfs/cms_db_backup/<binary_backup_filename>
```

# Adding a Full Maintenance Backup Timetable for an ACD using the PC Client

#### Before adding a Full Maintenance Backup Timetable for an ACD

The following items should be read and understood before performing maintenance backups:

• Maintenance backups to tape require that backup tapes must be manually rotated. The frequency of the rotation depends on the dates and times of all scheduled backups. By creating individual ACD backups, the risk of data being overwritten is increased. Timetable backups must be scheduled such that the tape can be manually rotated before another

scheduled backup runs. Failing to rotate the tape causes the data to be overwritten by the next scheduled backup.

- If you are backing up to tape, a sufficient supply of tapes should be available so that tapes can be rotated. One common plan is to keep seven tapes in stock and recycle them daily. A new tape is used each day of the week, and each week the sequence is repeated.
- The maintenance backups do not back up the CMS software, operating system files, or non-CMS customer data on the system. For complete data recovery, both CMSADM and all maintenance backups are required.
- Running backups during archiving may cause performance problems. For best performance, run backups either before or after the archiving process.
  - 😒 Note:

When doing this procedure, use the arrow keys or type the first few unique letters of an item to highlight the item.

## Adding a Full Maintenance Backup Timetable for an ACD using the PC Client

#### Procedure

- 1. Log in to CMS.
- 2. From the Main Menu, press F4 to access the CMS timetables.
- 3. Select Timetable.
- 4. Press Ctrl+Zto clear out the entries in the form.
- 5. Enter fullBackup in the Timetable name field.
- 6. Press Enter.
- 7. Select Find one.
- 8. Press Enter.
- 9. Rename the "fullBackup timetable" to a unique name that identifies the ACD being backed up, such as "acd1fullBackup" for ACD 1.
- 10. Press Enter.
- 11. Enter the letter a to highlight the **Add** item.
- 12. Press Enter.

Key strokes for building the new timetable is now tracked. A message appears at the bottom of the Main Menu with the words Keeping Entries.

- 13. Press F3 to access the Options menu.
- 14. Enter the letter  $\circ$  to highlight the **Options** item.
- 15. Press Enter.

- 16. Enter the letters cu to highlight the Current ACD item.
- 17. Press Enter.
- 18. Enter the number of the ACD for which the timetable is created.
- 19. Press Enter.
- 20. Enter the letter m to highlight the **Modify** item.
- 21. Press Enter.
- 22. Press F5 to get out of the **Options** menu.
- 23. Enter the letter m to highlight the **Maintenance** item from the **Main Menu**.
- 24. Press Enter.
- 25. Do one of the following:
  - If the Back Up Data item is already be highlighted, press Enter.
  - If the Back Up Data item is not highlighted, enter the letters back to select Back Up Data, and press Enter.
- 26. Use the down arrow key to move to the **ACD(s) to back up** field.
- 27. Place an  $\times$  in the **Current ACD** field.
- 28. Press Enter.
- 29. Enter the letter r to select the **Run** option.
- 30. Press Enter.
- 31. Press F5 to exit the **Timetable** menu.
- 32. Press F4 to open the **Timetable/Shortcut** options.
- 33. Stop should be highlighted, press Enter. If Stop is not highlighted, enter the letters st to highlight Stop.
- 34. Press Enter.
- 35. Enter y when prompted to save the changes.
- **36. Press** Enter.

The timetable has been created. The system returns to the Timetable screen for the timetable just created.

- 37. As needed, modify the dates and times you want the timetable to run. If changes are made:
  - a. Press Enter.
  - b. Enter the letter  ${\tt m}$  to select the  ${\it Modify}$  item.
  - c. Press Enter.

- 38. Press Enter.
- 39. Press F5 to exit the Timetable menu.
- 40. From the Main Menu, press F4 to access the CMS timetables.
- 41. Select Timetable.
- 42. Press Ctrl+Z to clear out the entries in the form.
- 43. Press Enter.
- 44. Enter the letter 1 to select the List all item.

A list of all Timetables is displayed.

- 45. Use the arrow keys to locate the Timetable just created. If the timetable is not found, repeat this procedure.
- 46. Press F5 to exit the Timetable: List all menu.
- 47. Press F5 to exit the **Timetable** menu.

## About restoring data

Use the Restore Data window to restore CMS data that has been lost due to system failure, disk crashes, or power outages. You can restore all CMS data files that you have previously backed up. You can also select which ACDs and CMS data to restore.

The automatic restore restores all CMS data files from your last backup. Most data is restored by the automatic restore procedure.

The manual restore restores specific CMS data files. The manual restore is used only when a select number of database tables need to be restored. A manual restore gives you control over which data is restored.

## Before restoring data

The following items should be read and understood before attempting to restore data:

- The Data Collection and CMS states must be set as noted for the following backups:
  - Local system administration data Data Collection off; CMS Single-user mode
  - CMS system administration data Data Collection on or off; CMS Single-user mode
  - ACD system administration data Data Collection on or off; CMS Single-user mode
  - Historical data, Non-CMS data, or specific tables Data Collection on or off; CMS Singleor Multi-user mode.
- Data must be backed up before it can be restored. To ensure the safety of your data, you should frequently back up your system.

- The restore procedure is run in the background. The **Status** field on the Restore Data window allows you to monitor the status of the restore process as it is performed.
- You can turn CMS back to multi-user mode when the **Status** field displays Restore is complete.
- When migrating or restoring a non-LDAP user from a maintenance backup, and the "logid" (logon ID) for a user does not exist in /etc/passwd, the user is created as a new logid. That logid requires password administration just as if the user was created as described in <u>About</u> <u>administering users</u> on page 214.

When this happens, the migration and restore logs contain messages similar to the following examples:

- /cms/maint/r3mig/mig.log

INFO: New UNIX user normusr1: name, room and telephone will not be migrated.

- /cms/maint/restore/rest.log

```
Created UNIX login 'normusr1'.
```

```
Warning: Name, Telephone, and Room will not be restored for normusr1.
```

## Permissions required to restore data

To restore data, you must have "write" permission for the Maintenance subsystem.

## Doing an automatic restore using the Web Client

#### Procedure

1. Navigate to Administration > Maintenance > Restore Data.

CMS Supervisor displays the Restore Data window.

- 2. Select the restore device you want to use from the **Device name** drop-down list.
- 3. Under the **Restore from last backup** option, select **Yes**.
- 4. Do one of the following:
  - Click **Run** to start the backup.
  - Click **Reset** to clear all of your option choices.

If you click **Run**, the restore process begins. The Restore Data window shows the following progress messages:

- The Status field shows which data is being restored.
- The **Run** button displays a spinning icon, preventing you from clicking it again.

## 😵 Note:

If you navigate away from the Restore Data window while the restore is in progress, the restore continues. If you try to navigate back to the Restore Data window, the system displays the message Cannot get to screen, meaning that the restore is still in progress and you cannot start another restore.

The system notifies you which volumes to mount to restore the data. At the end of every restored volume, the tables that are fully or partially restored are displayed. If your device is "Other", the backup file is automatically located for you. You only need to press the **Continue** key to perform the requested restore.

If the system asks for a tape that you cannot provide, you must cancel the restore process. The restore can be rerun if the tape is found.

## Doing a manual restore using the Web Client

#### About this task

#### Important:

The manual restore stops when severe errors occur or when you specify there are no more volumes to restore. Select **Stop** to indicate to the restore process that you are finished. Do not select **Cancel** since it implies an abnormal termination. Canceling a restore leaves the already restored data in the tables, which may result in an abnormal database state. You receive an acknowledgment window asking if you are sure you want to cancel the restore.

#### Procedure

#### 1. Navigate to Administration > Maintenance > Restore Data.

CMS Supervisor displays the Restore Data window.

- 2. Select the restore device you want to use from the Device name drop-down list.
- 3. Under the Restore from last backup option, select No.
- 4. In the Start date field, enter the oldest date to be included in the restore.
- 5. In the **Start time** field, enter the time you want to start restoring data. Use the format of HH:MM XM when entering the time where HH is hours, MM is minutes, and XM is AM or PM.
- 6. In the Stop date field, enter the end date to be included in the restore.
- In the Stop time field, enter the time you want to stop restoring data. Use the format of HH:MM XM when entering the time where HH is hours, MM is minutes, and XM is AM or PM.
- 8. In the ACD(s) to restore options, select All ACDs or Current ACD.
- 9. In the **Data to restore** group, select the types of data you want to restore.

10. If you do not select **Specific tables**, go to Step <u>16</u> on page 403. Otherwise, select **Specific tables**.

Supervisor displays the Restore Data - Select tables window.

If you are doing the **Specific tables** restore, you cannot restore any other information simultaneously. This includes:

- Local system administration data This data can only be restored once. A second attempt corrupts the data.
- CMS system administration data
- ACD system administration data
- · Historical data
- 11. Select the tables you want to restore.
- 12. Do one of the following:
  - Click **Run** to start the restore.
  - Click Reset to clear all of your option choices.

The system notifies you which volumes to mount to restore the data. At the end of every restored volume, the tables that are fully or partially restored are displayed. If your device is "Other", then the backup file is automatically located for you. You only need to press the **Continue** key to perform the requested restore.

If the system prompts for a tape that you cannot provide, you must cancel the restore process. The restore can be rerun if the tape is found.

## Doing an automatic restore using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Restore Data in the Operations list.
- 4. Click **OK**.

Supervisor displays the Restore Data window.

The **Status** field shows the status of the current restore or a previous restore if one has taken place.

The **Error name** field shows any errors found during the restore.

5. Check the **Device name** field to make sure the correct backup/restore device is selected.

If you want to use another backup/restore device, select **Actions** > **List devices**. Enter the correct backup/restore device name in the **Device name** field.

This field defaults to the device named during installation.

- 6. Select the Restore from the latest backup? check box.
- 7. From the Actions menu, select Run.

The system notifies you which volumes to mount to restore the data. At the end of every restored volume, the tables that have been fully or partially restored are displayed. If your device is "Other", then the backup file is automatically located for you. You only need to press the **Continue** key to perform the requested restore.

If the system asks for a tape that you cannot provide, you must cancel the restore process. The restore can be rerun if the tape is found.

## Doing a manual restore using the PC Client

#### About this task

#### Important:

The manual restore stops when severe errors occur or when you tell it there are no more volumes to restore. Select **Stop** to tell the restore process that you are finished. Do not select **Cancel** since it implies an abnormal termination. Canceling a restore leaves the data that has already been restored in the tables, which may result in the database being in an abnormal state. You receive an acknowledgment window asking if you are sure you want to cancel the restore.

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Restore Data in the Operations list.
- 4. Click OK.

Supervisor displays the Restore Data window.

The **Status** field shows the status of the current restore or a previous restore if one has taken place.

The Error name field shows any errors found during the restore.

5. Check the **Device name** field to ensure that the correct backup/restore device is selected.

If you want to use another backup/restore device, select **Actions > List devices**. Enter the correct backup/restore device name in the **Device name** field.

This field defaults to the device named during installation.

#### Important:

If your backup device is tape, do not select the **Restore from the latest backup?** check box. A manual restore accepts any tape you mount as long as the data on the tape corresponds with the requested data.

- 6. In the **Start date** field, enter the oldest date to be included in the restore by using one of the following methods:
  - Enter the date in the mm/dd/yy format.
  - Use the drop-down calendar to select a date.
  - Enter the date in relative format; for example, 0 for today and -1 for yesterday.
- 7. In the **Start time** field, enter the time you want to start restoring data. Use the format of hh:mm XM when entering the time where hh is hours, mm is minutes, and XM is AM or PM.

If you wanted to restore data starting at 1:15 AM, you would enter 01:15 AM

If AM or PM is not specified, a 24-hour clock is assumed.

- 8. In the **Stop date** field, enter the most recent date to be included in the restore.
- 9. In the **Stop time** field, enter the time you want to stop restoring data. Use the format of hh:mm XM when entering the time.
- 10. In the ACD(s) to restore options, select either All ACDs or Current ACD.
- 11. In the **Data to restore** group, select the types of data you want to restore.
- 12. If you do not select **Specific tables**, go to Step <u>16</u> on page 403. Otherwise, select **Actions > Select tables**.

Supervisor displays the Restore Data - Select tables window.

If you are performing the **Specific tables** restore, you cannot restore any other information at the same time. This includes:

- Local system administration data This data can only be restored once. A second attempt corrupts the data.
- CMS system administration data
- · ACD system administration data
- · Historical data
- 13. Select the tables you want to restore.
- 14. From the Actions menu, select Modify.
- 15. Close the Restore Data Select tables window to return to the Restore Data window.
- 16. From the **Actions** menu, select **Run**.

The system notifies you which volumes to mount to restore the data. At the end of every restored volume, the tables that have been fully or partially restored are displayed. If your

device is "Other", then the backup file is automatically located for you. You only need to press the **Continue** key to perform the requested restore.

If the system asks for a tape that you cannot provide, you must cancel the restore process. The restore can be rerun if the tape is found.

## **Restoring the database from a binary backup**

The binary backup does not back up the CMS software, operating system files or non-CMS customer data on the system. For complete data recovery, both a CMSADM restore and a binary restore are required. See *Maintaining and Troubleshooting Avaya Call Management System* for instructions on how to perform a CMSADM restore and a binary restore.

# About administering backup and restore devices

Use the Backup/Restore Devices window to assign a name and description to a full pathname for a device. The device name is used for data backup, data migration, data restore, and for loading a pseudo-ACD. The maintenance device menu displays **Tape** and **Other** options for Device Type. **Other** is used for USB storage devices and network-mounted file systems (NFS).

The LAN Backup feature of CMS is not accessible using the CMS Supervisor interface. For more information regarding LAN Backup, see *Using Avaya Call Management System LAN Backup*.

## Permissions required to administer backup and restore devices

Depending on the procedure you want to do, you need the following permissions:

- You need "read" permission for the Maintenance subsystem to view the Backup/Restore Devices window.
- You need "write" permission for the Maintenance subsystem to add, delete or modify any backup or restore devices.

## Viewing backup or restore devices using the Web Client Procedure

Navigate to Administration > Maintenance > Backup/Restore Devices.

CMS Supervisor displays the backup and restore devices currently administered.

## Adding a backup or restore device using the Web Client Procedure

1. Navigate to Administration > Maintenance > Backup/Restore Devices.

CMS Supervisor displays the backup and restore devices currently administered.

2. Click Add Backup/Restore Device.

CMS Supervisor displays the Add Backup/Restore Device window.

- 3. Administer the following options:
  - In the **Device name** field, enter the name of the backup/restore device.
  - In the Path field, enter the full operating system path to access the device.

See the "Accessing devices" section in your operating system's Administrator's Guide for more information about devices and paths. If the device type is **Other**, its system path cannot be located on the CMS disk. In addition, the USB storage device or network must be mounted.

- In the **Description** field, enter any additional information to help identify the device.
- For **Device Type**, select either **Tape** or **Other**. **Tape** includes all currently supported tape drives. **Other** includes the USB and network type backup devices.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click OK.

CMS Supervisor displays an updated list of items.

## Modifying a backup or restore device using the Web Client Procedure

1. Navigate to Administration > Maintenance > Backup/Restore Devices.

CMS Supervisor displays the backup and restore devices currently administered.

2. Click **Modify** on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 3. Administer the following options:
  - The **Device name** field is display-only. You cannot change the name.
  - In the **Path** field, enter the full operating system path to access the device.

See the "Accessing devices" section in your operating system's Administrator's Guide for more information about devices and paths. If the device type is **Other**, its system

path cannot be located on the CMS disk. In addition, the USB storage device or network must be mounted.

- In the **Description** field, enter any additional information to help identify the device.
- For **Device Type**, select either **Tape** or **Other**. **Tape** includes all currently supported tape drives. **Other** includes the USB and network type backup devices.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

## Deleting a backup or restore device using the Web Client

#### Procedure

1. Navigate to Administration > Maintenance > Backup/Restore Devices.

CMS Supervisor displays the backup and restore devices currently administered.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

- Click Yes to continue with the change. Click Cancel to cancel the operation.
   CMS Supervisor displays a confirmation message.
- 4. Click OK.

CMS Supervisor displays an updated list of items.

## Viewing backup or restore devices using the PC Client Procedure

- From the Controller window, select **Tools > Maintenance**.
   CMS Supervisor displays the Maintenance window.
- 2. Select the **Operations** tab.
- 3. Select Backup/Restore Devices in the Operations list.
- 4. Click OK.

Supervisor displays the Backup/Restore Devices window.

5. From the **Actions** menu, select **Find one**.

Supervisor displays the information for the first device.

6. If more than one match is found, go to the **Actions** menu, and select **Next**. Repeat this step until all devices have been displayed.

# Listing all backup and restore devices using the PC Client

#### Procedure

- From the Controller window, select Tools > Maintenance.
   CMS Supervisor displays the Maintenance window.
- 2. Select the **Operations** tab.
- 3. Select Backup/Restore Devices in the Operations list.
- 4. Click OK.

Supervisor displays the Backup/Restore Devices window.

5. From the Actions menu, select List all.

Supervisor displays a list of all devices.

## Adding a backup or restore device using the PC Client Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Backup/Restore Devices in the Operations list.
- 4. Click **OK**.

Supervisor displays the Backup/Restore Devices window.

5. In the **Device name** field, enter the name of the backup/restore device.

If you want to refer to your backup/restore device as ddrive1, enter ddrive1 in the **Device** name field.

6. In the **Path** field, enter the full operating system path to access the device.

See the "Accessing devices" section in your operating system's Administrator's Guide for more information about devices and paths. If the device type is **Other**, its system path cannot be located on the CMS disk. In addition, the USB storage device or network must be mounted.

7. In the **Description** field, enter any additional information to help identify the device.

The **Device name** field now has the option of **Tape** and **Other**. **Tape** includes all currently supported tape drives. **Other** includes the USB and network type backup devices.

8. From the **Actions** menu, select **Add**.

The device is defined through CMS and can be used for backup and restore operations.

## Modifying a backup or restore device using the PC Client Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Backup/Restore Devices in the Operations list.
- 4. Click OK.

Supervisor displays the Backup/Restore Devices window.

- 5. Perform one of the following procedures to select the correct backup/restore device:
  - If you know the name of the device, enter the name of the device in the **Device name** field and then press the Enter key.
  - If you do not know the name of the device, select **Find one** from the **Actions** menu. If more than one match is found, go to the **Actions** menu, and select **Next**. Repeat this step until the device you want to delete is displayed in the dialog box.
- 6. Enter the new information in the fields that require modification.
- 7. From the Actions menu, select Modify.

The changes made to the device definition are saved.

## Deleting a backup or restore device using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Backup/Restore Devices in the Operations list.
- 4. Click OK.

Supervisor displays the Backup/Restore Devices window.

- 5. Perform one of the following procedures to select the correct backup/restore device:
  - If you know the name of the device, enter the name of the device in the **Device name** field and then press the Enter key.

- If you do not know the name of the device, select **Find one** from the **Actions** menu. If more than one match is found, go to the **Actions** menu, and select **Next**. Repeat this step until the device you want to delete is displayed in the dialog box.
- 6. From the **Actions** menu, select **Delete**.

The specified backup/restore device definition is deleted from the CMS server.

# About administering a printer

Use the Printer Administration window to assign a name, description, and options to a printer that can be used by terminals connected to a CMS server. Users of CMS Supervisor do not have access to these CMS server printers. CMS Supervisor users must use printers that are associated with their own PCs.



Printers directly connected to CMS servers is a legacy feature that is not supported with new installations.

## Before administering a printer

Consider the following items before you administer a printer:

- Printers directly connected to CMS servers is a legacy feature that is not supported with new installations.
- Before you can assign a printer in the Printer Administration window, the printer must already be administered in the operating system.
- The printer set up as the default printer will receive all terminal requested print jobs, unless otherwise specified by the user.
- If jobs are sent to a printer that is no longer administered, the print job will be sent to the default printer and an error will be logged in the Maintenance Error Log.
- The name of a printer administered in the Printer Administration window can be used by terminal users as the default destination when printing historical reports.

## Permissions required to administer a printer

Depending on the procedure you want to do, you will need the following permissions:

- To view the Printer Administration window, you must have "read" permission for the Maintenance subsystem.
- To add, delete, or modify the Printer Administration window, you must have "write" permission for the Maintenance subsystem.

## Viewing printers using the Web Client Procedure

Navigate to **Administration > Maintenance > Printer Administration**.

CMS Supervisor displays the printers currently administered.

## Adding a printer using the Web Client

#### Procedure

1. Navigate to Administration > Maintenance > Printer Administration.

CMS Supervisor displays the printers currently administered.

2. Click Add Printer.

CMS Supervisor displays the Add Printer window.

- 3. Administer the following options:
  - In the **CMS printer name** field, enter the name of the new printer. The name assigned to the printer must be unique from all other installed printers; however, it can be assigned the same name it was given during the operating system administration.
  - In the **LP printer name** field, enter the name assigned to the printer when it was administered in the operating system.
  - In the **Description** field, enter any additional information to identify the printer.
  - If the printer uses IBM graphic characters, select the **IBM graphic characters** check box. Otherwise, leave the check box cleared.
  - In the **Lines per page** field, enter the number of lines that fit on a page. The default is 66 lines. CMS formats reports to correspond to the value in this field.
  - In the Print type options select one of the following choices:
    - Select Normal (default setting).
    - Select Other. Then, in the corresponding field, enter the specific print type such as pica, elite, or compressed.
  - If you want a banner to be printed for every print job, select the **Banners** check box. A banner is a cover sheet that identifies the user who requested the print job.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

## Modifying printer options using the Web Client Procedure

1. Navigate to Administration > Maintenance > Printer Administration.

CMS Supervisor displays the printers currently administered.

2. Click Modify on the item you want to modify.

CMS Supervisor displays the Modify Item window.

- 3. Administer the following options:
  - In the **CMS printer name** field, enter the name of the new printer. The name assigned to the printer must be unique from all other installed printers; however, it can be assigned the same name it was given during the operating system administration.
  - In the **LP printer name** field, enter the name assigned to the printer when it was administered in the operating system.
  - In the **Description** field, enter any additional information to identify the printer.
  - If the printer uses IBM graphic characters, select the **IBM graphic characters** check box. Otherwise, leave the check box cleared.
  - In the **Lines per page** field, enter the number of lines that fit on a page. The default is 66 lines. CMS formats reports to correspond to the value in this field.
  - In the Print type options select one of the following choices:
    - Select Normal (default setting).
    - Select Other. Then, in the corresponding field, enter the specific print type such as pica, elite, or compressed.
  - If you want a banner to be printed for every print job, select the **Banners** check box. A banner is a cover sheet that identifies the user who requested the print job.
- 4. Click **OK** to commit the operation. Click **Cancel** to cancel the operation.

CMS Supervisor displays a confirmation message.

5. Click **OK**.

CMS Supervisor displays an updated list of items.

## Deleting a printer using the Web Client

#### Procedure

1. Navigate to Administration > Maintenance > Printer Administration.

CMS Supervisor displays the printers currently administered.

2. Click **Remove** on the item you want to delete.

CMS Supervisor displays the Confirm Delete window.

- Click Yes to continue with the change. Click Cancel to cancel the operation.
   CMS Supervisor displays a confirmation message.
- 4. Click OK.

CMS Supervisor displays an updated list of items.

## Listing all printers using the PC Client

#### Procedure

- From the Controller window, select Tools > Maintenance.
   CMS Supervisor displays the Maintenance window.
- 2. Select the **Operations** tab.
- 3. Select Printer Administration in the Operations list.
- 4. Click OK.

Supervisor displays the Printer Administration window.

5. From the Actions menu, select List all.

Supervisor displays the Printer Administration - List All window.

## Adding a printer using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Printer Administration in the Operations list.
- 4. Click **OK**.

Supervisor displays the Printer Administration window.

5. In the **CMS printer name** field, enter the name of the new printer.

The name assigned to the printer must be unique from all other installed printers; however, it can be assigned the same name it was given during the operating system administration.

- 6. In the **LP printer name** field, enter the name assigned to the printer when it was administered in the operating system.
- 7. In the **Description** field, enter any additional information to identify the printer.

- 8. If the printer uses IBM graphic characters, select the **IBM graphic characters** check box. Otherwise, leave the check box cleared.
- 9. In the **Lines per page** field, enter the number of lines that fit on a page.

The default is 66 lines. CMS formats reports to correspond to the value in this field.

- 10. In the **Print type** options select one of the following choices:
  - Select Normal (default setting)
  - Select **Other**. Then, in the corresponding field, enter the specific print type such as pica, elite, **or** compressed.
- 11. If you want a banner to be printed for every print job, select the **Banners** check box.

A banner is a cover sheet that identifies the user who requested the print job.

12. From the Actions menu, select Add.

# Modifying printer options using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Printer Administration in the Operations list.
- 4. Click OK.

Supervisor displays the Printer Administration window.

- 5. Perform one of the following procedures to select the correct printer:
  - If you know the name of the printer, enter the name of the printer in the CMS printer name field, and then press Enter.
  - If you do not know the name of the printer, select Find one from the Actions menu. If more than one match is found, go to the Actions menu, and select Next. Repeat this step until the printer you want to delete is displayed.

#### Important:

You cannot modify the name of a CMS printer. If you want to change a printer name, you must delete the printer and add it again with a new name. See <u>Deleting a printer</u> <u>using the PC Client</u> on page 414, and <u>Adding a printer using the PC Client</u> on page 412 for more information.

- Make changes to any of the fields in the Printer Administration window, except the CMS printer name field
- 7. From the Actions menu, select Modify.

## Deleting a printer using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Printer Administration in the Operations list.
- 4. Click OK.

Supervisor displays the Printer Administration window.

- 5. Perform one of the following procedures to select the correct printer:
  - If you know the name of the printer, enter the name of the printer in the CMS printer name field, and then press Enter.
  - If you do not know the name of the printer, select **Find one** from the **Actions** menu. If more than one match is found, go to the **Actions** menu, and select **Next**. Repeat this step until the printer you want to delete is displayed.
- 6. From the Actions menu, select Delete.

If you try to delete a printer that is assigned to users, you will receive a message asking if you still want to delete the printer.

Users assigned to this printer will not have another printer assigned when it is deleted.

# About administering report properties

You can use the Report Administration window to impose a system wide limit on report queries. The system wide limit on report queries is implemented using the following two properties:

• You may impose a specific time limit, in 1 second increments, on historical report queries. That is, if a report query takes more than X seconds to return data from the Informix database, it times out. The range of allowed values is 3 to 999 seconds, or you may allow all historical report queries to run for an unlimited amount of time.

If the time limit for all historical reports is set to any value other than never (unlimited), a historical report whose query takes longer than the limit times out, and the user receives an error message.

• You may also limit the size of an agent group which is part of either a real time or historical query. The limit choices for agent group are groups of 99 members or less, or unlimited.

If the agent group limit is set to 99 members or less, a real time or historical agent group report which uses an agent group of 100 members or more does not run. The user receives an error message.

The system defaults for both of these properties are the unlimited value, and it changes only if you modify these properties with this window. The changes to this window take effect upon the next running report, and are imposed on all users. This window is only available from the ASCII interface and cannot be used from Supervisor.

Report limits apply to standard reports, custom reports, designer reports, and reports run from timetables. In the case of a report running from a timetable, if the report fails due to the set limits, the error is recorded in elog.

This window may be placed in a timetable. Therefore, if you wish to limit the properties of report queries only during certain times of the day, you can create two timetables. The first timetable should run at the beginning of your system's busiest time, and modifies the report properties to impose time limits. The second timetable should run at the beginning of your system's duiet time, and modifies the report properties back to unlimited.

#### 😵 Note:

Administering report properties is only available using the Web Client or the ASCII (text) Client.

## Before administering report properties

• Examine the query log to determine if you have any reports which are adversely affecting your system performance due to the time spent on their Informix database query.

Note:

The report should be historical or real time, and it should use agent groups.

- Decide if you want to limit your historical report queries and what that limit, in number of seconds, should be
- · Decide if you want to limit the size of agent groups used in agent group reports

## Permissions required to administer report properties

Depending on the procedure you want to do, you need the following permissions:

- To view the Report Administration window, you must have "read" permission for the Maintenance subsystem.
- To modify the Report Administration window, you must have "write" permission for the Maintenance subsystem.

## Modifying report properties using the Web Client Procedure

1. Navigate to Administration > Maintenance > Report Administration.

CMS Supervisor displays the report properties currently administered.

- 2. Administer the following options:
  - Either enable or disable the **Agent groups > 99 members allowed in queries** option. The default value is enabled.
  - In the **Timeout value for historical report queries** field, enter the number of seconds (3 to 999) to limit historical report queries to a specific time length. The default value of zero means reports will not time out.
- 3. Click **Modify** to save the change. Click **Reset** to reset the values of the fields.

CMS Supervisor displays the window with the updated values.

## Modifying report properties using the ASCII (text) Client

#### Procedure

- 1. Log on to the ASCII (text) Client.
- 2. From the Main Menu, choose Maintenance and press Enter.
- 3. Choose Report Administration and press Enter.
- 4. Enter n in the first field if you wish to limit Agent Group reports to groups of 99 members or less. If you wish to allow all sizes of Agent Groups in queries, enter y.
- 5. Enter the number of seconds (3 to 999) in the second field if you wish to limit historical report queries to a specific time length. If you do not want a time limit to be enforced by the system, enter never.
- 6. From the Actions menu, select Modify.

# About viewing connection status

You can use the Connection Status window to monitor the data link between the CMS server and the Communication Manager system. You can also view the current status of the application, session, and connection layers of the link between the Communication Manager system and CMS server.

## Permissions required to view connection status

You must have "read" permission for the Maintenance subsystem to view the Connection Status window.

## Viewing connection status using the Web Client

#### Procedure

1. Navigate to Administration > Maintenance > Connection Status.

CMS Supervisor displays the current connection status for all Communication Manager systems connected to the CMS server.

For a description of the connection status information, see <u>Connection status field</u> <u>descriptions</u> on page 418.

2. Click **Refresh** to update the current connection status.

## Viewing connection status of an ACD using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Connection Status in the Operations list.
- 4. Click **OK**.

CMS Supervisor displays the Connection Status window.

5. In the ACDs field, enter the name or number of the ACD or ACD Group.

For a description of the connection status information, see <u>Connection status field</u> <u>descriptions</u> on page 418.

6. From the Actions menu, select Find one.

CMS Supervisor displays the Connection Status window for the selected ACD.

# Listing connection status of all ACDs using the PC Client Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Connection Status in the Operations list.
- 4. Click OK.

CMS Supervisor displays the Connection Status window.

For a description of the connection status information, see <u>Connection status field</u> <u>descriptions</u> on page 418.

- 5. If the **ACDs** field is not clear, select **Edit** > **Clear All**.
- 6. From the **Actions** menu select **List all**.

CMS Supervisor displays the Connection Status - List All window.

## **Connection status field descriptions**

Field	Description	Status Messages
ACD	Displays the number or name of the ACD.	-
Application	Displays status for the application layer of the link between the Communication Manager system and CMS .	<pre>waiting session - The application layer is inactive. This is the state of the application layer when the system is first powered on. translation pumpup - CMS is receiving translations from the Communication Manager system. Translations are needed for CMS to correctly track the ACD calls coming from the switch. data transfer - The application layer can receive and transmit data successfully. not collecting data - Data collection has been turned off. CMS System Setup - The link has gone down. To resume data collection, use the Data Collection window busied out (switch) - The link between CMS and the Communication Manager system has been busied out from the switch side, usually to change switch translations.</pre>
Session	Displays status for the session layer of the link between the Communication Manager system and CMS .	<pre>quiescent - The session layer is inactive. This is the state of the session layer when the system is first powered on. waiting acceptance - The session layer is waiting for the connection layer to become operational and for the remote session layer to accept the session. data transfer - The session layer can now transmit and receive data from the Communication Manager system.</pre>

The Connection Status window contains the following fields.

Table continues...

Field	Description	Status Messages
Connection	Displays status for the connection layer of the link between the Communication Manager system and CMS .	<pre>quiescent - Indicates that the connection is inactive. This is the state of the connection when the system is first powered on. out of order - Something is wrong with the connection to the Communication Manager system. For example, the network connection between the Communication Manager system and CMS is currently unavailable. operational - The connection can transmit information physically between the Communication Manager system and CMS . waiting session accept - The link is down. Secondary-Indicates that CMS is connected to the secondary CM for ACD. The system displays this option when you select Find one, Previous, or Next.</pre>
Date/Time	Displays the date/time for the ACD, unless the link to the ACD is down when CMS is brought up. If this happens, CMS uses the operating system time until the link is reestablished.	
Error	Displays any errors found.	

# About viewing ACD status

The ACD Status window displays information about the current selected ACD, including the number of splits or skills, agents logged in, trunk groups, trunks, VDNs, vectors (if your company has purchased Call Vectoring), and measured splits.

# Before viewing ACD status

Read and understand the following items before viewing the status of an ACD through the Maintenance subsystem:

- The link must be up between the Communication Manager system and the CMS server if you want to view the status of a specific ACD.
- Data collection must be on for the specific ACD.

## Permissions required to view ACD status

To view the ACD Status window, you must have "read" permission for the Maintenance subsystem.

# Viewing ACD status using the Web Client

#### Procedure

Navigate to Administration > Maintenance > ACD Status.

CMS Supervisor displays the status of all connected ACDs.

For information about the fields in the ACD Status window, see <u>ACD status field descriptions</u> on page 421.

## Viewing ACD status using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Highlight ACD Status in the Operations list.
- 4. Click OK.

Supervisor displays the ACD Status window.

For information about the fields in the ACD Status window, see <u>ACD status field</u> <u>descriptions</u> on page 421.

- 5. Perform one of the following steps to enter information in the **ACDs** field:
  - Enter the name or number of the ACD directly into the field.
  - Use the history list to select an ACD.
  - Use the Browse button to select an ACD.

#### 😵 Note:

You can also select an ACD Group which will return all the members of that group.

6. From the Actions menu, select Find one.

Supervisor displays the ACD Status window for the selected ACD.

If you selected an ACD Group, the first member of the group is displayed. View any other member ACDs by using the **Next** and **Previous** buttons.

# Listing ACD status using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Highlight ACD Status in the Operations list.
- 4. Click OK.

Supervisor displays the ACD Status window.

- 5. From the Edit menu, select Clear All.
- 6. From the Actions menu select List all.

Supervisor displays the ACD Status - List All window.

For information about the fields in the ACD Status window, see <u>ACD status field</u> <u>descriptions</u> on page 421.

# ACD status field descriptions

The following table provides the descriptions of the fields on the ACD Status window:

Name	Description	
Skills	The skills measured by CMS.	
Skill members in use	The agent/skill pairs logged in at the time the ACD Status window was opened.	
Trunk Groups	The trunk groups measured by CMS.	
Trunks	The trunks measured by CMS. Unmeasured trunks are not included.	
VDNs	The VDNs measured on the selected ACD.	
Vectors	The vectors available for use in the selected ACD.	
Error name	The errors encountered by the ACD.	

# About viewing archiving status

Use the Archiving Status window to display the status, date, and time of the last archive for interval, daily, weekly, and monthly data. This information can help you decide when to turn off data collection or change your archiving times to minimize data loss.

## 😵 Note:

The Archiving Status window displays the status for the default time zone archiving for each ACD and the archiving of each time zone set up with Data Summarization Time Zone. If the tenancy feature is turned on and the user has permissions for the given tenant, the user sees the status of the tenant time zone archiving for each ACD.

## Permissions required to view archiving status

You must have "read" permission for the Maintenance subsystem to view the Archiving Status window.

## Viewing archiving status using the Web Client

#### Procedure

1. Navigate to Administration > Maintenance > Archiving Status.

CMS Supervisor displays the current data archiving status for all archiving types, Interval, Daily, Weekly, and Monthly.

2. Change the Archiving type options to narrow or widen your view of the archiving status.

## Viewing archiving status of a single ACD using the PC Client Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Archiving Status in the Operations list.
- 4. Click OK.

CMS Supervisor displays the Archiving Status window.

- 5. Perform one of the following steps to enter information in the ACDs field:
  - Enter the name or number of the ACD directly into the field.
  - Use the history list to select an ACD.
  - Use the Browse button to select an ACD.
- 6. In the **Archiving type** check boxes, clear the archives you do not want to view. If you want to view all archive types, leave the check boxes as check marked and proceed to the next step.
- 7. From the **Actions** menu, select **List all**.

CMS Supervisor displays the Archiving Status - List All window.

For more information about the Archiving Status window, see <u>Archiving status field</u> <u>descriptions</u> on page 423.

#### 😵 Note:

It is also possible to view the archiving status of all members of a single ACD Group using this procedure. Instead of the name or number of a single ACD, enter the name or number of the ACD Group in the **ACD** field.

# Viewing archiving status of all ACDs using the PC Client

#### Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Operations** tab.
- 3. Select Archiving Status in the Operations list.
- 4. Click OK.

CMS Supervisor displays the Archiving Status window.

- 5. If the ACDs field is not clear; go to the Edit menu, and select Clear All.
- 6. Select the type of archives you want to view in the **Archiving type** check boxes.
- 7. From the Actions menu, select List all.

CMS Supervisor displays the Archiving Status - List All window.

For more information about the Archiving Status window, see <u>Archiving status field</u> <u>descriptions</u> on page 423.

## Archiving status field descriptions

The following table lists the fields and the associated descriptions for the Archiving Status window:

Name	Description	
ACD	Displays the name of the ACD.	
Tenant	Displays whether archiving is done for all tenants or individual tenants for the ACD.	
Archive Type Displays which archive type is being displayed in that row of dat		

Table continues...

Name	Description	
Status	Displays the archiving status of the ACD.	
	The three archive status indications are:	
	- "Finished" - The last archive has been completed	
	- "Running" - The archive is currently running	
	- "Not run" - The archive has never run	
Date	Displays the date the last archive completed for the ACD.	
Time	Displays the time the last archive completed for the ACD.	
Next Scheduled	Displays the date and time of the next-scheduled archive.	
	Dates and times will not appear for the Interval archiving. Interval archives occur at the end of each interval: 15, 30, or 60 minutes.	
Time ZoneDisplays the time zone used for that archiving period. Default meaused the master ACD time zone.		
Tenant Name	Displays the tenant name that belongs to the archived data.	

# Viewing firewall status using the Web Client

#### About this task

Use this procedure to view the status of an IPv4 or IPv6 firewall settings.

#### Before you begin

The firewall must be running on the system to see any status.

#### Procedure

#### 1. Navigate to Administration > Maintenance > Firewall Status.

CMS Supervisor displays the Firewall Status window.

2. In the Interface Type field, select either IPv4 or IPv6.

CMS Supervisor displays the firewall status for the selected IP version.

# Viewing the CMS licensed features and status

#### Procedure

Navigate to Administration > Maintenance > License Status.

CMS Supervisor displays the License Status window. The license shows the current status, what features are licensed, along with quantities of the license, and any license violations.

# Administering LDAP

## **About LDAP integration**

CMS supports the use of Lightweight Directory Access Protocol (LDAP) Active Directory (AD) integration for CMS user management. It supports Active Directory for the Windows Server 2008, 2008 R2, 2012, 2012 R2, 2016, and 2019 versions. CMS can integrate with only a single AD system, not multiple AD systems, and Azure AD is not supported. The CMS user interface and management features do not change the CMS user experience when activating the LDAP integration.

With LDAP integration, CMS users authenticate against the configured LDAP server when a user logs on to CMS. With this feature, users need not use the Avaya Services engagement for CMS user password management.

You can administer both traditional CMS users (Linux) and LDAP authenticated users with CMS. When you activate the LDAP feature, the system updates the existing CMS User Data screen to provide an interface and identify the LDAP authenticated users. Once you administer a CMS user with LDAP authentication, the user gains access to CMS and is authenticated against the LDAP server when logging on to CMS. Linux password administration is not required.

With LDAP integration, CMS users can log on using all CMS interfaces, including:

- CMS Supervisor Web Client
- CMS Supervisor PC Client
- CMS ASCII

You can also encrypt the connection to the AD server to avoid exposing personal data over the LDAP connection. Data encryption with LDAP is an optional feature that you enable or disable when you install the LDAP authentication feature package.

#### 😒 Note:

The CMS user ID maps to the Active Directory user or person **objectClass: sAMAccountName** field. The CMS user ID field supports 31 characters. However, for LDAPauthenticated users, you are limited to 20 characters. Special characters are not allowed. Special characters include hyphens, underscores, punctuation of any type, and any diacritical, accented, special characters, or blanks (for example, á, ñ, ç, |).

You must also verify that the user name is configured in a user or person **objectClass** and that the user name is in the **sAMAccountName** field. Verify that the names match exactly (spelling, capitalization, no unexpected spaces, and so on.)

Use the descriptions in this table to help you gather all of the information you need for LDAP integration.

Active Directory Server information	Example	Your Value
Enable optional encrypted LDAP connection (TLS/SSL)	yes, no	
Path to certificate exported from LDAP server – must be provided when LDAP encryption=yes	/tmp/my_AD_cert.cer	
Windows Active Directory server IP Address or Fully Qualified Domain Name An FQDN must be provided	10.20.30.40 or ADServer.company.com	
when LDAP encryption=yes		
Port number for the Active	389 (default for TCP)	
Directory server	689 (default for TLS/SSL)	
	Or specific value from your AD server	

The installation log file for LDAP is found in the CMS security log located at:

/cms/install/logdir/security/cms\_sec.log

# Configuring LDAP

#### Before you begin

Before you can configure LDAP, verify that the LDAP package is installed. If it is not installed, use the feature package installation procedures found in *Maintaining and Troubleshooting Avaya Call Management System*.

#### Procedure

- 1. Enter **cmsadm**.
- 2. Enter the number that corresponds to update LDAP directory server configuration.
- 3. Enter **1** to configure the LDAP Directory Server and press **Enter**.
- 4. Perform one or both of the following tasks:
  - To change the IP address of the LDAP server or the FQDN, place the cursor before the prompt and enter the new IP address of the LDAP or the FQDN and press **Enter**.
  - To change the IP address of the LDAP domain connection string, place the cursor before the prompt and enter the IP address of the LDAP domain connection string, for example, type **DC=com** and press **Enter**.

When you enter the LDAP Server IP Address/FQDN and domain connection string, the system gains access to verify the LDAP Active Directory server. If the system cannot verify the LDAP Active Directory server, the system displays a failure message and prompts you

to enter appropriate information until it establishes a connection to the LDAP Active Directory server.

The system updates the NSS-PAM-LDAPD configuration files, such as nslcd.conf and nsswitch.conf and PAM stack in the PAM file, such as cs-auth. PAM stack authenticates LDAP first and falls through to the Linux authentication. It provides two separate sources for CMS user logins, such as LDAP and Linux users authentication.

5. Update the /cms/db/backupDevice to confirm the LDAP feature installation.

In case of failure, the system displays a failure message with corrective action and exits the cmsadm. The system updates the logs to the admin.log file.

# Advanced Debugging window

Always call Avaya Support before you use this window. For more information, see <u>http://</u><u>support.avaya.com</u>

# Chapter 12: Using administration and maintenance reports

## About administration and maintenance reports

This chapter describes the various administration and maintenance reports you can run using CMS Supervisor. The reports include:

- Dictionary reports (PC Client only)
- Exception reports
- Trunk Group Members reports
- Vector Configuration reports
- Tenant administration reports
- Maintenance reports

# **About Dictionary reports**

In the Dictionary window of the PC Client, use the Reports tab to generate reports on most sections of the Dictionary. These reports can be printed, sent to a file, or displayed on the screen.

#### 😵 Note:

Dictionary reports only work using the PC Client. Information you would see in the Dictionary reports is automatically displayed on the Dictionary windows used with the Web Client.

😵 Note:

Dictionary reports are not available to tenant users. Tenant users are unable to see these reports in the user interface.

## Permissions required to run Dictionary reports

To obtain a report, you need to read the permissions for the Dictionary subsystem.

## **Types of Dictionary reports**

This section provides a description of each of the Dictionary reports.

## **Dictionary ACDs Report**

This report gives you a report of the ACD names you have assigned in the Dictionary ACDs Operation input window and the corresponding ACD number.

## **Dictionary Agent Groups Report**

You can generate reports of the groups(s) you created using the Dictionary Agent Groups Operation input window.

## **Dictionary Call Work Codes Report**

The names you add in the Dictionary Call Work Codes Operation input window are displayed on the Dictionary Call Work Codes report.

## **Dictionary Custom Items Report**

This report gives you a report of all the custom items in the database on the Avaya CMS server.

## **Dictionary Login Identifications Report**

This report gives you a report of the names of agents that you have assigned to Login IDs in the Dictionary Login IDs Operation input window. If you assign names to the login IDs, agent names appear on all reports. However, if you make any additions or changes to login IDs, the changes do not appear on any real-time report that is currently running. You must exit the report and rerun it to see the new agent names.

## **Dictionary Splits/Skills Report**

This report provides the names that have been assigned to splits or skills using the Dictionary Splits/Skills Operation input window. When you assign a split or skill name, that name appears on all split/skill windows and real-time and historical split/skill reports. However, if you make any additions or changes to split or skill names, the changes do not appear on any real-time report that is currently running. You must exit the report and rerun it to see the new split or skill names.

## **Dictionary Standard CMS Items Report**

This report provides a list of all the Standard CMS database items on the Avaya CMS server.

## **Dictionary Tenants Report**

This report displays the tenants defined on the system. You can access this report just like the other dictionary reports.

## **Dictionary Trunk Groups Report**

This report provides the names that have been assigned to trunk groups using the Dictionary Trunk Groups Operation input window. When you assign a trunk group name, that name appears on all trunk group windows and real-time and historical reports. If you make any additions or changes to trunk group names, the changes do not appear on any real-time report that is currently running. You must exit the report and rerun it to see the new trunk group names.

## **Dictionary VDNs Report**

#### Important:

If you have not purchased the Vectoring feature, this window is not available.

This report provides the names that have been assigned to VDNs in the Dictionary VDNs Operation input window. When you assign a VDN name, that name appears on all real-time and historical reports that include that VDN. However, if you make any changes to VDN names, the changes do not appear on any real-time report that is currently running. You must exit the report and rerun it to see the new VDN names.

## **Dictionary Vectors Report**

#### Important:

If you have not purchased the Vectoring feature, this window is not available.

This report provides the names that have been assigned to vectors in the Dictionary Vectors Operation input window. When you assign a vector name, that name appears on all real-time and historical reports that include that vector. However, if you make any additions or changes to the vector names, the changes do not appear on any real-time report that is currently running. You must exit the report and rerun it to see the new vector names.

## Printing dictionary reports

#### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

2. Select the **Reports** tab.

CMS Supervisor displays the Reports window.

- 3. In the **Reports** list, select the Dictionary item on which you want to generate a report.
- 4. Select OK .

CMS Supervisor displays the Reports window.

- 5. Select one of the following options:
  - View Report on Screen

#### Print Report on

To send the report to a printer other than the default printer in the report window, select **Print Report on** and then select the printer button on the right side of the report window. Select the new printer from the Print window.

6. Select OK.

Depending on the option that you selected, the report is either sent to a printer or displayed on the screen.

## Running an agent group members report

#### Procedure

1. From the Controller window, select **Commands > Dictionary**.

CMS Supervisor displays the Dictionary window.

2. Select the **Reports** tab.

CMS Supervisor displays the Reports window.

- 3. In the Reports list, select Agent Group Members.
- 4. Select OK.

CMS Supervisor displays the Dictionary Agent Groups window.

- 5. In the **Agent group name** field, enter the name of the agent group, and then press the Enter key.
- 6. Select one of the following options:
  - View Report on Screen
  - Print Report on
- 7. Select OK.

Depending on the option that you selected, the report is either sent to a printer or displayed on the screen.

## About exception reports

Use the exception reports to view information about exceptions that occur on your system.

# Running the Agent Exceptions by Location report using the Web Client

#### About this task

Use the Agent Exceptions by Location report to view exceptions that have occurred for the selected agents. For each agent exception, the report shows the time, agent, and type of exception.

#### Before you begin

To be able to view data for an agent exception report, the following events must have occurred:

- One or more agent exceptions must have been activated.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.

#### Procedure

1. Navigate to Administration > Exceptions > Reports > Agent Exceptions by Location.

CMS Supervisor displays the Agent Exceptions by Location window.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to run a report.
- 3. In the **Order by** field, select one of the following sorting options:
  - Time The report results are sorted by the time that the exceptions occurred.
  - Agent The report results are sorted by agent name or number.
- 4. In the **Split/Skill** field, select a split or skill using the drop-down list or search on the name or number of a split or skill.
- 5. In the **Date** field, specify the date for the report using one of the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Select a date or range of dates using the calendar icon.

Click Reset to blank out the Date field.

6. Click **Agents** to select the agents to display in the report.

You can enter agent names or login IDs separated by a semicolon (;), or you can use the **Search Results** shuttle to move agents to the **Selected Agents** area. You can add up to 1,000 agents for the report.

- 7. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 8. Click **Exceptions** to select one or more exceptions to include in the report.

Select only those exceptions that are or have been activated during the date specified. If you select exceptions that have not been active during the date specified, the report does not display any data in the report.

- 9. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 10. Click **OK** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report.

# Running the Data Collection Exceptions report using the Web Client

## About this task

Use the Data Collection Exceptions report to view any event that affects the storage of call center data. This includes the following:

- Starting or stopping data collection
- Resetting the clock
- A session (link) is down

## Before you begin

The following items should be read and understood before working with the Data Collection Exceptions report:

- Exceptions must have occurred for the exception type that you want the report to cover. Otherwise, the report is blank.
- User IDs must have the "exception" permission for the ACD in order to be notified of a "linkdown" exception.

## Procedure

1. Navigate to Administration > Exceptions > Reports > Data Collection Exceptions.

CMS Supervisor displays the Data Collection Exceptions window.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to run a report.
- 3. In the **Date** field, specify the date for the report using one of the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Select a date or range of dates using the calendar icon.

Click Reset to blank out the Date field.

4. Click **OK** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report.

## Running the Malicious Call Trace report using the Web Client

## About this task

The Malicious Call Trace feature provides a way for a terminal user to notify a predefined set of users that he or she may be party to a malicious call, such as bomb threats, hackers, and so forth.

The following actions occur when the Malicious Call Trace feature is activated:

- The inbound phone line is prevented from "hanging up".
- Management is immediately alerted.
- The call is recorded (with an additional Communication Manager feature).
- All data regarding the call is stored.

The Malicious Call Trace report is used to view detailed information on the occurrences of these calls. The report shows the date and time when each call occurred, the agent who received the call, and the involved split or skill. If the automatic number identification / station number identification (ANI/SID) network feature has been purchased and implemented, the report also shows where the call originated. This report is only available with CMS Supervisor.

#### Before you begin

The following items should be read and understood before working with the malicious call trace report:

• To view the Malicious Call Trace report, the user ID used to log in to this CMS Supervisor session requires the "exception" permission for the split/skill that received the malicious call.

#### Procedure

1. Navigate to Administration > Exceptions > Reports > Malicious Call Trace by Location.

CMS Supervisor displays the Malicious Call Trace by Location window.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to run a report.
- 3. In the **Date** field, specify the date for the report using one of the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Select a date or range of dates using the calendar icon.

Click **Reset** to blank out the **Date** field.

4. Click **OK** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report.

## Running the Split or Skill Exceptions report using the Web Client

## About this task

The Split or Skill Exceptions report is used to view exceptions that have occurred for the selected splits or skills. For each split or skill exception, the report shows the time and type of exception.

## Before you begin

To be able to view data for a Split or Skill Exceptions report, the following events must have occurred:

- One or more split or skill exceptions must have been activated.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.
- The user ID used to run the report must have the "read" permission for the Exceptions subsystem and the affected splits or skills as well as the "exceptions" permission for all affected splits or skills.

#### Procedure

1. Navigate to Administration > Exceptions > Reports > Split/Skill Exceptions.

CMS Supervisor displays the Split/Skill Exceptions window.

- 2. In the Current ACD drop-down list, select the ACD for which you want to run a report.
- 3. In the **Order by** field, select one of the following sorting options:
  - Time The report results are sorted by the time that the exceptions occurred.
  - Split/Skill The report results are sorted by the split or skill number.
- 4. In the **Date** field, specify the date for the report using one of the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Select a date or range of dates using the calendar icon.

Click Reset to blank out the Date field.

5. Click **Split/Skill** to select the splits or skills to display in the report.

Enter a split or skill number or a series of split or skill numbers separated by semicolons (;) to display the results in the **Search Results** shuttle. Move the splits or skills to the **Selected Split(s)/Skill(s)** area. You can add up to 1,000 splits or skills for the report.

- 6. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 7. Click **Exceptions** to select one or more exceptions to include in the report.

Select only those exceptions that are or have been activated during the date specified. If you select exceptions that have not been active during the date specified, the report does not display any data in the report.

- 8. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 9. Click **OK** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report.

# Running the Trunk Group by Location Exceptions report using the Web Client

## About this task

Use the Trunk Group by Location Exceptions to view exceptions that have occurred for the selected trunk groups. For each trunk group exception, the report shows the time and type of exception.

To be able to view data for a Trunk Group by Location Exceptions report, the following events must have occurred:

- One or more trunk group exceptions must have been activated.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.

#### Procedure

1. Navigate to Administration > Exceptions > Reports > Trunk Group Exceptions by Location.

CMS Supervisor displays the Trunk Group Exceptions by Location window.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to run a report.
- 3. In the **Order by** field, select one of the following sorting options:
  - Time The report results are sorted by the time that the exceptions occurred.
  - Trunk Group The report results are sorted by the trunk group.
  - Trunk Location The report results are sorted by trunk location.
- 4. In the **Date** field, specify the date for the report using one of the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Select a date or range of dates using the calendar icon.

Click Reset to blank out the Date field.

5. Click **Trunk Groups** to select the trunk groups to display in the report.

Enter a trunk group number or a series of trunk group numbers separated by semicolons (;) to display the results in the **Search Results** shuttle. Move the trunk groups to the **Selected Trunk Group(s)** area. You can add up to 1,000 trunk groups for the report.

- Click OK to use the selected options. Click Cancel to close the window and discard the selected options.
- 7. Click **Exceptions** to select one or more exceptions to include in the report.

Select only those exceptions that are or have been activated during the date specified. If you select exceptions that have not been active during the date specified, the report does not display any data in the report.

- 8. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 9. Click **OK** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report.

## **Running the VDN Exceptions report using the Web Client**

#### About this task

Use the VDN Exceptions report to view exceptions that have occurred for the selected VDN. For each VDN exception, the report shows the time and type of exception.

#### Before you begin

To be able to view data for a VDN exception report, the following events must have occurred:

- One or more VDN exceptions must have been activated.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.

#### Procedure

1. Navigate to Administration > Exceptions > Reports > VDN Exceptions.

CMS Supervisor displays the VDN Exceptions window.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to run a report.
- 3. In the **Order by** field, select one of the following sorting options:
  - Time The report results are sorted by the time that the exceptions occurred.
  - VDN The report results are sorted by the VDN.
  - Vector The report results are sorted by vector.
- 4. In the **Date** field, specify the date for the report using one of the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Select a date or range of dates using the calendar icon.

Click Reset to blank out the Date field.

5. Click **VDNs** to select the VDNs to display in the report.

Enter a VDN or a series of VDNs separated by semicolons (;) to display the results in the **Search Results** shuttle. Move the VDNs to the **Selected VDN(s)** area. You can add up to 1,000 VDNs for the report.

- 6. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 7. Click **Exceptions** to select one or more exceptions to include in the report.

Select only those exceptions that are or have been activated during the date specified. If you select exceptions that have not been active during the date specified, the report does not display any data in the report.

- 8. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 9. Click **OK** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report.

## **Running the Vector Exceptions report using the Web Client**

#### About this task

Use the Vector Exceptions report to view exceptions that have occurred for the selected vectors. For each vector exception, the report shows the time and type of exception.

#### Before you begin

To be able to view data for a Vector Exceptions report, the following events must have occurred:

- One or more vector exceptions must have been activated at some time in the past.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.

#### Procedure

1. Navigate to Administration > Exceptions > Reports > Vector Exceptions.

CMS Supervisor displays the Vector Exceptions window.

- 2. In the Current ACD drop-down list, select the ACD for which you want to run a report.
- 3. In the **Order by** field, select one of the following sorting options:
  - Time The report results are sorted by the time that the exceptions occurred.
  - Vector The report results are sorted by vector.
- 4. In the **Date** field, specify the date for the report using one of the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Select a date or range of dates using the calendar icon.

Click **Reset** to blank out the **Date** field.

5. Click Vectors to select the vectors to display in the report.

Enter a vector or a series of vectors separated by semicolons (;) to display the results in the **Search Results** shuttle. Move the vectors to the **Selected Vector(s)** area. You can add up to 1,000 vectors for the report.

- 6. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 7. Click **Exceptions** to select one or more exceptions to include in the report.

Select only those exceptions that are or have been activated during the date specified. If you select exceptions that have not been active during the date specified, the report does not display any data in the report.

- 8. Click **OK** to use the selected options. Click **Cancel** to close the window and discard the selected options.
- 9. Click **OK** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report.

# Running the Agent Exceptions by Location report using the PC Client

#### About this task

Use the Agent Exceptions by Location report to view exceptions that have occurred for the selected agents. For each agent exception, the report shows the time, agent, and type of exception.

## Before you begin

To be able to view data for an agent exception report, the following events must have occurred:

- One or more agent exceptions must have been activated.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. Select the **Reports** tab.
- 3. In the **ACD** field, select the ACD that contains the agents on which to run the report.
- 4. In the **Reports** list, highlight **Agent Exceptions by Location**.
- 5. Click **OK**.

CMS Supervisor displays the Agent Exceptions window.

- 6. In the **Date** field, specify the date for the report in one of the following date formats:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Enter the relative day; for example, 0 for today, -1 for yesterday, or -7 for one week ago.
  - Enter a relative range; for example, -9-0 causes the report to display data for the past ten days including today.
  - Select a date from the drop-down list.
  - Select a date by using the Browse button.

This is a required field.

7. In the Skill State field, enter the name or number of the split/skill to display in the report.

This is a required field.

8. In the **Agents** field, specify the name or number of the agents to display in the report. This field accepts the specification of multiple agents. Multiple values must be separated by a semicolon (;).

This is a required field.

- 9. In the **Order by** field, select one of the following sorting options:
  - Agent The report results are sorted by agent name or number.
  - Time The report results are sorted by the time that the exceptions occurred.
- 10. In the **Exceptions** field, select one or more exceptions to include in the report.

Select only those exceptions that are or have been activated during the date specified. If you select exceptions that have not been active during the date specified, the report does not display any data in the report.

- 11. In the **Destination** group, select the output option of the report:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 12. Click OK.

CMS Supervisor sends the report to the specified output option.

# Running the Data Collection Exceptions report using the PC Client

## About this task

Use the Data Collection Exceptions report to view any event that affects the storage of call center data. This includes the following:

- Starting or stopping data collection
- Resetting the clock
- A session (link) is down

## Before you begin

The following items should be read and understood before working with the Data Collection Exceptions report:

- Exceptions must have occurred for the exception type that you want the report to cover. Otherwise, the report is blank.
- User IDs must have the "exception" permission for the ACD in order to be notified of a "linkdown" exception.

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. Select the **Reports** tab.
- 3. In the **Reports** list, highlight **Data Collection Exceptions**.
- 4. Click OK.

CMS Supervisor displays the Data Collection Exceptions window.

5. In the ACD field, select the ACD that contains the vector on which to run the report.

This field accepts multiple values. Multiple ACDs must be separated by a semicolon (;).

- 6. In the **Date** field, specify the date to view for the report. Entry of the date can be done through the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Enter the relative day; for example, 0 for today, -1 for yesterday, or -7 for one week ago.
  - Enter a relative range; for example, -9-0 causes the report to display data for the past ten days including today.
  - Select a date from the drop-down list.
  - Select a date by using the Browse button.

This is a required field.

- 7. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 8. Click **OK**.

CMS Supervisor sends the data collection exceptions report to the specified output option.

## Running the Malicious Call Trace report using the PC Client

#### About this task

The Malicious Call Trace feature provides a way for a terminal user to notify a predefined set of users that he or she may be party to a malicious call, such as bomb threats, hackers, and so forth.

The following actions occur when the Malicious Call Trace feature is activated:

- The inbound phone line is prevented from "hanging up".
- Management is immediately alerted.
- The call is recorded (with an additional Communication Manager feature).
- All data regarding the call is stored.

The Malicious Call Trace report is used to view detailed information on the occurrences of these calls. The report shows the date and time when each call occurred, the agent who received the call, and the involved split or skill. If the automatic number identification / station number identification (ANI/SID) network feature has been purchased and implemented, the report also shows where the call originated. This report is only available with CMS Supervisor.

## Before you begin

The following items should be read and understood before working with the malicious call trace report:

• To view the Malicious Call Trace report, the user ID used to log in to this CMS Supervisor session requires the "exception" permission for the split/skill that received the malicious call.

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. Select the **Reports** tab.
- 3. In the **ACD** field, select the ACD that contains the vector on which to run the report.
- 4. In the **Reports** list, highlight **Malicious Call Trace by Location**.
- 5. Click **OK**.

CMS Supervisor displays the Malicious Call Trace window.

- 6. In the **Date** field, specify the date to view for the report. Entry of the date can be done through the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Enter the relative day; for example, 0 for today, -1 for yesterday, or -7 for one week ago.
  - Enter a relative range; for example, -9-0 causes the report to display data for the past ten days including today.
  - Select a date from the drop-down list.
  - Select a date by using the Browse button.

This field can accept multiple date values, but the dates must be separated by a semicolon (;). This field is required.

- 7. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 8. Click OK.

CMS Supervisor sends the report to the specified output option.

## Running the Split or Skill Exceptions report using the PC Client

#### About this task

The Split or Skill Exceptions report is used to view exceptions that have occurred for the selected splits or skills. For each split or skill exception, the report shows the time and type of exception.

## Before you begin

To be able to view data for a Split or Skill Exceptions report, the following events must have occurred:

- One or more split or skill exceptions must have been activated.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.
- The user ID used to run the report must have the "read" permission for the Exceptions subsystem and the affected splits or skills as well as the "exceptions" permission for all affected splits or skills.

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. Select the **Reports** tab.
- 3. In the **ACD** field, select the ACD that contains the split or skill on which to run the report.
- 4. In the **Reports** list, highlight **Split/Skill Exceptions**.
- 5. Click OK.

CMS Supervisor displays the Split/Skill Exceptions window.

- 6. In the **Date** field, specify the date to view for the report. Entry of the date can be done through the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Enter the relative day; for example, 0 for today, -1 for yesterday, or -7 for one week ago.
  - Enter a relative range; for example, -9-0 causes the report to display data for the past ten days including today.
  - Select a date from the drop-down list.
  - Select a date by using the Browse button.

This is a required field.

- 7. In the **Splits/Skills** field, specify the name or number of one or more splits or skills to run the report against. Entry of the split or skill can be done through the following methods:
  - Enter the name or number of the split or skill.
  - Select the split or skill from the drop-down list.
  - Select the split or skill by using the Browse button.

Multiple splits or skills can be entered in this field, but must be separated by a semicolon (;). This is a required field.

- 8. In the **Order by** field, select one of the following sorting options:
  - Split/Skill The report results are sorted by split or skill name or number.
  - **Time** The report results are sorted by the time the exceptions occurred.
- 9. In the **Exceptions** field, select one or more exceptions to include in the report.

Only those exceptions that have been activated in the past should be selected. Selecting exceptions that have not been activated will not return any data in the report.

- 10. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 11. Click OK.

CMS Supervisor sends the report to the specified output option.

# Running the Trunk Group by Location Exceptions report using the PC Client

## About this task

Use the Trunk Group by Location Exceptions to view exceptions that have occurred for the selected trunk groups. For each trunk group exception, the report shows the time and type of exception.

To be able to view data for a Trunk Group by Location Exceptions report, the following events must have occurred:

- One or more trunk group exceptions must have been activated.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.

## Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. Select the Reports tab.
- 3. In the **ACD** field, select the ACD that contains the trunk group on which to run the report.
- 4. In the **Reports** list, highlight **Trunk Group Exceptions by Location**.
- 5. Click OK.

CMS Supervisor displays the Trunk Group Exceptions window.

- 6. In the **Date** field, specify the date to view for the report. Entry of the date can be done through the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Enter the relative day; for example, 0 for today, -1 for yesterday, or -7 for one week ago.
  - Enter a relative range; for example, -9-0 causes the report to display data for the past ten days including today.
  - Select a date from the drop-down list.
  - Select a date by using the Browse button.

This is a required field.

- 7. In the **Trunk Groups** field, specify the name or number of one or more trunk groups to run the report against. Entry of the trunk group can be done through the following methods:
  - Enter the name or number of the trunk group.

- Select the trunk group from the drop-down list.
- Select the trunk group by using the Browse button.

Multiple trunk groups can be entered in this field, but must be separated by a semicolon (;).

This is a required field.

- 8. In the **Order by** field, select one of the following sorting options:
  - Trunk Groups The report results are sorted by trunk group number.
  - Trunk Location The report results are sorted by individual trunks.
  - **Time** The report results are sorted by the time the exceptions occurred.
- 9. In the **Exceptions** field, select one or more exceptions to include in the report.

Select only those exceptions that are or have been activated during the date specified. If you select exceptions that have not been active during the date specified, the report does not display any data in the report.

**Audio difficulty** is a trunk group exception that can be requested on a report even though it cannot be administered in trunk group exception operations.

- 10. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 11. Click **OK**.

CMS Supervisor sends the report to the specified output option.

## **Running the VDN Exceptions report using the PC Client**

## About this task

Use the VDN Exceptions report to view exceptions that have occurred for the selected VDN. For each VDN exception, the report shows the time and type of exception.

## Before you begin

To be able to view data for a VDN exception report, the following events must have occurred:

- One or more VDN exceptions must have been activated.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.

## Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. Select the **Reports** tab.
- 3. In the **ACD** field, select the ACD that contains the VDN on which to run the report.
- 4. In the **Reports** list, highlight **VDN Exceptions by Location**.
- 5. Click OK.

CMS Supervisor displays the VDN Exceptions window.

- 6. In the **Date** field, specify the date to view for the report. Entry of the date can be done through the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Enter the relative day; for example, 0 for today, -1 for yesterday, or -7 for one week ago.
  - Enter a relative range; for example, -9-0 causes the report to display data for the past ten days including today.
  - Select a date from the drop-down list.
  - Select a date by using the Browse button.

This is a required field.

- 7. In the **VDNs** field, specify the name or number of one or more VDNs to run the report against. Entry of the VDN can be done through the following methods:
  - Enter the name or number of the VDN.
  - Select the VDN from the drop-down list.
  - Select the VDN by using the Browse button.

Multiple VDNs can be entered in this field, but must be separated by a semicolon (;). This is a required field.

- 8. In the **Order by** field, select one of the following sorting options:
  - Time The report results are sorted by the time the exceptions occurred.
  - VDNs The report results are sorted by VDN name or number.
  - Vectors The report results are sorted by vector.
- 9. In the **Exceptions** field, select one or more exceptions to include in the report.

Select only those exceptions that have been activated at some point in the past. Selecting exceptions that have not been activated will not return any data in the report.

- 10. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 11. Click **OK**.

CMS Supervisor sends the report to the specified output option.

## **Running the Vector Exceptions report using the PC Client**

## About this task

Use the Vector Exceptions report to view exceptions that have occurred for the selected vectors. For each vector exception, the report shows the time and type of exception.

## Before you begin

To be able to view data for a Vector Exceptions report, the following events must have occurred:

- One or more vector exceptions must have been activated at some time in the past.
- The exceptions must have occurred at some point. Otherwise, the report is blank.
- Active exceptions must be specified in the input window so that they are included in the report.

#### Procedure

1. From the Controller window, select **Commands** > **Exceptions** on the menu bar.

CMS Supervisor displays the Exceptions window.

- 2. Select the **Reports** tab.
- 3. In the **ACD** field, select the ACD that contains the vector on which to run the report.
- 4. In the **Reports** list, highlight **Vector Exceptions**.
- 5. Click OK.

CMS Supervisor displays the Vector Exceptions window.

- 6. In the **Date** field, specify the date to view for the report. Entry of the date can be done through the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Enter the relative day; for example, 0 for today, -1 for yesterday, or -7 for one week ago.
  - Enter a relative range; for example, -9-0 causes the report to display data for the past ten days including today.
  - Select a date from the drop-down list.
  - Select a date by using the Browse button.

This is a required field.

- 7. In the **Vectors** field, specify the name or number of one or more vectors to run the report against. Entry of the vector can be done through the following methods:
  - Enter the name or number of the vector.
  - Select the vector from the drop-down list.
  - Select the vector by using the Browse button.

Multiple vectors can be entered in this field, but must be separated by a semicolon (;). This is a required field.

- 8. In the **Order by** field, select one of the following sorting options:
  - Time The report results are sorted by the time the exceptions occurred.
  - Vectors The report results are sorted by vector name or number.
- 9. In the Exceptions field, select one or more exceptions to include in the report.

The exceptions selected in this field should be those that have been activated at some point in the past. Selecting exceptions that have not been activated will not return any data in the report.

- 10. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 11. Click OK.

CMS Supervisor sends the report to the specified output option.

## **About Trunk Group Members reports**

The Trunk Group Members report is used to view the equipment locations of all the trunks that are in a particular trunk group. The report lists the selected trunk groups in numerical order, each trunk group's assigned name, and the equipment location of each trunk in the trunk group. If the trunk group does not have an assigned name, the **Trunk Group Name** field shows the trunk group number. Also, if the trunk group has no trunks assigned to it, the equipment location field is blank.

## Before using the Trunk Group Members report

The following items should be read and understood before working with the Trunk Group Members report:

- Custom or designer reports cannot be created from the Trunk Group Members report.
- The link to the Communication Manager system must be active in order to run this report.

## Permissions required to use the Trunk Group Members report

To run a Trunk Group Members report, the user ID used to log in to this session requires "read" permission for the Call Center Administration subsystem and all affected trunk groups.

## Running the Trunk Group Members report using the Web Client Procedure

1. Navigate to Administration > Call Center Administration > Reports > Trunk Group Members.

CMS Supervisor displays the Trunk Group Members window.

- 2. In the Current ACD drop-down list, select the ACD for which you want to run a report.
- 3. Click **Trunk Group** to select the trunk groups to display in the report.

Enter a trunk group number or a series of trunk group numbers separated by semicolons (;) to display the results in the **Search Results** shuttle. Move the trunk groups to the **Selected Trunk Group(s)** area. You can add up to 32 trunk groups for the report.

4. Click **OK** to run the report. Click **Cancel** to discard the selected report parameters.

CMS Supervisor displays the report.

# Running the Trunk Group Members report using the PC Client Procedure

1. From the Controller window, select **Commands** > **Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. On the Call Center Administration window, select the Reports tab.
- 3. In the **ACD** field, select the ACD for which the report will run.
- 4. In the **Reports** list, highlight **Trunk Group Members**.
- 5. Click **OK**.

Supervisor displays the Trunk Group Members window.

6. In the **Trunk Groups** field, enter the numbers or names of the trunk groups that are to be used in the report.

Multiple trunk groups must be separated by a semicolon (;).

- 7. In the **Destination** group, select the output option of the report:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** Sends the report to the printer that is specified in the associated field. To change the specified printer, select the **Select printer** button located on the right side of this group.
- 8. Select OK.

Supervisor runs the report and sends it to the specified destination.

# **About Vector Configuration reports**

Vector Configuration reports display the following items that are associated with a vector:

- Trunk group
- Trunk group name
- VDN
- VDN name
- Vector
- Vector name
- 1st, 2nd, and 3rd skill preferences
- 1st, 2nd, and 3rd skill names

## Before using the Vector Configuration report

The following items should be read and understood before running Vector Configuration reports:

- A vector may appear in a report even if it is not associated with a trunk group or VDN.
- A vector may appear in a report even if it does not contain any steps.
- A custom or designer report cannot be created from a vector configuration report.
- A go to vector step can cause a trunk group or VDN to carry calls to another vector to which the VDN being used is not assigned. Trunk groups and VDNs that carry calls to a secondary vector in this manner do not appear in the vector configuration report for those secondary vectors.

## Permissions required to use the Vector Configuration report

Depending on the procedure that you want to perform, you need the following permissions:

• To view a Vector Configuration report, the user ID used to log in to this session requires "read" permission for the Call Center Administration subsystem and all vectors to be listed on the report. Permissions are not required for the trunk groups and VDNs that are associated with the specified vectors.

## Running the Vector Configuration report using the Web Client

## Procedure

1. Navigate to Administration > Call Center Administration > Reports > Vector Configuration.

CMS Supervisor displays the Vector Configuration window.

- 2. In the **Current ACD** drop-down list, select the ACD for which you want to run a report.
- 3. Click Vectors to select the vectors to display in the report.

Enter a vector or a series of vectors separated by semicolons (;) to display the results in the **Search Results** shuttle. Move the vectors to the **Selected Vector(s)** area. You can add up to 1,000 vectors for the report.

4. Click **OK** to run the report. Click **Cancel** to discard the selected report parameters.

CMS Supervisor displays the report.

## Running the Vector Configuration report using the PC Client Procedure

1. From the Controller window, select **Commands > Call Center Administration**.

CMS Supervisor displays the Call Center Administration window.

- 2. Select the Reports tab.
- 3. In the **ACD** field, select the ACD containing the vector on which the report will be run.
- 4. In the **Reports** list, highlight **Vector Configuration**.
- 5. Click **OK**.

Supervisor displays the Vector window.

6. In the **Vectors** field, enter the name or number of the vector for which the report will be run.

Multiple vectors can be entered in this field but must be separated by a semicolon (;).

- 7. In the **Destination** group, select the output option of the report:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** Sends the report to the printer that is specified in the associated field. To change the specified printer, select the **Select printer** button located on the right side of this group.
- 8. Select OK.

Supervisor runs the report and sends it to the specified destination.

## About tenant administration reports

Use the Tenant Agent Group Members report to view all of the administered tenants, tenant agent groups, agents, and agent login IDs.

# Running the Tenant Agent Group Members report using the Web Client

## Procedure

1. Navigate to **Tenant Administration > Reports > Tenant Agent Group Members**.

CMS Supervisor displays the Tenant Agent Group Members window showing the report data for the current ACD.

2. In the **Current ACD** drop-down list, select the ACD for which you want to run a report.

CMS Supervisor displays the Tenant Agent Group Members window showing the report data for the selected ACD.

# Running the Tenant Agent Group Members report using the PC Client

## Procedure

1. From the Controller window, select **Commands** > **Tenant Administration**.

CMS Supervisor displays the Tenant Administration window.

- 2. Select the **Reports** tab.
- 3. Select Tenant Agent Group Members.

CMS Supervisor displays the Tenant Administration Agent Group Members window.

- 4. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 5. Click **OK**.

CMS Supervisor sends the report to the specified output option.

## Running the Tenant Agent Groups report using the PC Client

## Procedure

1. From the Controller window, select **Commands > Tenant Administration**.

CMS Supervisor displays the Tenant Administration window.

- 2. Select the **Reports** tab.
- 3. Select Tenant Agent Groups.

CMS Supervisor displays the Tenant Administration Agent Groups window.

- 4. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 5. Click OK.

CMS Supervisor sends the report to the specified output option.

## About maintenance reports

This section provides information about setting up and running maintenance reports. CMS administrators and users with read permission for the Maintenance subsystem can display the maintenance reports.

Maintenance reports:

- Identify problems and facilitate the work necessary to fix problems.
- Aid Services personnel in clearing problems in your system.
- Track changes made to the system by administrative users.

## About the ACD Administration Log report

The ACD Administration Log provides an audit trail for all administrative changes made to an ACD by CMS administrative users. The administrative changes include changes to agents, skills, and any other ACD-related features. The ACD Administration Log records real-time administrative changes made by a user through CMS Supervisor or the CMS ASCII interface. The log also records the administrative changes made by a user through a scheduled timetable or a CMS Supervisor script. You can view all of these log entries using the ACD Administration Log report.

## Before using the ACD Administration Log report

The following items should be read and understood before working with the ACD Administration Log report:

- The maximum capacity for the log is set at 30,000 records and cannot be changed. When the table size exceeds 30,000 records, the 100 oldest records will be deleted.
- This report can be scheduled through a CMS timetable or a CMS Supervisor script.
- The historical database items of the CMS ACD Administration Log are not available for use with the CMS Supervisor Report Designer tool. The menu option for this report will not display the Designer option. It will, however, behave in the same manner as drill-down reports.

## Permissions required to use the ACD Administration Log report

To view the ACD Administration Log report, the user ID must have "read" permission for the Maintenance subsystem.

## Important:

If the ACD Administration Log report is run to display all 30,000 records, your PC should have no less than 200 MB of free disk space to allow for the caching of this data.

# Running the ACD Administration Log report using the Web Client

#### Procedure

1. Navigate to Administration > Maintenance > Reports > ACD Admin Log Report.

CMS Supervisor displays the ACD Admin Log Report window.

- 2. In the available fields, enter the data to use in the report. For a description of the ACD Administration Log window fields, see <u>ACD Administration Log report field descriptions</u> on page 456 for additional information.
- 3. Click **Run** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report data. Since there can be up to 30,000 rows of data, the report might take several minutes to display on the screen.

## Running the ACD Administration Log report using the PC Client Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Reports** tab.
- 3. In the **Reports** list, select **ACD Administration Log Report**.

It is not necessary to select an ACD in the **ACD** field as this feature allows ACD specification in a subsequent dialog.

4. Click OK.

Supervisor displays the ACD Administration Log window.

The height of this dialog box varies according to the current screen resolution of your PC. A higher screen resolution results in more fields being displayed.

For a description of the ACD Administration Log window fields, see <u>ACD Administration</u> <u>Log report field descriptions</u> on page 456 for additional information.

5. In the available fields, enter the data to use in the report.

The data can also be selected through the drop-down history lists or through the Browse buttons.

The more fields that you specify, the more restricted the data will be that is used in the report. If all of the input fields are left blank, all records will be displayed.

- 6. In the **Destination** group, select one of the following output options:
  - View Report on Screen The report is displayed on the screen.
  - **Print Report on** The report is sent to the specified printer. Any printer available to the PC can be used and selected through the button at the right of the field.
- 7. Select OK.

Supervisor displays the ACD Administration Log with the specified data.

## ACD Administration Log report field descriptions

Name	Description	
CMS User IDs	The user IDs to display in the report. If changes were made to the ACD with the specified user IDs, those user IDs and the associated changes are displayed.	
Dates	The date or range of dates to be covered in the report. Only those administrative changes made on or within the date(s) specified will be present in the report.	
Times	A range of time for which log entries are to be displayed. Only those administrative changes made within this time range will be present in the report.	
ACDs(n)	The ACDs to include in the report.	
VDNs(n)	The VDNs on the ACD to include in the report.	
Vectors(n)	The Vectors on the ACD to include in the report.	
Agents(n)	The login IDs on the ACD to include in the report.	

## About the Maintenance Error Log report

Use the Maintenance Error Log report to help you in working on system problems and to help Services personnel in clearing problems from your system. The Maintenance Error Log report displays a chronological list of warnings, information, and errors detected by CMS.

## Before using the Maintenance Error Log report

The following items should be read and understood before working with the Maintenance Error Log report:

- The Maintenance Error Log report can contain 500 entries. When the log reaches 500 records, the next record will overwrite the oldest record.
- The entries in the Maintenance Error Log report are displayed in chronological order, starting with the most recent entry.
- You can search the log by error severity or by error code

- The results of all archives and backups are written to the Maintenance Error Log.
- If you have the CMS Forecast feature, the results of the Forecast Manager are written to the Maintenance Error Log report.

## Running the Maintenance Error Log report using the Web Client Procedure

1. Navigate to Administration > Maintenance > Reports > Data Collection Exceptions.

CMS Supervisor displays the Error Log Report window.

- 2. In the **ACD** drop down list, select **All ACDs** or select an individual ACD for which you want to see an error log report. Selecting an ACD Group shows the error logs for only the member ACDs of that group.
- 3. In the **Error codes** field, leave it blank if you want to display all error codes in the error log report. If you only want the report to include specific error codes, enter the codes in the **Error codes** field.
- 4. In the **Severities** drop down list, select **All Severities** to include errors of any severity level, or select the severity level you want to see in the report.

See <u>Severity of errors</u> on page 458 for additional information on error code classifications.

- 5. In the **Date** field, specify the date for the report using one of the following methods:
  - Enter MM/DD/YY format; for example, 10/06/20.
  - Select a date or range of dates using the calendar icon.

Click **Reset** to blank out the **Date** field.

6. Click **Run** to run the report. Click **Clear** to discard the selected report parameters.

CMS Supervisor displays the report data.

See <u>Maintenance Error Log messages</u> on page 458 for additional information about the error messages.

## Running the Maintenance Error Log report using the PC Client

## Procedure

1. From the Controller window, select **Tools > Maintenance**.

CMS Supervisor displays the Maintenance window.

- 2. Select the **Reports** tab.
- 3. Select Error Log Report in the Reports list.
- 4. Click OK.

Supervisor displays the Maintenance Error Log window.

5. In the **ACD** drop down list, select **All ACDs** or select an individual ACD for which you want to see an error log report. Selecting an ACD Group shows the error logs for only the member ACDs of that group.

- 6. In the **Error codes** field, leave it blank if you want to display all error codes in the error log report. If you only want the report to include specific error codes, enter the codes in the **Error codes** field.
- 7. In the **Severities** drop down list, select **All Severities** to include errors of any severity, or select the severity level you want to see in the report.

See <u>Severity of errors</u> on page 458 for additional information on error code classifications.

- 8. In the **Date** field, enter the amount of time that the report will include through one of the following methods:
  - Enter the date(s) in the MM/DD/YY format.
  - Use the history list to select the dates.
  - Use the Browse button to select the dates
  - Enter the date in relative format; for example, 0 for today, -1 for yesterday.
- 9. Select one of the following **Destination** options:
  - To display the Maintenance Error Log on the monitor, select View Report on Screen.
  - To send the Maintenance Error Log to a printer, select **Print Report on**.
- 10. Select OK.

CMS Supervisor displays the report data.

See <u>Maintenance Error Log messages</u> on page 458 for additional information about the error messages.

## **Severity of errors**

The following list describes the error classifications in the Maintenance Error Log:

- ALARM This type of entry could cause the system to crash or fail. You must work with Avaya Services to avoid the possibility of system failure.
- ERROR This type of entry needs immediate action. For example, a backup may not be working properly.
- INFO This type of entry does not need immediate action but is listed either to let you know that some aspect of the system is not operating correctly or to indicate the status of an operation. For example, Successful.

## Maintenance Error Log messages

The Maintenance error codes and related messages are organized by error code number. If any of the solutions do not resolve the problem you are experiencing, contact your CMS services representative. If a reference to a task number is shown in the Maintenance Error Log, give the number to the CMS services personnel.

The following table lists the possible error codes as well as the related information.

Error Code	Message	Reason/Action
500	UNIX error on OPEN, file: <filename></filename>	Could not write a file which is part of a timetable. One or more timetable tasks may be corrupted.
505	UNIX error on WRITE, file: File system may be out of space.	Error in writing the file. Potential file space problem.
505	The following two errors are found together: UNIX error on WRITE, file: SIGPIPE signal caught during printing, print request is incomplete or failed	Could not print a file. The CMS server probably does not have a default system line printer assigned, and the user probably does not have a CMS default printer assigned.
	UNIX error on WRITE, file: lp. The user may have no default printer assigned and the UNIX(r) system administration for a default system line printer has not been done.	Using the operating system documentation, administer a default printer. Select the <f3> key -&gt; <b>Options</b> &gt; <b>Default printer</b> to assign a default printer to a user. Ensure that the user has the appropriate permissions to the printer in the User Permissions subsystem.</f3>
555	UNIX error on EXEC: Couldn't execute the following command: <user command=""></user>	System is too busy for command to be processed.
555	UNIX error on EXEC: CMS couldn't run because crt_io_man wouldn't execute	System is too busy for command to be processed.
556	UNIX error on FORK: CMS couldn't run because the system was too busy.	System is too busy for command to be processed.
556	UNIX error on FORK: UNIX process limit exceeded, system is too busy	CMS was unable to start a process. This occurs most likely if a user is logged into CMS through multiple terminals.
		Make sure each user logs in on only one CMS terminal/session at a time. If this message occurs when timetables are running, try adjusting the starting times of the timetables so that fewer are running simultaneously. If it occurs when running , try rewriting the <b>Main Menu Addition</b> to use fewer simultaneous operating system processes.
556	UNIX error on FORK: Call records not being sent. Call Services.	The process for transferring external call records could not be started.
		Call Services.
557	UNIX call error: UNIX process limit exceeded. System is too busy	This error could occur for multiple reasons. Call services for assistance.
		Table continues

Error Code	Message	Reason/Action
557	UNIX call error: uucp failed	The uucp file transfer mechanism for the External Call Records feature has failed.
		The system will automatically retry the transfer. If it fails repeatedly, call Services.
1001	UNIX error on NEW Agent upper bound has been reached. You have administered more Agent Exceptions than are allocated. You must either delete unneeded exceptions or allocate more space in System Setup: Data Storage Allocation.	The exception distributor process (ED) is attempting to log more agent exceptions than will fit in the storage space allocated for them. Delete unneeded exceptions or allocate more space in <b>Data Storage Allocation</b> > <b>System Setup</b> .
1001	UNIX error on NEW Split upper bound has been reached. You have administered more Split Exceptions than are allocated. You must either delete unneeded exceptions or allocate more space in System Setup: Data Storage Allocation.	The exception distributor process (ED) is attempting to log more Split exceptions than will fit in the storage space allocated for them. Delete unneeded exceptions or allocate more space in <b>Data Storage Allocation</b> > <b>System Setup</b> .
1001	UNIX error on NEW Trunk group upper bound has been reached. You have administered more Trunk Group Exceptions than are allocated. You must either delete unneeded exceptions or allocate more space in System Setup: Data Storage Allocation.	The exception distributor process (ED) is attempting to log more Trunk Group exceptions than will fit in the storage space allocated for them. Delete unneeded exceptions or allocate more space in <b>Data Storage Allocation</b> > <b>System Setup</b> .
1001	UNIX error on NEW VDN upper bound has been reached. You have administered more VDN Exceptions than are allocated. You must either delete unneeded exceptions or allocate more space in System Setup: Data Storage Allocation.	The exception distributor process is attempting to log more VDN exceptions than will fit in the storage space allocated for them. Delete unneeded exceptions or allocate more space in <b>Data Storage Allocation</b> > <b>System Setup</b> .

Error Code	Message	Reason/Action
1001	UNIX error on NEW Vector upper bound has been reached. You have administered more Vector Exceptions than are	The exception distributor process is attempting to log more Vector exceptions than will fit in the storage space allocated for them.
	allocated. You must either delete unneeded exceptions or allocate more space in System Setup: Data Storage Allocation.	Delete unneeded exceptions or allocate more space in <b>Data Storage Allocation</b> > <b>System Setup</b> .
1050	INFORMIX SQL syntax error:	The given SQL command is syntactically incorrect. Usually more details of the error are included. For customers, this error is reported via their custom report and is corrected there. For CMS, this is usually a software problem which may need reporting.
		Correct the SQL statement in the custom report.
1053	INFORMIX insert error	An internal error or a full ACD dbspace is preventing data from being inserted into the ag_actv database table.
		Make sure that there is enough room in the ACD dbspace that holds the table.
1100	IPC error on messages: message queue queue is NN% full	This message is logged when a message queue is more than 75 percent full. Each message queue is checked approximately once every two minutes. If this message is repeatedly logged, CMS is in danger of losing messages that may result in loss of customer data.
		Single occurrences of this message can be ignored. If it happens repeatedly, contact services for assistance. Try reducing your CMS usage while this message is being logged to reduce the chances of losing data. If this message occurs while you are doing a CMS backup, try doing the backup during a less busy period.

Error Code	Message	Reason/Action
1302	PROCESS COMMUNICATIONS (PO) library error, function: ERROR - <harch> receiving too many exceptions too fast. Some exceptions have been discarded. Reduce the number of active exceptions or change thresholds</harch>	Exceptions are being generated faster than interval archiver process can handle them. This is the result of having too many exceptions activated, or having thresholds set to produce too many exceptions. Reduce the number of active exceptions or change thresholds so that fewer exceptions
	so that fewer exceptions are triggered.	are triggered.
1302	PROCESS COMMUNICATIONS (PO) library error, function: ERROR - <idbm> receiving too many exceptions too fast. Some exceptions have been discarded. Reduce the number of active</idbm>	Exceptions are being generated faster than intermediate database manager interface process can handle them. This is the result of having too many exceptions activated, or having thresholds set to produce too many exceptions.
	exceptions or change thresholds so that fewer exceptions are triggered.	Reduce the number of active exceptions or change thresholds so that fewer exceptions are triggered.
1302	PROCESS COMMUNICATIONS (PO) library error, function: ERROR - <spi> receiving too many exceptions too fast. Some exceptions have been discarded. Reduce the number of active exceptions or change thresholds</spi>	Exceptions are being generated faster than the switch interface process can handle them. This is the result of having too many exceptions activated, or having thresholds set to produce too many exceptions. Reduce the number of active exceptions or change thresholds so that fewer exceptions
4050	so that fewer exceptions are triggered.	are triggered.
1350	GENERAL error internal to process: Unable to successfully complete archiving.	Unable to initialize CMS environment. Re-initiate Data Summarizing.
1350	GENERAL error internal to process: Failure in agent exception database table. Agent exception data not being stored. Call Services.	This error message is logged when the exception distributor process is unable to insert rows in the agent exception table. The error can occur when the ACD dbspace holding the agent exception table becomes full. No more agent exceptions can be recorded until the problem is corrected.
1350	GENERAL error internal to process: Failure in link exception database table. Link exception data not being stored. Call Services.	This error message is logged when the exception distributor process is unable to insert rows in the link exception (linkEx) table. The error can occur when the disk partition holding the link exception table becomes full. No more link exceptions can be recorded until the problem is corrected.

Error Code	Message	Reason/Action
1350	GENERAL error internal to process: Failure in malicious call trace exception database table. MCT exception data not being stored. Call Services.	This error message is logged when the exception distributor process is unable to insert rows in the malicious call trace exception (mctEx) table. The error can occur when the disk partition holding the malicious call trace exception table becomes full. No more malicious call exceptions can be recorded until the problem is corrected.
		Call Services.
1350	GENERAL error internal to process: Failure in split exception database table. Split exception data not being stored. Call Services.	This error message is logged when the exception distributor process is unable to insert rows in the split exception (spEx) table. The error can occur when the disk partition holding the split exception table becomes full. No more split exceptions can be recorded until the problem is corrected.
		Call Services.
1350	GENERAL error internal to process: Failure in trunk group exception database table. Trunk group exception data not being stored. Call Services.	This error message is logged when the exception distributor process is unable to insert rows in the trunk group exception table. The error can occur when the disk partition holding the trunk group exception table becomes full. No more trunk group exceptions can be recorded until the problem is corrected.
		Call Services.
1350	GENERAL error internal to process: Failure in VDN exception database table. VDN exception data not being stored. Call Services.	This error message is logged when the exception distributor process is unable to insert rows in the VDN exception (vdnEx) table. The error can occur when the disk partition holding the VDN exception table becomes full. No more VDN exceptions can be recorded until the problem is corrected.
		Call Services.
1350	GENERAL error internal to process: Failure in vector exception database table. Vector exception data not being stored. Call Services.	This error message is logged when the exception distributor process is unable to insert rows in the vector exception (vecEx) table. The error can occur when the disk partition holding the vector exception table becomes full. No more vector exceptions can be recorded until the problem is corrected.
		Call Services.

Error Code	Message	Reason/Action
1350	GENERAL error internal to process: CMS task limit exceeded, system is too busy	This message means that a CMS task cannot be created because CMS is already running the maximum number of tasks.
		Make sure each user logs in to CMS only once. If this message occurs when timetables are running, try adjusting the starting times of the timetables so that fewer are running simultaneously. If it occurs when running <b>Main Menu Addition</b> , try rewriting the <b>Main Menu Addition</b> to use fewer simultaneous operating system processes.
1350	GENERAL error internal to	Item searched for is too large.
	<pre>process: Update failure for <item searched=""> Too much data. Try again with a more restrictive search.</item></pre>	The search needs to be restricted further. Restrict the search to a smaller amount of data.
1350	GENERAL error internal to	Error in searching for item. Disk may be full.
	process: disk may be full.	Clean up unnecessary files from disk.
1350	GENERAL error internal to process: Failure in removing data from database table:	An internal error occurred that prevents data from being deleted from the ag_actv database table.
	ag_actv. Agent Trace data not being stored. Call Services.	Call Services.
1351	GENERAL error in process interface: Invalid action	Something is corrupted with the window interface.
	request.	Exit and re-enter the data summarizing window. Attempt to initiate data summarizing again.
1351	GENERAL error in process interface: Cannot archive a day which interval data does not exist for.	Interval data does not exist for the requested day or any day prior to the requested day. The number of days of interval data saved is based on the <b>Days of</b> <b>Intrahour</b> field set on the Data Storage Allocation window.
		Re-initiate Data Summarizing for a day that is within the number of <b>Days of Intrahour</b> saved. For future reference, the number of <b>Days of Intrahour</b> data can be increased. Disk space must be considered before changing this parameter.

Error Code	Message	Reason/Action
1351	GENERAL error in process interface: Cannot archive the requested week/month. Daily data does not exist for all tables for the week/month beginning xx/xx/xx.	Daily data does not exist for the requested week/month or any week/month prior to the requested day. The number of days of interval data saved is based on the <b>Days of</b> <b>Daily</b> field set on the Data Storage Allocation window.
		Re-initiate Data Summarizing for a week/ month that is within the number of <b>Days of</b> <b>Daily</b> saved. For future reference, the number of <b>Days of Daily</b> data can be increased. Disk space must be considered before changing this parameter. If the number of <b>Days of Daily</b> is changed and intrahour daily data is present for the days of the requested week/month, those days can be archived and the week/month can then be archived.
1351	GENERAL error in process interface: ERROR - <arch> receiving too many archive requests too fast. Some requests</arch>	Too many data summarizing requests (more than 25) have been initiated in a short period of time (approx. 1/2 hour) and cannot all be processed.
	have been discarded.	Determine all data summarizing requests that have been initiated. Once all requests have been processed, verify the requests against the completed archives (as reported in /cms/dc/archive/arch.log). Re- initiate archive for the date and archive (daily/weekly/monthly) for the archives not initiated. In the future, do not initiate all requests at once.
1351	GENERAL error in process interface: Cannot archive a day in the future.	The date of the requested archive has not happened yet.
		Re-initiate the daily archive for a date prior to today.
1351	GENERAL error in process interface: Cannot archive a partial weeks/months data.	The last day for the week/month has not been archived yet.
		Verify that a weekly/monthly archive is not being requested for the current week/month. That is, the end of the week/month has not been reached yet. Re-initiate the weekly/ monthly archive for a week/month in which the last day has already been archived.

Error Code	Message	Reason/Action
1351	GENERAL error in process interface: stopping task id to free up message queue	A message queue is more than 85 percent full and the task that should be reading from the queue is apparently stuck. This message is logged when CMS restarts the task to attempt to clear the error condition. Depending on which task has been stopped, it is likely that some customer data has been lost.
		Report the problem to services. If this error is logged repeatedly, try reducing your CMS usage while this message is being logged to reduce the chances of losing data. If this message occurs while you are doing a CMS backup, try conducting the backup during a less busy period.
1351	GENERAL error in process interface: External applications not started. Set to OFF	When the External Application feature was started, there was some general error. The feature was turned back off because of this error.
		Request help from your External Application provider (Avaya Professional Services Organization).
1351	GENERAL error in process interface: Activate Agent Trace request failed. Try again.	This error is logged when the agent activity recorder process (AAR) has too many messages in its message queue to accept any more. This can occur when many very active agents are being traced, keeping aar's queue full.
		Trace fewer agents or try this request again later.
1351	GENERAL error in process interface: Task < task_num> of timetable <name> may not have completed, window status was: <status></status></name>	Timetable ran and has a status other than Successful.
		Based on what the timetable was, examine the state of things (database, ACD administration, etc) to see if the request completed. If desired, complete the action manually by running CMS now.

Error Code	Message	Reason/Action
1400	SPI session error: data collection session is down	An error has occurred in the X.25 connection to the switch. CMS data is not being collected. CMS will automatically try to restore the link.
		If the link does not re-establish by itself within five minutes, check the cables, modems, and other hardware between the CMS and the switch for any obvious loose connections.
1404	SPI configuration error: Insufficient unmeasured trunks allocated. To avoid further data loss, go to Data Storage Allocation and administer more unmeasured trunk facilities.	There are not enough unmeasured trunks allocated in the CMS realtime database to track all calls. This message is logged once during each data collection interval when the error condition occurs. When this message appears, some call data has already been lost. Data will continue to be lost until more trunk facilities have been allocated.
		Allocate more unmeasured trunk facilities in the Data Storage Allocation screen.
1404	SPI configuration error: Switch and UNIX clocks differ by more than 24 hours. Switch clock is <nn:nn:nn nn=""> UNIX clock is <mm:mm:mm mm=""> Data collection will remain down until switch or UNIX clock is</mm:mm:mm></nn:nn:nn>	CMS requires that the times on the Communication Manager and operating system remains within 24 hours of each other. This is done to prevent an accidental deletion of all historical data if someone were to inadvertently change the clock to a date far into the future.
	reset so they agree.	If the operating system clock is correct but the Communication Manager clock is incorrect, reset the clock at the switch. CMS will bring the link up automatically within five minutes after correcting the switch clock.
1404	SPI configuration error:	Protocol error as explained in the message.
	Extension <number> has been staffed by two different login IDs: <first> and <second>. Data will be tracked only for the last login ID. Ask the agent to log off and log in again with a single login ID.</second></first></number>	Ask the agent to log off and log in again with a single login ID.

Error Code	Message	Reason/Action
1404	One of the following messages will be displayed depending on the switch configuration: Two agents at extensions <ext>in split <num> and <ext>in split <num> are logged in with the same login ID: <id> This may indicate table corruption on the switch. Contact Services to repair table as soon as possible.</id></num></ext></num></ext>	Protocol violation or switch corruption. Try requesting new translations in ACD Status screen. If the problem persists, call Services.
	Two agents at extensions <ext> and <ext>are logged in with the same login ID: <id>. This may indicate table corruption on the switch. Contact Services to repair table as soon as possible.</id></ext></ext>	
1404	One of the following messages will be displayed depending on the switch configuration: SPI configuration error: Agent <logid> at extension <ext>has logged into too many splits: <spl>, and <sp2>. Data will only be tracked for the last split. This may indicate incorrect switch type on CMS for G3.</sp2></spl></ext></logid>	Switch type mismatch, protocol violation or switch table corruption. Try requesting new translations in Data Storage Allocation screen. If the problem persists, call Services.
	SPI configuration error: Agent <logid> at extension <ext> has logged into too many splits: <spl>, <sp2>, <sp3>, and <sp4> . Data will only be tracked for the last split. This may indicate incorrect switch type on CMS for G3.</sp4></sp3></sp2></spl></ext></logid>	
	SPI configuration error: Agent <logid> at extension <ext> has logged into too many splits: <spl>, <sp2>, <sp3>, <sp4>, and <sp5>. Data will only be tracked for the last split. This may indicate incorrect switch type on CMS for G3.</sp5></sp4></sp3></sp2></spl></ext></logid>	Table continues

Error Code	Message	Reason/Action
1406	SPI data message error: ERROR can't new a message (or got illegal opcode)	This generally indicates that there is a mismatch between the administered CMS type on the Communication Manager system and the actual CMS or there is a mismatch between the administered switch type and feature set of the switch on the CMS . This results in message formats being of unexpected lengths. Data is lost since the remainder of the buffer is discarded after the unknown message.
		Determine if the problem happens more than once. Call Services.
1407	SPI timer expired error: there is no response from the switch	CMS has stopped receiving messages from the Communication Manager system. CMS data is not being collected. CMS will automatically try to restore the link.
		At the switch, perform a busy out and release the MIS connection.
1409	SPI ACD administration error: switch was unable to logon agent <logid> with skill <num></num></logid>	For some reason the login failed on the switch. This login may have been part of a Move Agent or Change Agent Skills request which was pending.
		Have the agent try to log in to the skill again. Or put the agent in the AUX workmode for all skills and have no calls on their set. Repeat the administration request. If the request fails again, collect the information from the status window for Services.
1409	One of the following messages will be displayed: SPI ACD administration error: switch unable to move ext <ext></ext>	Previous ACD administration request for moving an agent or changing an agent's skills was pending. When the pending was resolved, the agent could not be moved for
	from split <num> to <num></num></num>	some reason.
	SPI ACD administration error: switch unable to move ext <ext> from split <num></num></ext>	Put the agent in the AUX workmode for all split/skills and have no calls on their set. Repeat the administration request. If the request fails again, collect the information from the status window for Services.
1501	SCREEN MANAGER error: system may be overloaded by real time	CMS is behind on refreshing the real-time reports currently running.
	reports behind by XX seconds.	Run fewer real-time reports or lengthen refresh rates for the reports currently running.

Error Code	Message	Reason/Action
1600	FORECAST status: Forecast Manager failed for mm/dd/yy	Forecast Manager failed in its attempt to perform the daily data collection and/or the current day report for mm/dd/yy.
		If the date is invalid, correct the date and rerun the report. If it is not a problem with the date, call Services for assistance.
1600	FORECAST status: Forecast Manager failed for mm/dd/yy - mm/dd/yy	Forecast Manager failed in its attempt to perform the recollect data for a range of dates mm/dd/yy - mm/dd/yy. The first date is the start date and the second date is the stop date.
		If the dates are invalid, correct the date and rerun the report. If it is not a problem with the date, call Services for assistance.
1700	BACKUP Process out of sync. Contact Services.	A bad message was received from the backup screen. If this occurs, some sort of interference may have occurred in the message queue between the backup process and backup screen. If the problem re-occurs, something is impacting the communication between the processes. Further investigation is necessary to determine the source of the problem.
		Exit the current instance of the backup screen and re-initiate the backup. Verify that the problem does not re-occur.
1701	BACKUP Process out of memory. Contact Services.	If this error occurs, it is when the tape is being verified, but after the backup has already completed successfully. If tape verification is not essential, no further action is necessary. This error indicates a problem with memory allocation.
		Exit the current instance of the backup screen and re-initiate the backup. Verify that the problem does not re-occur.

Error Code	Message	Reason/Action
1702	BACKUP Process startup failed. Contact Services	Any number of startup activities could cause this problem. Most are message and database activities that should never be encountered. If the problem re-occurs, something is peculiar in the environment of the backup process and further investigation is necessary to determine the source of the problem.
		Exit the current instance of the backup screen and re-initiate the backup. Verify that the problem does not re-occur.
1703	BACKUP Volume access failed. Retry Backup.	A problem accessing the backup device has occurred. This problem could range from an invalid backup device to the tape drive requiring cleaning.
		Verify the following:
		<ul> <li>The backup device is administered properly (name corresponds with the operating system administered device)</li> </ul>
		The tape compatibility is correct (320 meg tape for 320 meg drive, etc.).
		• The tape drive is clean.
1704	BACKUP Volume check failed. Retry Backup.	Either the inserted tape is a recent backup and backup was initiated in timetable or backup had difficulty determining the most recent backup (either full or incremental) volume.
		Determine if the inserted tape is associated with the most recent backup (full or incremental). Replace the tape and re- execute backup (or services run br_check).
1705	BACKUP Volume verification	A problem reading the tape exists.
	failed. Retry Backup.	Exit the current instance of the backup screen and re-initiate the backup. Verify that the problem does not re-occur.

Error Code	Message	Reason/Action
1706	BACKUP Table backup failed. Retry Backup. Table=	A problem was encountered either reading the indicated table or writing that table to tape.
		Replace the tape with a new tape (after verifying no problems with the indicated table) and re-execute the backup process. Verify that the problem does not re-occur.
1707	BACKUP Volume span failed. Retry Backup	When verifying the backup tape, a problem was discovered between the current volume and the previous volume. Most likely, the blocks are out of sequence. More specifically, at least 1 block is missing.
		Re-execute the backup process. Verify that the problem does not re-occur.
1708	BACKUP Error in process communication. Retry Backup.	This should never be encountered. A bad message was received from the backup screen (or erroneously from another process). If this occurs, some sort of interference occurred in the message queue between the backup process and backup screen. If the problem re-occurs, something is impacting the communication between the processes. Further investigation is necessary to determine the source of the problem.
		Exit the current instance of the backup screen and re-initiate the backup. Verify that the problem does not re-occur.
1709	BACKUP Backup history update failed. Retry Backup.	This should never be encountered. The backup was completed successfully. A problem exists with the update tables or the process to update the tables.
		Verify that the next backup does not encounter this problem.
1710	BACKUP Process in need of service. Please check the Backup	An acknowledgement window is requiring a response.
	screen.	Respond to the backup acknowledgement window.

Error Code	Message	Reason/Action
1711	INFO Warning backup waited 210/7200 seconds before archive completed.	The backup process waited 210 seconds for the current archiving process to finish. Backups should not be run during the archiving process.
		If this occurs consistently, consider rescheduling your archiving and backup processes so that overlap does not occur.
1711	ERROR backup terminated because archive did not complete within 2 hours.	The backup process waited two hours for the archiving process to be completed and was terminated as a result. Backups should not be run during the archiving process.
		Reschedule the backup and archiving processes so that simultaneous processing does not occur.
1711	BACKUP INFO:	Backup was initiated through a timetable and information is reported (number of volumes and backup completed) simply for information purposes.
		No action required
1750	BACKUP Screen startup failed. Contact Services.	Any number of startup activities could cause this problem. Most problems deal with accessing screen entries and database activities that should never be encountered. If the problem re-occurs, something is peculiar in the environment of the backup process. Further investigation is necessary to determine the source of the problem.
		Exit the current instance of the backup screen and re-initiate the backup. Verify that the problem does not re-occur.
1751	BACKUP Screen execution failed. Retry Backup.	Any number of startup activities could cause this problem. Most problems deal with accessing screen entries and database activities that should never be encountered. If the problem re-occurs, something is peculiar in the environment of the backup process. Further investigation is necessary to determine the source of the problem.
		Exit the current instance of the backup screen and re-initiate the backup. Verify that the problem does not re-occur.

Error Code	Message	Reason/Action
1800	RESTORE Process out of sync. Contact Services.	A bad message was received from the restore screen. If this occurs, some sort of interference occurred in the message queue between the restore process and restore screen. If the problem re-occurs, something is impacting the communication between the processes. Further investigation is necessary to determine the source of the problem.
		Exit the current instance of the restore screen and re-initiate the restore. Verify that the problem does not re-occur.
1801	RESTORE Process out of memory.	A problem with memory allocation exists.
	Contact Services.	Exit the current instance of the restore screen and re-initiate the restore. Verify that the problem does not re-occur.
1802	RESTORE Process startup failed. Contact Services	Any number of startup activities could cause this problem. If the problem re-occurs, something is peculiar in the environment of the restore process and further investigation is necessary to determine the source of the problem.
		Exit the current instance of the restore screen and re-initiate the restore. Verify that the problem does not re-occur.
1803	RESTORE Volume access failed. Retry Restore.	A problem exists accessing the restore device. This could be an invalid restore device, the tape drive requiring cleaning, or a table header format problem (internal error).
		Verify the following:
		• The backup/restore device is administered properly (name corresponds with the operating system administered device).
		• The tape compatibility is correct (320 meg tape for 320 meg drive, etc.).
		• The tape drive is clean.

Error Code	Message	Reason/Action
1804	RESTORE Error in process communication. Retry Restore.	A bad message was received either by the restore screen or the restore process. If this occurs, some sort of interference occurred in the message queue between the restore process and the restore screen. If the problem re-occurs, something is impacting the communication between the processes. Further investigation is necessary to determine the source of the problem.
		Exit the current instance of the restore screen and re-initiate the restore. Verify that the problem does not re-occur.
1805	RESTORE Table restore failed. Retry Restore. Table=	A problem was encountered either reading the indicated table from tape or writing that table into the database.
		Perform a specific table restore for the indicated table. Verify that the problem does not re-occur.
1806	RESTORE INFO: Volume contains no data for ACD=X	This is an Information message indicating that the current table for the indicated ACD does not have data.
		No action required.
1850	RESTORE Screen startup failed. Contact Services.	Any number of startup activities could cause this problem. Most problems result from accessing screen entries that should never be encountered. If the problem re-occurs, something is peculiar in the environment of the restore process and further investigation is necessary to determine the source of the problem.
		Exit the current instance of the restore screen and re-initiate the restore. Verify that the problem does not re-occur.
1851	RESTORE Screen execution failed. Retry Restore.	Updating the status on the screen could cause this problem (although extremely rare). If the problem re-occurs, something is peculiar in the environment of the restore process and further investigation is necessary to determine the source of the problem.
		Exit the current instance of the restore screen and re-initiate the restore. Verify that the problem does not re-occur.

Error Code	Message	Reason/Action
1900	SYSTEM ME SSA GE OVERLOAD: Agent Trace (AAR) is overloaded, some agent trace data lost. Turn off traces for some agents to prevent possible further overloading.	AAR is receiving messages faster than it can process them. Turn off traces for some agents.
1900	SYSTEM ME SSA GE OVERLOAD: Call History Recorder (ch_rec) overloaded, some call record data lost.	Data is being sent faster than it can be processed. This usually indicates that the system as a whole is overloaded. Stop some reports or applications so that the system capacity is increased.
1901	FULL DISK ERROR: Out of disk space. Data Collection failed (Archiver).	Enough disk space is not available for the insertion of daily/weekly/monthly archive data. Free up disk space or add more disk space
		in the form of additional hard disks.
1901	FULL DISK ERROR: Out of disk space. Harchiver could not write to <tablename>.</tablename>	Enough disk space is not available for the insertion of agent login/logout or interval archive data.
		Free up disk space or add more disk space in the form of additional hard disks. If the problem persists, call Services.
1901	FULL DISK ERROR: cannot write to xxx.	The filesystem or ACD dbspace is out of disk space.
		Use <b>Data Storage Allocation</b> to adjust the amount
		of space available to the ACD.
1901	FULL DISK ERROR:	There is no more disk space to load the data for this pseudo-ACD. The load ACD process cannot continue.
		Delete the pseudo-ACD and start over again using a later "Start date" for the pseudo- ACD and load less data. Reduce the amount of historical data kept in other ACDs.

Error Code	Message	Reason/Action
1901	FULL DISK ERROR: Automatically turning off data collection and bringing CMS to single user mode	All ACD dbspaces are checked for free space every 10 minutes. By turning off data collection and going to single user mode, CMS prevents corruption of the data that may occur if IDS tries to write data to a full ACD dbspace. CMS cannot be returned to its normal operational state until space has been made available in the ACD dbspace.
		Use <b>Data Storage Allocation</b> to adjust the amount of space available to the ACD.
1901	FULL DISK ERROR: WARNING: File system <filesys> is <nn> percent full.</nn></filesys>	This message is logged once each day near midnight and whenever CMS is started. The message is logged once for each file system or ACD dbspace that is at or beyond 80 percent of maximum capacity. This message is intended as an early warning that disk space may need to be reallocated.
		No immediate action is necessary.
1901	FULL DISK ERROR: Storage	The disk or ACD dbspace is out of space.
	Interval Migration failed migrating	Use <b>Data Storage Allocation</b> to adjust the amount of space available to the ACD.
1901	FULL DISK ERROR	The dbspace containing the ag_actv database table is full.
		Change the allocation of disk space for the various classes of data to accommodate storage of more agent trace records.
1901	FULL DISK ERROR: Out of disk space. Call Records not	The dbspace containing the call_rec database table is full.
	recorded.	Change the allocation of disk space for the various classes of data to accommodate storage of more internal call records.
1901	FULL DISK ERROR: Call Records not being stored. Call Services.	The dbspace containing the external call records files is full.
		Call Services.
1902	CALL RECORD ERROR: Call Records not being stored. Call Services.	An error was encountered in writing call records to a disk file.
		Call Services
1902	ALL RECORD ERROR: Call Records are being collected again.	Previous errors writing files have been cleared and records are again being stored.
		No action necessary.

Error Code	Message	Reason/Action
1902	CALL RECORD ERROR: Call Records not being stored, buffer area is full. Call Services	Files containing call records have not been successfully transferred. All storage space has been used and new records cannot be added.
		Call Services.
1902	CALL RECORD ERROR: Call rate exceeded capacity: xxx calls not transmitted	The internal Call History feature is activated but the call rate exceeds the maximum capacity handled by this feature; therefore, call records are not being sent to the Call History feature. This message indicates how many calls were not sent in the past data collection interval. This has no effect on the collection of regular data.
		Call Services.
2000	Could not run timetable: - Aborting Timetable. <timetable< td=""><td>Something is wrong with the timetable which is not allowing properly functionality.</td></timetable<>	Something is wrong with the timetable which is not allowing properly functionality.
	name>	Try rescheduling the timetable. Consult the section on using timetables to see if there are erroneous tasks in the timetable.
2000	Could not run timetable:	A timetable task is in error.
	<timetable name=""> Task <number> of <total> was unable to complete. Reason: <reason></reason></total></number></timetable>	One common possibility is that the user does not have permissions for the split, vdn, etc. for which they are running reports.
2000	Could not run timetable: don't run timetable, in single user timetable = <timetable_name> <user_name></user_name></timetable_name>	Timetables cannot run when CMS is in single user mode. An administrator has put CMS in single user mode as required by some special administrative tasks. The severity of the problem is that the user's timetables are not being run when expected.
		Schedule the timetables that should have run to be performed as soon as possible and then reschedule those timetables back to their original times. Schedule their timetables to run at a time that does not conflict during the time when CMS needs to be in single user mode.
2000	Could not run timetable: sorry post office open of timetable	Communications cannot be established with a crt_io_man in order to run the timetable.
	<pre>crt_io_man was not successful for timetable - <timetable name=""></timetable></pre>	Try rescheduling the timetable.
	and <cms id=""> - <user name="">.</user></cms>	

Error Code	Message	Reason/Action
2000	Could not run timetable: Archiver <timetable name=""> did not run on <date> for the user - <user name="">. Please schedule it to rerun using the Data Summarizing screen.</user></date></timetable>	The Archiver has a problem in moving historical data into tables for the timetable to use. Call Services.
2000	Could not run timetable: Archiver <timetable name=""> did not run on <date> for the user - <user name="">. To schedule a timetable to run as soon as possible, enter a cms start time that is two minutes into the future, and a start date of 0.</user></date></timetable>	A user scheduled a timetable to run in less than two minutes into the future. Reschedule the timetable for at least two minutes into the future.
2100	Unable to execute <process>. <impact-description>.Call Services.</impact-description></process>	The specified process could not be executed. The impact is usually the failure of a major component of CMS such as Agent Trace, Exceptions, or Data Collection. This problem can usually be repaired by stopping CMS and restarting it.
		Call Services.
2200	Sometimes the problem can be repaired by stopping CMS and restarting it.	An error was encountered during migration. Call services for assistance.
2300	INTERVAL MIGRATION: Interval migration was canceled before it completed. Restart it from the Storage Intervals screen to complete the migration	The migration was canceled manually before it completed. Restart the migration from the Storage Intervals screen.
2300	INTERVAL MIGRATION: Migrating intrahour historical data for ACD xx from xx to yy minute interval is complete.	This message indicates when intrahour migration is complete. No action required.
2400	FREE SPACE ALLOCATION: <error message&gt;</error 	This type of error message specifies that the <b>Free Space Allocation</b> feature has suffered a problem in locating or updating database tables.
2500	STORAGE INTERVALS: Weekly start/ stop day(s) have been changed from xx to yy.	This is an informational message indicating that the Storage Interval days have changed.
		Verify that the new days are correct.

Error Code	Message	Reason/Action
2600	ARCHIVER status: Daily/Weekly/ Monthly Archive not executed for xx/xx/xx due to Data Storage Allocation administration.	Data Storage Allocation indicates 0 days/ weeks/months are to be saved; therefore, no reason to archive data exists. This is most commonly a result of an error in user input.
		If daily archives are desired, <b>Days of Daily</b> / <b>Weeks of Weekly/Months of Monthly</b> entries must be changed to allow an archive to take place. Disk space must be considered before changing these fields.
2600	ARCHIVER status: Daily/Monthly/ Weekly Archiver for xx/xx/xx Successful.	Indicates successful completion of the daily/ weekly/monthly archive. The status of previous and current archives also exists in /cms/dc/archive/arch.log.
		No action necessary.
2600	ARCHIVER status: Daily/Monthly/ Weekly Archiver for xx/xx/xx Failed.	Indicates failure of the daily/weekly/monthly archive. The status of previous and current archives also exists in /cms/dc/archive/ arch.log.
		Re-initiate an archive for the same date and archive type (daily/weekly/monthly) using the Data Summarizing screen.
2700	MIGRATE DATA Process out of sync. Call Services.	A bad message was received from the R3 Migrate Data screen. If this occurs, some sort of interference occurred in the message queue between the R3 Migrate process and the associated screen. If the problem re- occurs, something is impacting the communication between the processes. Further investigation is necessary to determine the source of the problem.
		Exit the current instance of the R3 Migrate Data screen and re-initiate the migration. Verify that the problem does not re-occur.
2701	MIGRATE DATA Process out of memory. Contact Services.	A problem with memory allocation has occurred.
		Exit the current instance of the R3 Migrate Data screen and re-initiate the migration. Verify that the problem does not re-occur.

Error Code	Message	Reason/Action
2702	MIGRATE DATA Process startup failed. Contact Services	Any number of startup activities could cause this problem. If the problem re-occurs, there is an error in the environment of the migrate process and further investigation is necessary to determine the source of the problem.
		Exit the current instance of the R3 Migrate Data screen and re-initiate the migration. Verify that the problem does not re-occur.
2703	MIGRATE DATA Volume access failed. Retry Restore.	A problem exists accessing the migration device. This could range from:
		Invalid migration device
		Tape drive needs cleaning
		<ul> <li>Table header format problem (internal error).</li> </ul>
		Verify the following:
		• The backup/restore device is administered properly (name corresponds with the operating system administered device)
		• The tape compatibility is correct (320 meg tape for 320 meg drive, etc.).
		• The tape drive is clean.
2706	MIGRATE DATA Table migration failed. Retry Migrate. Table=	A problem was encountered either reading the indicated table from tape or writing that table into the database.
		Stop the migration and call Services for help with the table that failed. After the problem is fixed, restart the migration.
2708	MIGRATE DATA Error in process communication. Retry Restore.	A bad message was received either by the R3 Migrate Data screen or the migration process. If this occurs, some sort of interference occurred in the message queue between the migration process and the R3 Migrate Data screen. If the problem re- occurs, something is impacting the communication between the processes. Further investigation is necessary to determine the source of the problem.
		Exit the current instance of the R3 Migrate Data screen and re-initiate the migration. Verify that the problem does not re-occur.

Error Code	Message	Reason/Action
2750	MIGRATE DATA Screen startup failed. Contact Services.	Any number of startup activities could cause this problem. Most can be attributed to accessing screen entries that should never be encountered. If the problem re-occurs, something is in error in the environment of the migrate process and further investigation is necessary to determine the source of the problem.
		Exit the current instance of the R3 Migrate Data screen and re-initiate the migrate. Verify that the problem does not re-occur.
2751	MIGRATE DATA Screen execution failed. Retry Migrate.	This error can result when an update to the R3 Migrate Data screen fails.
		If the problem re-occurs, something is in error in the environment of the migrate process and further investigation is necessary to determine the source of the problem.
		Exit the current instance of the R3 Migrate Data screen and re-initiate the migration. Verify that the problem does not reoccur.

# **Chapter 13: Scripting CMS operations**

# **Scripting CMS operations**

Scripting enables the automation of tasks such as running reports, exporting report data, and other operations.

😵 Note:

CMS scripting is available only using the PC Client.

# Before you begin scripting CMS operations

Before a script can be run through CMS Supervisor, the following conditions must be met:

- The username associated with an automatic script must be assigned all the permissions required for all operations specified by the script.
- No more than four scripting CMS Supervisor sessions, including background sessions initiated by automatic scripts, can be run simultaneously on a PC.



When using scripts to change VDNs, verify that only one script is running at a time. If multiple scripts execute in parallel that are all changing VDNs, some VDN changes may not finish.

- The PC must be running at the time when an automatic script is scheduled to run.
- Once a script is created, it can be started by accessing the script file directly from a Microsoft Windows Explorer window.
- You must schedule mission-critical activities, such as backups, through Timetables on the CMS Supervisor server. For more information about Timetable scheduling, see <u>Creating and</u> <u>scheduling a timetable</u> on page 501.

### Tasks scripts can automate

Scripts can be used to automate several CMS tasks, such as:

• Running reports

- Exporting data from reports
- · Performing Dictionary operations and reports
- · Administering Exceptions and requesting Exception reports
- Performing Agent Administration operations
- Performing Call Center Administration operations and reports
- Performing System Setup operations
- Performing Maintenance operations and viewing the Error Log
- Administering User Permissions

# Interactive and automatic scripts

Each script is designated to be either interactive or automatic, as defined below:

- An interactive script runs in the current CMS Supervisor session and the actions display on the PC. If the CMS Supervisor session is disconnected from the CMS server, the script will not run.
- An automatic script launches a new Supervisor session that logs into CMS and runs the requested tasks as a background process. Script actions are not displayed on the screen. Although CMS Supervisor provides the ability to create automatic scripts, a third-party scheduling program must be used in order to run the scripts automatically on a regular schedule.

# **Script creation**

This section describes how to create interactive or automatic scripts used to run reports. Interactive and automatic scripts used to run reports have the following differences:

- An *interactive* script runs in the current Supervisor session and the actions display on the PC. If the CMS Supervisor session is disconnected from the CMS server, the script will not run.
- An *automatic* script launches a new Supervisor session that logs into CMS and runs the requested tasks as a background process. Script actions are not displayed on the screen. Although Supervisor provides the ability to create automatic scripts, a third-party scheduling program must be used in order to run the scripts automatically on a regular schedule.

### **Accessing scripts**

### Procedure

Scripts can be created and accessed through the **Scripts** button found on several dialog boxes. Dialog boxes containing the **Scripts** button can be accessed through the following menu selections:

Commands > Reports

- Commands > Dictionary
- Dictionary > Exceptions
- Commands > Agent Administration
- Commands > Call Center Administration
- Tools > System Setup
- Tools > Maintenance
- Tools > User Permissions

Scripts can also be accessed from agent administration windows or once a report is run. The **Scripts** button is also available when you use any other Supervisor command or tool that allows you to add or change objects.

### Accessing the script options

### About this task

Before you create scripts, you should be aware of the different options and behaviors available for scripts.

### Procedure

### Select Tools > Options > Scripting.

The Scripting dialog provides the fields required to set the scripting options, which are described in <u>Scripting options description</u> on page 485.

# Scripting options description

Name	Description
User ID	This read only ID allows automatic scripts to make their connection to the CMS server. The login ID and password are not validated until an automatic script is run.
Set User	You must specify a CMS user ID and password before you can run any automatic scripts. For more information, see <u>Setting user ID and</u> password on page 486

Name	Description
Logging Level	The extent to which script-related activities and outputs are logged, according to the following criteria:
	<ul> <li>Minimum - Logged activities are limited to those errors and messages from CMS Supervisor which would otherwise be displayed when the scripts are run manually.</li> </ul>
	<ul> <li>Normal - Logged activities include those recorded at the Minimum setting, plus the following information: task start time; task end time; name of the script.</li> </ul>
	<ul> <li>Maximum - Logged activities include all those recorded at Minimum and Normal settings, plus additional error messages which may be useful for debugging a script.</li> </ul>
Log File Path	Allows you to specify a non-default file directory path. Selecting the folder icon to the right of this field also lets you browse the file system to select a log file directory.
Log File Size	Allows you to specify the size of the log file before it rolls over and begins to overwrite itself.

# Setting user ID and password

Before you create an automatic script, you must set a user ID and password to allow the script to log into CMS. If you do not set the ID and password beforehand, you are prompted to do so the first time you save an automatic script.

# Setting users procedure

### Procedure

- 1. Select **Tools > Options > Scripting**.
- 2. Select Set User.
- 3. Enter your CMS login ID in the User ID field.
- 4. Enter your password in the **Password** field.
- 5. Enter your password again in the **Confirm Password** field.
- 6. Select OK.

The two password entries are checked to make sure they match. If they do not, the message Passwords do not match appears and you remain in the window. If they match, your user ID and password are encrypted and saved and are used to log in when this or any automatic script is run.

Your user ID and password are not verified with the server at this time. The only way to check if they are correct is to attempt to run an automatic script and check the script log to see if the script ran successfully.

# **Scripting reports**

### Creating an interactive report script

### Procedure

1. Select **Commands** > **Reports** from the Controller window menu bar.

CMS Supervisor displays the Reports window.

- Select the tab associated with the type of report you want to run (Real-Time, Historical, or Integrated), and then highlight the report from the categories and listings which are displayed.
- 3. Select the **Script** button on the report selector window.

CMS Supervisor displays the Save as Script window.

4. Select a directory and file name for the script and select **Save**.

CMS Supervisor closes the Save as Script window and returns you to the report selector window.

# Creating an automatic report script

### Procedure

1. Select **Commands** > **Reports** from the Controller window menu bar.

CMS Supervisor displays the Reports window.

2. To select a report for scripting, select the appropriate report type from the dialog box tabs, highlight the report, and select **OK**.

CMS Supervisor displays the input window for the selected report.

3. Enter the appropriate data in the input window and run the report by selecting **OK**.

CMS Supervisor displays the selected report.

Note:

If a historical report was selected, set the **Destination** controls to **View Report on Screen**.

 In the dialog displayed for the report, select Reports > Commands > Script from the main menu.

CMS Supervisor displays the Save as Script window.

- 5. Select a directory and file name for the script. The file type is set to Automatic by default.
- 6. Select Save.

Executing this automatic script causes the report to run with the inputs provided during its creation.

# Creating a script to export report data

### Procedure

1. Run a report and display it to screen.

CMS Supervisor displays the window for the selected report.

- 2. From the Edit menu of the report window, select one of the following actions:
  - Export Chart Data
  - Export Table Data
  - Export All Data

The data export dialog box is displayed. The dialog that is displayed will vary according to which export option is selected.

Some of these options can also be selected from a pop-up menu by performing a rightclick in the report window.

3. Set the appropriate options in the data export dialog, and then select the **Script** button.

### Important:

Do not select **OK** after the options are selected.

CMS Supervisor displays the Save as Script window.

- 4. Select a directory and file name for the script, and set the file type to either **Interactive** or **Automatic**.
- 5. Select Save.

# Creating a script to export report data as HTML

### Procedure

1. Select a report that you want to export as HTML and display it to the screen.

CMS Supervisor displays the report window.

2. From the menu bar of the report window, select **Reports > Save As**.

CMS Supervisor displays the Save as HTML window.

3. Select the appropriate option from the **Template** group.

A template can be used to provide company logos, background color, specific fonts, or surrounding text to the HTML file. If you do not select a template, the export process generates basic HTML tags to display the report.

CMS Supervisor provides you with several templates that can be found in the \samples directory of the main CMS Supervisor directory.

4. In the **Output** field, select a name for the HTML file you are creating.

To save the file in a directory other than the current directory, specify a full file path, such as c:\temp\myrpt.htm. You may also use the browse button located to the right of this field to navigate to a target directory.

5. Select the Script button.

CMS Supervisor displays the Save as Script window.

- 6. Select a directory and file name for the script, and set the file type to either **Interactive** or **Automatic**.
- 7. Select Save.

If there are charts associated with the file, they are converted into . GIF files. After the HTML is saved, you can move or copy it and all associated graphics files to a web server directory for viewing on the Internet or an Intranet.

# Scripting operational tasks

This section provides information on the procedures used to create and save scripts for operational tasks, that is, actions not associated with reports. Operational tasks include:

- Displaying an input window for actions, not reports, requiring data entry when the script is run.
- An Add, Modify, or Delete action.

### About scripting an input window

This procedure describes how to create a script that displays an input window for a specific, nonreport operation. Executing the script displays the input window for the operation selected when this script was created. Actions associated with the following functions can be captured in a script:

- Dictionary
- Exceptions
- Maintenance
- System Setup
- Agent Administration
- Call Center Administration

### Scripting an input window

### Procedure

1. Select the necessary item from the **Commands** menu on the Controller window.

CMS Supervisor displays the associated selector window for the item selected.

### Important:

Do not double-click the option or press the Enter key when an operation is highlighted or the action will be initiated and the script recording will be aborted.

2. Highlight the operation to be made into a script from the **Operations** list on the Operations tab of the selector window and then select the **Script** button in the selector window.

CMS Supervisor displays the Save as Script window.

The file type is set to **Interactive** by default.

3. Complete the Save as Script window by entering a file name and folder location and then select **Save** when finished.

CMS Supervisor displays an acknowledgment message to indicate that the script has been saved.

4. Select the **OK** button on the acknowledgment message box.

CMS Supervisor closes the Save as Script window and the selector window remains open.

### Scripting an action

### About this task

Use this procedure to create a script that results in the execution of an action. Running the saved script will cause an add, modify, no action, or delete action to be performed for the selected operation.

### ▲ Caution:

When using scripts to change VDNs, verify that only one script is running at a time. If multiple scripts execute in parallel that are all changing VDNs, some VDN changes may not finish.

Valid items for scripting an action include:

- Dictionary
- Exceptions
- Maintenance
- System Setup
- Agent Administration
- Call Center Administration

### Procedure

1. Select the necessary item from the **Commands** menu on the Controller window.

CMS Supervisor displays the selector window associated with the selected item.

- 2. Highlight the operation to be made into a script from the **Operations** list on the Operations tab of the selector window.
- 3. Select the **OK** button.

CMS Supervisor displays the input window for the selected operation.

4. Select **Actions** > **Scripts** from the menu bar of the input window.

If none of the valid scriptable actions, **Add**, **Modify**, or **Delete**, are present, you cannot select **Script**.

CMS Supervisor displays the Save as Script - Action window.

- 5. Select the action to be performed by the script.
- 6. Select the **OK** button.

CMS Supervisor displays the Save as Script window.

😵 Note:

If the **Cancel** button is selected, Supervisor dismisses this window and displays the input window without saving an action.

CMS Supervisor displays the Save as Script window.

### 😵 Note:

If the **Cancel** button is selected, CMS Supervisor dismisses this window and displays the input window without saving an action.

- 7. In the Save as Script window, select a file folder location and file name.
- 8. Specify the script type as either Automatic or Interactive.
- 9. Select Save.

CMS Supervisor displays an acknowledgment message box stating that the script has been saved.

10. Select the **OK** button on the acknowledgment message box

CMS Supervisor displays the Save as Script - Action window.

### **Organizing scripts**

### About this task

The Organize Scripts window provides a simple file management interface which allows you to rename, delete or move script files.

### Procedure

1. Select **Scripts** > **Organize Scripts** from the menu bar on the Controller window.

CMS Supervisor displays the Organize Scripts window.

2. Perform actions on the scripts as needed.

This can include renaming, deleting, and moving.

3. When you are finished organizing scripts, select **Close** to exit the Organize Scripts window.

# Error and warning messages

This section lists possible error messages which may be encountered when running scripts and describes their associated causes and possible solutions.

#### Table 1:

Message	Reason	Solution
This script will not run unless a CMS login ID and password have been specified.	The CMS login ID and password have not been set on the Scripting tab of the Controller Options window.	Specify a login ID and password on the User Information window.
Automatic scripts are set to run with the permissions of another user of the PC.	The User Information window designates the other user as the owner of automatic scripts.	You can change the permissions via the login information on the Scripting tab of the Controller Options window. The change will apply to subsequent automatic scripts that are run on the PC.

Message	Reason	Solution
(Action) Supervisor displays the Save as Script: Add or Replacewindow.	The file already exists.	Select one of the following actions at the bottom of the window:
		<ul> <li>Add (default) - Adds the new script to the end of the existing script</li> </ul>
		• <b>Replace</b> - Deletes the existing script and create a new script file
		<ul> <li>Cancel - Closes the Add or Replace window and returns to the Save as Script twindow</li> </ul>
		<ul> <li>Help - Displays the help topic for the current window.</li> </ul>

# Chapter 14: Administrative tasks using the operating system

# Using the operating system

Avaya CMS uses the operating system to communicate with terminals and printers, to log errors, and to perform operations. This section addresses how to perform several procedures using operating system commands.

# Before using the operating system

Be cautious when accessing the operating system and running operating system commands. Damage can result to your CMS system if you use the operating system commands incorrectly. Before you run any operating system command, be sure you know what effect it can have.

# Logging in to CMS

This section contains procedures for logging in to CMS through methods other than using Supervisor. Some administrators will need to do this in order to access capabilities not available through the CMS Supervisor interface.

# Logging in to CMS from the remote console

### About this task

This procedure describes how to log in to CMS from a remote console. Most users log in to CMS remotely.

### Important:

Do not allow users to share the same login ID as this action will use up operating system processes.

### Procedure

1. At the Login: prompt, enter your login ID.

The Password: prompt is displayed.

2. Enter your password.

A prompt for the terminal type is displayed.

3. Enter your terminal type.

If you use a login other than "cms", CMS will automatically open to the CMS Main Menu.

If "cms" is used as the login, you will have to enter cms a second time at the \$ prompt before the **Main Menu** will be displayed

# Logging in to CMS from the server console

### About this task

This procedure describes how to log in to CMS from the CMS server console. Logging in to CMS at the server is occasionally necessary in order to perform certain functions, such as a CMSADM backup or other administration functions that require you to switch to single-user mode.

### Important:

Users who use a /usr/bin/cms shell will not be able to log in to CMS through the Common Desktop Environment (CDE).

To remedy this problem, you can either use the /usr/bin/ksh shell or use a command line login. The command line login will not use the CDE.

### Procedure

1. If the server has just been rebooted or inactive for an extended period of time, the console may be password-protected. If this is the case, unlock the console by entering your authorized username (if necessary) and password in the appropriate login console fields.

Solaris displays the CDE interface.

2. Right-click the cursor in an empty area within the desktop space.

The Workspace Menu is displayed.

- 3. Depending on how CMS was installed, choose one of the following alternatives:
  - If the CMS XTERM option is displayed in the **Workspace Menu**, you can open an xterm window directly by selecting that option.
  - If the CMS XTERM option is not displayed, choose **Tools** > **Terminal** from the **Workspace Menu** to open a terminal window. At the command prompt, enter xterm to open an xterm window.

An xterm window is displayed with a # prompt.

# Administering passwords

For system security, passwords are required for all CMS user login IDs. If a password is not entered on your first login, the system will prevent you from continuing until one is supplied.

CMS users can enter and change their passwords, but only a CMS administrator working on the CMS operating system or using the Web Client can reset a forgotten password.

For more information about how to change passwords using the Web Client, see <u>About changing</u> <u>user passwords using the Web Client</u> on page 223.

# Before administering passwords

The following items should be read and understood before attempting to administer passwords:

- Password administration should only be done by an administrator with the password for the root user.
- Forcing a password change and administering the Password Aging feature can only be done through the CMS ASCII interface. The ASCII interface is available through the following methods:
  - A Terminal Emulator connection to the CMS server
  - A telnet session to the CMS server
  - Direct interaction with the CMS server
- Users should choose a password with no less than six characters. The password must have at least one character as a number or special character and have a minimum of two alphabetic characters.
- When changing a password, the new password must have at least three characters that are different from the previous password.

See <u>Chapter 10: Administering user permissions</u> on page 213 for more information on special characters.

# Changing a user's password

### About this task

When a user's password expires or it is forcibly made to expire by an administrator, the user is presented with a prompt or window during the CMS login process that allows the entry of a new password. The following procedure allows an administrator to cause a user's password to expire so that the user must enter a new password upon their next login attempt.

If a user forgets their password, perform the following procedure.

### Procedure

- From the CMS Main Menu, highlight the Commands Screen-Labeled Key (SLK).
   CMS displays the Commands menu.
- 2. Select the operating system (Linux) option.

The screen clears and a \$ prompt is displayed.

- 3. Enter the su command.
- 4. At the Password: prompt, enter the root password.

The # prompt is displayed.

5. Enter the following command:

```
passwd <userid>
```

Where *userid* is the ID of the user who needs a new password.

The operating system displays a prompt for the new password.

- 6. Enter a new password for the user.
- 7. Re-enter the password when prompted for the confirmation password.

The operating system displays the command line prompt.

- If the operating system is Solaris, continue with Step 8 on page 497.
- If the operating system is Linux<sup>®</sup>, continue with Step <u>10</u> on page 497.
- 8. Enter the following command:

passwd -f userid

Where *userid* is the ID of the user with a new password.

The operating system displays the command line prompt.

The <code>passwd -f</code> command will force the user to change their password the next time they log in to CMS .

- 9. Continue with step <u>11</u> on page 497.
- 10. Enter the following command:

chage -d 0 <userid>

where <userid> is the ID of the user with a new password.

The operating system displays the command line prompt.

The chage -d 0 command forces the user to change their password the next time they log in to CMS.

11. Enter exit and press the Enter.

The system displays the \$ prompt.

12. Enter exit and press the Enter.

CMS displays the Main Menu.

# Administering password aging

### About this task

This section provides introductory and prerequisite information regarding the password aging feature of CMS .

Password aging is a feature that forces CMS users to change their password after a specified number of weeks have passed. Once this feature is activated, all users are required to change their passwords when the expiration period is reached.

### Before you begin

### Important:

If you have a custom configuration from the Avaya Professional Services Organization (PSO) or use third-party applications on your CMS server, you must contact the PSO before enabling the password aging feature so that customizations are not affected. The PSO can be contacted through the technical support telephone number.

The following items should be read and understood before attempting to change the password aging feature:

- The number of weeks that pass before a password change is required can range from 1 to 52 weeks. The default value for this feature is 9 weeks.
- The password aging feature is only available through the cmsadm menu in the ASCII interface of CMS . This feature is not accessible through Avaya CMS Supervisor .

### Procedure

For more information and procedures for administering the password aging feature, see *Maintaining and Troubleshooting Avaya Call Management System*.

# **Chapter 15: Using timetables and shortcuts**

# About using timetables and shortcuts

This section provides information on timetables and shortcuts and how to create and administer them. Timetables and shortcuts are used to run multiple administrative tasks and are only available through the CMS ASCII interface.

Access to the CMS ASCII interface can be done through the following methods:

- Terminal Emulator
- · Telnet session to the CMS
- · Direct interaction with the CMS server console

# **Timetables**

A timetable is a CMS feature that enables the scheduling of one or more administrative tasks. Each timetable can consist of up to 100 tasks and can be scheduled to run at any specific time. When you are creating a timetable, CMS records the tasks you perform and includes them in the timetable. This feature is similar to macros in many PC applications that perform multiple tasks or actions when the single macro is run.

Timetables are better suited for mission-critical tasks than Supervisor scripts. This is due to the fact that scripts reside on the PC where they were created. If network difficulties occur or if the PC where the script resides is powered down, the script cannot run. Timetables run directly on the CMS server and do not suffer from such problems.

# Before using timetables

The following items should be read and understood before working with timetables.

### General

- You cannot schedule real-time reports, Vector Contents, or custom report creation through a timetable.
- Timetables run in the background, not in the terminal session.

- Timetables that fail at some point during execution are logged in the Maintenance Error Log Report.
- Up to five timetables can be scheduled to run at the same time.
- You can have tasks associated with different ACDs in the same timetable.
- Do not create a timetable that attempts to write a file in the home directory of different user.
- The ACD that is currently selected when a timetable task is created will be the ACD on which the task runs. To change the ACD, you must delete the task and reset the current ACD before adding the correct task.
- When a CMS user is deleted, any timetables associated with that user ID are also deleted. For this reason, it is recommended that mission-critical timetables be created under the cms user ID.
- If the System Administration Terminal (SAT) terminal is still logged in to the Communication Manager system and is displaying a screen used in timetables, those timetables will not run.
- Timetables cannot run if CMS is in single-user mode.

#### Printing

- You cannot select the terminal as the destination for report output through a timetable.
- To print a report more than once from a timetable, you must enter a task for each copy of the report.
- Print jobs from timetables go to the default printer for the user who owns the timetable unless otherwise specified when the timetable is created. If the default printer for a user is changed, there is no need to edit the timetable as CMS automatically sends the print jobs from the timetable to the new default printer.
- If a user specifies a printer other than their default printer for a timetable task and that printer is out of service, the timetable will not execute.
- If the printer jams while attempting to print timetable tasks, you must resubmit the request that did not print.

#### Backups

- Timetables for incremental and full backups are created when the system is installed, but are not scheduled.
- Be sure to schedule backups to run either before archiving begins or after archiving has been completed.

### **Permissions for timetables**

Depending on the procedure that you want to perform, you need the following permissions:

- To view timetables, the user ID used to log in to this CMS session requires "read" permission for the Timetables feature, the requested CMS actions, and any ACD entities accessed by the timetable.
- To add, delete, or modify timetables, the user ID used to log in to this CMS session requires "write" permission for the Timetables feature.

- Users who are not Administrators can view and copy timetables from other users, but they cannot add, delete, or modify the timetables or the task entries.
- Users with Administrator permissions can add, delete, and modify timetables created by other users.
- If a timetable contains tasks for which the user does not have adequate permissions, the timetable will fail.

### Creating and scheduling a timetable

### About this task

This topic provides the procedure for creating and scheduling a timetable through the CMS ASCII interface.

### Procedure

- 1. From the CMS **Main Menu**, select the **Keep** Screen-Labeled Key (SLK), using one of the following methods, depending on the connection method:
  - For Terminal Emulator, select the F4 key.
  - From the CMS console, press the F4 key.
  - For a telnet session from a PC, press Ctrl+P+4.
- 2. Select Timetable name and press the Enter key.

CMS displays the Timetable window.

Timetable	test1
_	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: cms	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
< <u>x</u> > Once	Next
<_> Dates:	Previous
	21x68

3. In the **Timetable name** field, enter a unique name for this timetable. The name of the timetable cannot be changed after it has been created. Every timetable must have a unique name.

The following list provides the types of characters that can be entered in this field:

- Alphanumeric (A-z, 0-9)
- Underscore (\_)
- Blank ()
- Comma (,)
- Period (.)
- Single Quotation Marks (')
- Plus sign (+)
- 4. In the **Description** field, enter a description for the timetable.

This field is optional.

- 5. In the **User ID** field, the user ID currently logged in is displayed. If you are an administrator and want to create this timetable for another user ID, enter that user ID in this field.
- 6. In the **Start time** field, enter the time when the timetable will be executed. If you do not wish to schedule the timetable at this time, leave this field blank.

This field can accept time in the following formats:

- HH AM/PM
- HH:MM AM/PM
- 24-hour (00:00 23:59)

If AM/PM is not specified, CMS assumes that the time entered is in the 24-hour format.

7. In the Start date field, enter the date on which the timetable will begin running.

Use one of the following formats for entering the date in this field:

- MM/DD/YY For example, 12/12/01. Do not enter four-digits years in this field.
- Relative format For example, entering a 1 specifies the timetable will begin one day from today (tomorrow).

### Important:

If you do not wish to schedule the time table at this point, leave the **Start time** and **Start date** fields blank, ensure an x is in the **Once** field, and skip ahead to Step <u>11</u> on page 503.

- 8. In the Frequency and attributes group, choose from the following options:
  - Once This option runs the timetable one time for the date and time specified in the **Start date** and **Start time** fields. This is the default value for this field group.

- **Dates** This option runs the timetable on specific dates. Enter the dates in the fields provided for this option.
- **Hourly** This option runs the timetable each hour. In the **Stop time** field, enter the time when the timetable should stop running.
- **Daily** This option runs the timetable on the selected days in the **Hourly/Daily Days** group.
- 9. If the **Hourly** or **Daily** option was selected in the previous step, place an x next to the days in the **Hourly/Daily Days** group for which the timetable should run.
- 10. Place an  $\times$  in one of the following options:
  - **RunonlyonthisCMSserver** The timetable will run only on this CMS server. If this timetable is backed up and migrated to another CMS server, it will not run.
  - Run on this or another CMS server The timetable is capable of running on this or any other CMS server. If this timetable is backed up and migrated to another CMS server, it will function normally.
- 11. Press the Enter key, highlight the **Add** item on the action list by using the arrow keys on the keyboard, and press Enter again.

The window displays a Working message. If the timetable name is currently present, Already exists displays on the status line and you must enter a different timetable name in the **Timetable name** field. If all entries are valid, the **Main Menu** displays with Keeping Entries displayed in the border.

12. Select a task from the CMS Main Menu that will be recorded to this new timetable.

CMS displays an Entries Stored in the status line of the current window when the task is run.

- 13. To run an historical report for the system:
  - a. Select **Reports** from the **Main Menu**.
  - b. Select Historical.
  - c. Select System.
  - d. Select System.
  - e. Select Daily.

CMS displays the report window.

14. Enter the required information in the **Split(s)/Skill(s)** and **Date** fields.

The**Date** field can accept relative dates; for example, 0 represents today and -1 represents yesterday.

15. Press the Enter key to access the action list, select the menu item that performs the necessary action, and then press the Enter key again.

CMS displays a confirmation window.

It is possible to create more than one timetable task from a window. For example, suppose you want historical split/skill summary interval reports for skills 1 through 9, and you also want the same date and times for each report.

- 16. To create this report, perform the following steps:
  - a. Go to the report window and enter 1 for the skill number, 0 for the date, and 8:00-16:00 for the times.
  - b. Select **Run** on the action list. This creates a timetable task for skill 1.
  - c. Returning to the report input window, enter 2 for the skill number and select **Run** on the action list. This creates a timetable task for skill 2. Repeat the same process for skills 3 through 9.
- 17. Exit the window for the task and return to the Main Menu.
- 18. To add more tasks to the timetable, return to Step <u>12</u> on page 503. Otherwise, open the **Keep** SLK menu and then select the **Stop** option.

CMS displays a confirmation window asking if the timetable should be saved.

19. When CMS displays the confirmation window, press the Y key and then the Enter key to save the task.

😵 Note:

To exit the timetable at any time without saving your changes, select **Stop** from the **Keep** SLK menu and then enter n in the confirmation window.

20. Select the Exit SLK to close the Timetable window.

# Adding tasks to a timetable

### About this task

This topic provides the procedure for adding tasks to an existing timetable. This feature enables you to add tasks to a timetable in the same way you added tasks when you first created the timetable.

### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Timetable and press the Enter key.

CMS displays the Timetable window.

Timetable	test1
	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: cms	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
< <u>x</u> > Once	Next
<pre></pre>	Previous
<_> Hourly, Stop time: <u>11:59 PM</u>	
<_> Daily,	
Hourly/Daily Days (Select any you wish):	
[ <u>x</u> ] Sunday [ <u>x</u> ] Tuesday [ <u>x</u> ] Thursday	[ <u>x</u> ] Saturday
[x] Monday [x] Wednesday [x] Friday	· - ·
This timetable will run on this or another CMS serve	er
<_> Run only on this CMS server*	
$\langle \underline{\mathbf{x}} \rangle$ Run on this or another CMS server*	
*These fields not used for Find one or List all	
	21x68

3. Press Ctrl+Z.

The fields in the window are cleared of all default information.

- 4. In the **Timetable name** field, enter the name of the timetable to which you want to add a task.
- 5. Press the Enter key.

CMS shifts focus to the action list.

6. In the action list, use the arrow keys to select Get contents and press the Enter key.

CMS displays the Timetable: Get Contents window.

	ble <mark>:</mark> Ge	t Cont	tents				test1
Task(						Add tas	iks 🛛
Timet	able: S	ample t	timetal	ble	Number of tasks: 10	Сору	
Task J	Action	Windov	v Title	e		Delete	
1 1	Run	Rpts:	Hist:	Agent:	Summary: Interval Input	Global	edit
2 1	Run	Rpts:	Hist:	Agent:	Summary: Daily Input	Modify	
3 1	Run	Rpts:	Hist:	Agent:	Summary: Weekly Input L	-	
4	Run	Rpts:	Hist:	Agent:	Summary: Monthly Input	test1	a510
5 1						test1	a510
6 1	Run	Rpts:	Hist:	Agent:	Split/Skill: Daily Input	test1	a510
7 1						test1	a510 🛛
						103×1	.32 >

7. In the **Task(s)** field, enter the number of the task that you want to precede the task being added.

If the task being added should appear as the fifth task, enter 4 in the Task(s) field.

To add a task to the beginning of the timetable, leave the **Task(s)** field blank. The new task is added before the first task.

To add tasks to a timetable with no tasks, leave the **Task(s)** field blank.

8. Press the Enter key.

CMS shifts focus to the action list.

9. Use the arrow keys to highlight the Add tasks item and press the Enter key.

CMS displays the **Main Menu** and is waiting for you to perform an action that it can add as a task. The status line of the **Main Menu** displays Keeping Entries.

10. Perform the task that you wish to have added to timetable.

For more information on the steps necessary in adding a task to a timetable, see Step <u>12</u> on page 501 in <u>Creating and scheduling a timetable</u> on page 501.

When the task is performed, CMS displays Entries Stored in the status line.

11. Exit the task window.

CMS displays the Main Menu.

At this point, more tasks can be added simply by performing them. These tasks will be added to the timetable in order following the previous task.

12. If you finished adding tasks to the timetable, open the **Keep** SLK menu and then select the **Stop** option.

CMS displays a confirmation window asking if the timetable should be saved.

13. Press the Y key and then the Enter key.

CMS saves the timetable with the newly added tasks and displays the Timetable: Get Contents window.

### Listing all timetables

#### About this task

This topic provides the procedure for listing all timetables that currently exist in the CMS database. Listing all timetables can assist in finding specific timetables when you cannot remember the entire name of a timetable. It is also useful in helping to determine if too many timetables are scheduled to run at the same time.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. On the Keep SLK menu, select Keep Timetable.

CMS displays the Timetable window.

3. Press Ctrl+Z.

CMS clears the default information from all fields in the Timetable window.

4. Press the Enter key.

CMS shifts focus to the action list.

Using the arrow keys, move the cursor to the List all menu item and press the Enter key.
 CMS displays the Timetable: List All window listing all timetables.

Timetable: Iist All				G3V5_eas
<u>Timetable Name</u> skh11.20.2	<u>User ID</u> cms	<u>Status</u> finished	<u>Next Run</u>	Start <u>Time</u> 1:30 PM
temp7 temp9 tst	cms cms cmş	finished		1:30 PM
4 matches found				7x240 >

Use the right- and left-arrow keys to scroll to the other fields in this window.

The following list describes the entries that can appear in the Status field.

- Finished: This message indicates that the timetable was scheduled to run once and it completed successfully.
- Failed: This message indicates that the timetable failed to run successfully for the last scheduled run time.
- Successful: This message indicates that the timetable completed successfully.
- Unscheduled: This message indicates that the timetable does not have a start time or start date.
- Running: This message indicates that the timetable is currently running.

### Copying a timetable

#### About this task

This topic provides the procedure for copying an existing timetable to a new timetable. Although you can copy timetables from other users, you cannot copy over an existing timetable. When you copy a timetable, the scheduling information and tasks in the timetable are copied. The name of the timetable that will be copied should be known before starting this procedure.

#### Procedure

1. Select **Timetable** on the **Keep** Screen-Labeled Key (SLK) menu.

CMS displays the Timetable window.

Timetable	test1
	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: <u>cms</u>	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
< <u>x</u> > Once	Next
<_> Dates:	Previous
<pre></pre>	er
	21x68

2. In the **Timetable name** field, enter the name that will be used for the new timetable.

The following list provides the types of characters that can be entered in this field:

- Alphanumeric (A-z, 0-9)
- Underscore (\_)
- Blank ()
- Comma (,)
- Period (.)
- Single Quotation Marks (')
- Plus sign (+)
- 3. In the User ID field, confirm that your user ID is present.
- 4. Press the Enter key.

CMS shifts focus to the action list.

5. Use the arrow keys to highlight the **Copy** item in the action list and press the Enter key. CMS displays the Timetable: Copy window.



- 6. In the **Copy from** field, enter the name of the timetable to copy.
- 7. In the User ID field, enter the user ID that is currently associated with the existing timetable.
- 8. Press the Enter key.

CMS shifts focus to the action list of the Timetable: Copy window.

9. Press the Enter key again.

CMS displays Successful in the status bar.

If this new timetable is not scheduled to run, CMS displays a message notifying you that this copy needs to be rescheduled.

10. Select the Exit SLK to close the Timetable window.

### Copying timetable tasks

#### About this task

This topic provides the procedure for duplicating tasks within a timetable.

#### Before you begin

The following items should be read and understood before copying timetable tasks:

- Only the owner of the timetable or an administrator can copy timetable tasks.
- You cannot copy a task more than once using the **Copy** command in the Timetable: Get Contents window. You must reuse the **Copy** command to make additional copies of a task.
- You cannot copy more than 100 tasks into a timetable. If you exceed the limit, none of the tasks are copied. The status line will display a Failed message when this occurs.
- Copies of tasks can be placed after a specified task in the timetable, or each copy can be placed directly after the task from which it was copied. The default is to place the copies after the last task in the timetable.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Timetable and press the Enter key.

CMS displays the Timetable window.

Timetable	test1
	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: <u>cms</u>	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
< <u>x</u> > Once	Next
<_> Dates:	Previous
<pre></pre>	· - ·
	21x68

3. Press Ctrl+Z.

The fields in the window are cleared of all default information.

- 4. In the **Timetable name** field, enter the name of the timetable containing the task to copy.
- 5. In the **User ID** field, enter the user ID that created the timetable.

If you are not the owner or an administrator, you will not be able to copy tasks in the timetable.

6. Press the Enter key.

CMS shifts focus to the action list.

7. Use the arrow keys to highlight the **Get contents** menu item and press the Enter key.

CMS displays the Timetable: Get Contents window.


Timet	able: 🤇	Get Contents				test1
	(5):				Add ta	sks
Time	table:	Sample timet	able	Number of tasks: 10	Copy -	
Task	Action	n Window Tit	le		Delete	
1	Run	Rpts: Hist	: Agent:	Summary: Interval Input	Global	edit
2	Run	Rpts: Hist	: Ağent:	Summary: Daily Input	Modify	
3	Run	Rpts: Hist	: Agent:	Summary: Weekly Input		
4	Run	Rpts: Hist	: Ağent:	Summarý: Monthly Input	test1	a510
5	Run	Rpts: Hist	: Agent:	Split/Skill: Interval Input	test1	a510
6	Run	Rpts: Hist	: Agent:	Split/Skill: Daily Input	test1	a510
7	Run			Split/Skill: Weekly Input	test1	a510 V
		· ·	- F		103X3	132 >

8. In the Task(s) field, enter the task number to copy and press the Enter key.

CMS shifts focus to the action list of the Timetable: Get Contents window.

9. Using the arrow keys, highlight the **Copy** menu item, and press the Enter key.

CMS displays the Timetable: Get Contents window.



- 10. Choose one of the following options by placing an x next to it:
  - Add following task The copied task will be placed immediately after the task specified in this field.
  - Add each task after the task from which it was copied The copied task is placed immediately after itself.

The default action is to place the copied task at the end of the list.

11. Press the Enter key.

CMS shifts focus to the action list.

12. Press the Enter key again.

CMS displays Working in the status line. When the operation completes, the status line displays Successful. CMS closes the Copy window and displays the Timetable: Get Contents window.

If the operation fails, a message window appears stating the reason for the failure.

13. To close the Timetable: Get Contents window, select the Exit SLK.

### Modifying timetable tasks

#### About this task

This topic provides the procedure for modifying tasks within a timetable. The Modify feature allows you to modify the action or data associated with any task within the selected timetable.

#### Before you begin

The following items should be read and understood before modifying timetable tasks:

- Only the owner or an administrator can modify timetable tasks.
- The **Current** and **Main Menu** Screen-Labeled Keys (SLKs) are blocked while modifying tasks.
- If you press the **Exit** SLK without selecting a task action, a popup window is displayed stating that the task modification has been cancelled.

• To exit the timetable without saving any changes, select the **Stop** item from the **Keep** SLK menu.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Timetable and press the Enter key.

CMS displays the Timetable window.

Timetable	test1
	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: <u>cms</u>	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
< <u>x</u> > Once	Next
<_> Dates:	Previous
	21x68

3. Press Ctrl+Z.

The fields in the window are cleared of all default information.

- 4. In the **Timetable name** field, enter the name of the timetable containing the task to modify.
- 5. In the **User ID** field, enter the user ID that created the timetable.

If you are not the owner or an administrator, you will not be able to modify tasks in the timetable.

6. Press the Enter key.

CMS shifts focus to the action list.

Use the arrow keys to highlight the Get contents menu item and press the Enter key.
 CMS displays the Timetable: Get Contents window.

Timetable: Get Contents	test1
Task(s):	Add tasks
Timetable: Sample timetable Number of tasks: 10	Сору
Task Action Window Title	Delete
1 Run Rpts: Hist: Agent: Summary: Interval Input	Global edit
2 Run Rpts: Hist: Agent: Summary: Daily Input	Modify
3 Run Rpts: Hist: Agent: Summary: Weekly Input	-
4 Run Rpts: Hist: Agent: Summary: Monthly Input	test1 a510
5 Run Rpts: Hist: Agent: Split/Skill: Interval Input	test1 a510
6 Run Rpts: Hist: Agent: Split/Skill: Daily Input	test1 a510
7 Run Rpts: Hist: Agent: Split/Skill: Weekly Input	test1 a510 🗸
	103×132 >

- 8. In the **Task(s)** field, enter the number of the task to modify and press the Enter key. CMS shifts focus to the action list of the Timetable: Get Contents window.
- 9. Using the arrow keys, highlight the **Modify** menu item and press the Enter key.

CMS displays a window for the specified task.

Example:

Rpts: Hist: Agent: Summary: Interval Inp Agent: 0001 Date: 0 Times: 10:00	test1 Run
Report destination (Select one):	
<x> Printer, Printer name: &lt; &gt; File, File name:</x>	

- 10. Make any necessary changes to the task.
- 11. When the changes have been made, press the Enter key.

CMS shifts focus to the action list.

12. Using the arrow keys, highlight the appropriate action to perform in the action list and press the Enter key.

CMS displays a confirmation window asking if changes should be saved.

13. To save the changes made to the task, press the Y and then press the Enter key.

CMS saves the task changes to the timetable and displays the Timetable: Get Contents window.

14. To exit the Timetable: Get Contents window, select the Exit SLK.

## Editing timetables globally

#### About this task

Globally editing timetables changes the server compatibility for all timetables associated with a user ID.

Server compatibility of timetables can be one of the two following states:

- Add following task The timetable will run only on this CMS server. If this timetable is backed up and migrated to another CMS server, it will not run.
- Add each task after the task from which it was copied The timetable is capable of running on this or any other CMS server. If this timetable is backed up and migrated to another CMS server, it will function normally.

#### Before you begin

The following items should be read and understood before making global edits to timetable tasks:

- Only the owner of the timetable or an administrator can globally edit a timetable.
- If an error is made during a global edit, CMS displays an error message describing the nature of the problem. All errors must be corrected before CMS allows you to complete the modifications.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select **Timetable** and press the Enter key.

CMS displays the Timetable window.

Timetable	test1
	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: cms	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
< <u>x</u> > Once	Next
<pre></pre>	Previous
<_> Hourly, Stop time: <u>11:59 PM</u>	
<_> Daily,	
Hourly/Daily Days (Select any you wish):	
[ <u>x</u> ] Sunday [ <u>x</u> ] Tuesday [ <u>x</u> ] Thursday	[ <u>x</u> ] Saturday
[x] Monday [x] Wednesday [x] Friday	
This timetable will run on this or another CMS serve	er
<_> Run only on this CMS server*	
$< \underline{\mathbf{x}} >$ Run on this or another CMS server*	
*These fields not used for Find one or List all	
	21x68

3. Press Ctrl+Z.

The fields in the window are cleared of all default information.

- 4. In the **Timetable name** field, enter the name of the timetable containing the tasks to modify globally.
- 5. Press the Enter key.

CMS shifts focus to the action list.

6. Using the arrow keys, highlight Find one and press the Enter key.


CMS locates the timetable and populates the remaining fields with the information from the timetable.

7. Press the Enter key.

CMS shifts focus to the action list.

8. Using the arrow keys, highlight Global edit and press the Enter key.

CMS displays the Timetable: Global Edit window.



- 9. Select one of the following options by placing an x in the associated field:
  - Add following task All timetables owned by the specified user ID will be modified so that they can only run on this CMS server. Timetables migrated to another server will not function.
  - Add each task after the task from which it was copied All timetables owned by the specified user ID will be modified so that they can run on the current CMS server or, if migrated, a different CMS server.
- 10. Press the Enter key.

CMS shifts focus to the action list and highlights the Modify action.

11. Press the Enter key again.

CMS will display a message in the status line of this window indicating how many timetables were updated.

12. Use the Exit SLK to close this window and return to the Timetable window.

The timetable displayed in the Timetable window does not update automatically. Use the **Find one** action to re-query for this table in order to show the current configuration.

### Globally editing tasks in a timetable

#### About this task

This topic provides the procedure for changing multiple tasks in a timetable to use a common date, time, or printer destination. For example, you may want to run all reports within a timetable so that instead of reporting on data for today (relative date: 0), the reports will use data from yesterday (relative date: -1). Using the global edit feature can change the dates used for these reports in a simple series of steps instead of modifying each task separately. This feature can also be used to modify tasks that have different values for times, dates, or printer destinations so that all specified tasks use consistent values.

#### Before you begin

The following items should be read and understood before making global edits to timetable tasks:

- Only the owner of the timetable or an administrator can globally edit a timetable.
- If an error is made during a global edit, CMS displays an error message describing the nature of the problem. All errors must be corrected before CMS allows you to complete the modifications.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Timetable and press the Enter key.

CMS displays the Timetable window.

Timetable	testl
	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: <u>cms</u>	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
< <u>x</u> > Once	Next
<_> Dates:	Previous
<_> Hourly, Stop time: <u>11:59 PM</u> <_> Daily, Hourly/Daily Days (Select any you wish): [ <u>x</u> ] Sunday [ <u>x</u> ] Tuesday [ <u>x</u> ] Thursday [ <u>x</u> ] Monday [ <u>x</u> ] Wednesday [ <u>x</u> ] Friday This timetable will run on this or another CMS server <_> Run only on this CMS server* < <u>x</u> > Run on this or another CMS server* *These fields not used for Find one or List all	er
	21x68

3. Press Ctrl+Z.

The fields in the window are cleared of all default information.

- 4. In the **Timetable name** field, enter the name of the timetable containing the tasks to modify globally.
- 5. Press the Enter key.

CMS shifts focus to the action list.

6. Using the arrow keys, highlight Find one and press the Enter key.

CMS locates the timetable and populates the remaining fields with the information from the timetable.

7. Press the Enter key.

CMS shifts focus to the action list.

8. Using the arrow keys, highlight Get contents and press the Enter key.

CMS displays the Timetable: Get Contents window.

		Get Conte	ents						test1
	:(5):							Add ta	asks
Time	table:	Sample t	imetaŁ	ble	Number	of	tasks: 10	Сору	
Task	Actio	n Window	Title	2				Delete	2
1	Run	Rpts: H	Hist:	Agent:	Summary:	Int	erval Input	Global	l edit
2	Run	Rpts: I	Hist:	Agent:	Summary:	Dai	ly Input	Modify	/
3	Run	Rpts: I	Hist:	Ağent:	Summary:	Wee	kly Input		
4	Run	Rpts: I	Hist:	Agent:	Summary:	Mon	thly Input	test1	a510
5	Run						Interval Input	test1	a510
6	Run	Rpts: I	Hist:	Ağent:	split/sk	ill:	Daily Input	test1	a510
7	Run	Rpts: I	Hist:	Agent:	split/sk	ill:	Weekly Input	test1	a510 (
								103>	<132 >

- 9. In the **Task(s)** field, enter the tasks to modify using the following methods:
  - Range For example, 1–50.
  - Separate values For example, 1; 3; 6; 7.
  - Combination For example, 1; 3-7; 10.
- 10. After the tasks to globally edit have been specified, press the Enter key.

CMS shifts focus to the action list.

11. Using the arrow keys, highlight Global edit and press the Enter key.

CMS displays the Timetable: Get contents: Global edit window.

Timetable: Get Contents: Global Edit	test 1
Field to change (Select one):	Confirm
< <u>x</u> > Date/Dates	Modify
<_> Times	
<_> Printer	

- 12. Place an x in the field that will be changed for all specified tasks.
- 13. In the field to the right of the selected option, enter one or more values as necessary.

To have multiple reports retrieve call center data that occurred at 2:00 PM, place an  $\times$  in the **Times** option and enter 2:00 PM or 14:00 in the associated field to the right.

For the **Date/Dates** option, enter dates in either MM/DD/YY format or the relative format based on today (0 for today, -1 for yesterday). You can separate individual data entry items with semicolons (;) and value ranges with hyphens (-) between entries.

14. Press the Enter key.

CMS shifts focus to the action list.

15. Using the arrow keys, highlight **Confirm** and press the Enter key.

CMS displays the Timetable: Get Contents: Global Edit: Confirm window.

Timetable: Get Contents: Global Edit: Confirm te	st 1
The following tasks have fields of the selected type and can be modified t	:0
use the new value(s) as shown below.	
Task Title Values	
2 Rpts: Hist: Skill: AUX: Daily Input 42 0 lpr /usr/tmp/11.21	
Successful	

This window is used to confirm the tasks that will be modified. No changes have been made at this point. If some specified tasks do not appear in the confirmation window, it is because those tasks do not use the data specified when they are run. For example, some reports only use a date value to retrieve information; therefore, changing the time value will not modify this task. If the tasks listed in this window are not correct, you can go back to the previous windows and make adjustments as necessary.

16. Select the Exit SLK.

CMS closes the Timetable: Get Contents: Global Edit: Confirm window.

17. If you are satisfied with the changes, press the Enter key.

CMS shifts focus to the action list.

18. Using the arrow keys, highlight Modify and press the Enter key.

CMS modifies the tasks in this timetable with the data values specified, closes the Timetable: Get contents: Global edit window, and displays <code>Successful</code> in the status line when the operation is complete.

19. Close the Timetable: Get contents: Global edit by selecting the Exit SLK.

### Deleting tasks from a timetable

#### Before you begin

The following items should be read and understood before deleting tasks from a timetable:

- Only the owner of the timetable or an administrator can delete tasks from a timetable.
- To exit the timetable without saving any changes, select the **Stop** item from the **Keep** SLK menu.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Timetable and press the Enter key.

CMS displays the Timetable window.

Timetable	test1
	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: cms	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
<x> Once</x>	Next
<pre></pre>	Previous
<_> Hourly, Stop time: <u>11:59 PM</u>	
<_> Daily,	
Hourly/Daily Days (Select any you wish):	
[ <u>x]</u> Sunday [ <u>x</u> ] Tuesday [ <u>x</u> ] Thursday	[ <u>x</u> ] Saturday
[ <u>x]</u> Monday [ <u>x</u> ] Wednesday [ <u>x</u> ] Friday	
This timetable will run on this or another CMS serve	er
< > Run only on this CMS server*	
<x> Run on this or another CMS server*</x>	
*These fields not used for Find one or List all	
	21x68

3. Press Ctrl+Z.

The fields in the window are cleared of all default information.

- 4. In the **Timetable name** field, enter the name of the timetable containing the tasks to modify globally.
- 5. Press the Enter key.

CMS shifts focus to the action list.

6. Using the arrow keys, highlight **Find one** and press the Enter key.

CMS locates the timetable and populates the remaining fields with the information from the timetable.

7. Press the Enter key.

CMS shifts focus to the action list.

8. Using the arrow keys, highlight **Get contents** and press the Enter key.

CMS displays the Timetable: Get Contents window.

		Get Con	tents							test1
Task	(5):								Add ta	sks
Time	table:	Sample	timetal	ble	Number	of 1	tasks: 10		Copy	
Task	Actio	n Window	w Title	e					Delete	
1	Run	Rpts:	Hist:	Agent:	Summary:	Inte	erval Inpu	t	Global	edit
2	Run	Rpts:	Hist:	Agent:	Summary:	Dai	ly Input		Modify	
3	Run	Rpts:	Hist:	Agent:	Summary:	Weeł	kly Input			
4	Run	Rpts:	Hist:	Agent:	Summary:	Mont	thly Input		test1	a510
5	Run	Rpts:	Hist:	Agent:	_Split/Sk	ill:	Interval	Input	test1	a510
6	Run						Daily Inp		test1	a510
7	Run						Weekly In		test1	a510 🗸
				-					103×3	132 >

- 9. In the **Task(s)** field, enter the number of the task to delete.
- 10. Press the Enter key.

CMS shifts focus to the action list.

11. Using the arrow keys, highlight **Delete** and press the Enter key.

CMS displays a confirmation window.

12. Press the Y key and then the Enter key to save the changes.

CMS deletes the task from the timetable, the tasks are renumbered, the timetable is saved, and the status line displays a <code>Successful</code> message.

13. Select the **Exit** SLK to close the Timetable: Get Contents window.

### **Deleting a timetable**

#### About this task

Only the owner of the timetable or an administrator can delete timetables.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Timetable and press the Enter key.

CMS displays the Timetable window.

Timetable	test1
	Add
Timetable name:	Сору
Description:	Delete
	Find one
User ID: <u>cms</u>	Get contents
Start time:	Global edit
Start date:	List all
Frequency and attributes (Select only one):	Modify
< <u>x</u> > Once	Next
<_> Dates:	Previous
<pre></pre>	
	21x68

3. Press Ctrl+Z.

The fields in the window are cleared of all default information.

- 4. In the **Timetable name** field, enter the name of the timetable containing the tasks to modify globally.
- 5. Press the Enter key.

CMS shifts focus to the action list.

6. Using the arrow keys, highlight Find one and press the Enter key.

CMS locates the timetable and populates the remaining fields with the information from the timetable.

7. Press the Enter key.

CMS shifts focus to the action list.

8. Using the arrow keys, highlight **Delete** and press the Enter key.

CMS displays a confirmation window.

9. Press the Y key and then the Enter key.

CMS deletes the timetable and a successful message is displayed in the status line.

# Shortcuts

A shortcut is similar to a timetable except that it is not run based on time but rather when it is executed by a user. A shortcut is a fast and easy way for an ASCII terminal user to select windows that are used often. For example, you can create a shortcut for two different real-time reports that you normally view throughout the day. The shortcut displays these reports, fills out the input windows, and places them on the terminal screen so that they can both be viewed at once. Although useful for other tasks, shortcuts are most commonly used to run real-time reports.

### **Before using shortcuts**

The following items should be read and understood before working with shortcuts:

- · Shortcuts are only available through the ASCII interface to CMS .
- Each user can create a maximum of ten shortcuts.
- Once a shortcut has started running, it cannot be stopped.
- Shortcuts can be copied from those created by other users.
- You cannot exceed your maximum allowable window count by using a shortcut.
- You cannot create a custom report using a shortcut.
- When using the **Keep** mode to record the tasks for a shortcut, the **Current** Screen-Labeled Key (SLK) will only shift focus between windows in the shortcut window. It will not shift focus to windows that were open before you entered **Keep** mode.
- When you create a shortcut, tasks that have errors in them are saved, but they will not
  execute when the shortcut is run. The task containing the error will display an error message
  which causes the shortcut to stop. The error must be corrected before the shortcut can run
  properly. To delete the error, exit the shortcut without saving changes or edit the shortcut if
  the error has already been saved.
- Deleting a CMS user who owns shortcuts results in those shortcuts also being deleted.

### **Permissions for shortcuts**

Depending on the procedure that you want to perform, you need the following permissions:

- All users are allowed to create shortcuts.
- You must have "read" and "write" permissions for any CMS subsystems and ACD entities associated with the tasks included in a shortcut.
- Users without the Administrator permission can view and copy the shortcuts of other users, but they cannot add, modify, or delete those shortcuts.
- If the access permissions for a user are changed, it could cause the shortcuts of that user to not run properly. For example, removing skill permissions for a user can result in a shortcut report not running or displaying data for that skill.

### **Creating a shortcut**

#### About this task

This topic provides the procedure for creating a shortcut and adding tasks for it to perform.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Shortcut and press the Enter key.

CMS displays the Shortcut window.

Shortcut name: Copy Description: Delete User ID: <u>cms</u> Get contents List all Modify Next Previous	Shortcut	test1
	Shortcut name: Description:	Add Copy Delete Find one Get contents List all Modify Next

3. In the Shortcut name field, enter a unique name for this shortcut.

Keep the name for the shortcut simple as it becomes the name that must be entered when you wish to execute it from the CMS **Main Menu**.

4. In the **Description** field, enter a brief description for the shortcut.

This field is optional.

5. Press the Enter key.

CMS shifts focus to the action list.

6. Highlight the Add item and press the Enter key.

CMS displays the Main Menu. CMS is now in Keep mode.

- 7. Use the **Main Menu** to select tasks. Multiple windows can be shown on the screen at one time.
- 8. Use the **Move** and **Size** items from the **Wind** SLK menu to adjust the placement and dimensions of each window.
- 9. When satisfied with the report windows, input windows, and their placement and sizes on the screen, select the **Stop** item from the **Keep** SLK menu.

CMS displays a confirmation window asking if the shortcut should be saved.

10. Press the Y key and then Enter to save the shortcut.

CMS displays the Shortcut window again and the status line displays a Successful message indicated that the shortcut was saved.

11. Select the Exit SLK to close the Shortcut window and return to the Main Menu.

### Adding tasks to a shortcut

#### About this task

This topic provides the procedure for adding tasks to an existing shortcut.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Shortcut and press the Enter key.

CMS displays the Shortcut window.


Shortcut	test 1
Shortcut Shortcut name: Description: User ID: <u>cms</u>	test 1 Add Copy Delete Find one Get contents List all Modify Next Previous

- 3. In the **Shortcut name** field, enter the name of the shortcut which will have new tasks added.
- 4. Press the Enter key.

CMS shifts focus to the action list.

5. Highlight Get contents and press the Enter key.

CMS displays the Shortcut: Get Contents window.



- 6. In the Task(s) field, enter the number of the task that the new task will follow.
  To add a task in the second position of the shortcut, enter 1 in the Task(s) field.
  If you wish the new task to be in the first position, leave the Task(s) field blank.
- 7. Press the Enter key.

CMS shifts focus to the action list.

8. Highlight Add tasks and press the Enter key.

CMS displays the Main Menu.

9. On the **Main Menu**, use the normal menu items to perform the tasks you want to add to the shortcut.

When you have made and validated each action list selection, Entries Stored displays on the status line.

10. When you have finished performing tasks for the shortcut, select **Stop** from the **Keep** SLK menu.

CMS displays a confirmation asking if the changes should be saved.

11. Press the  ${\tt Y}$  key and then the  ${\tt Enter}$  key.

CMS saves the tasks and displays the Shortcut: Get Contents window.

12. Select the Exit SLK to close the Shortcut: Get Contents window.

### **Running a shortcut**

#### About this task

This topic provides the procedure for executing a shortcut.

#### Procedure

1. At the CMS Main Menu, press the ; (semicolon) key.

CMS selects the command line of the Main Menu.

MainMenu Reports>		
Dictionary>		
Exceptions>		
Agent Administration>		
Call Center Administration>		
Custom Reports>		
User Permissions>		
System Setup>		
Maintenance>		
Logout		
;		

2. Enter the name of the shortcut to run and press the Enter key.

The shortcut starts running and locks the keyboard until the shortcut finishes. When the shortcut finishes, the status line displays a Successful message.

### Modifying a shortcut description

#### About this task

This topic provides the procedure for editing the name or description of a shortcut.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Shortcut and press the Enter key.

CMS displays the Shortcut window.

Shortcut	test 1
	Add
Shortcut name:	Сору
Description:	Delete
	Find one
User ID: cms	Get contents
	List all
	Modify
	Next
	Previous

- 3. In the Shortcut name field, enter the name of the shortcut to modify.
- 4. Press the Enter key.

CMS shifts focus to the action list.

5. Highlight Find one and press the Enter key.

CMS retrieves the shortcut and populates the **Description** and **User ID** fields with information from the shortcut.

- 6. Make the necessary change to the **Description** field.
- 7. Press the Enter key.

CMS shifts focus to the action list.

8. Highlight Modify and press the Enter key.

CMS saves the changes to the shortcut displays a <code>Successful</code> message in the status line.

9. Select the Exit SLK to close the Shortcut window.

### Copying a shortcut

#### About this task

This topic provides the procedure for copying an existing shortcut into a new shortcut. All users can copy shortcuts owned by other users. However, no shortcuts owned by your user ID, even as an Administrator, can be copied by you to another user. It is not possible to copy a shortcut over an existing shortcut.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Shortcut and press the Enter key.

CMS displays the Shortcut window.

dd
Сору
elete
ind one
et contents
ist all
lodify
lext
revious

- 3. In the **Shortcut name** field, enter the name of the new shortcut that will be created.
- 4. In the **Description** field, enter a brief phrase identifying the new shortcut.

This field is optional.

- 5. In the **User ID** field, ensure your user ID is present.
- 6. Press the Enter key.

CMS shifts focus to the action list.

7. Highlight Copy and press the Enter key.

CMS displays the Shortcut: Copy window.



- 8. In the **Copy from** field, enter the name of the shortcut to copy as the new shortcut.
- 9. In the **User ID** field, enter the ID of the user that owns the shortcut to copy.
- 10. Press the Enter key.

CMS shifts focus to the action list.

11. Press the Enter key again.

CMS creates the new shortcut, closes the Shortcut: Copy window, and displays a  $\tt Successful$  message in the status line.

12. Select the **Exit** SLK to close the Shortcut window.

### **Copying shortcut tasks**

#### About this task

This topic provides the procedure for copying tasks within a shortcut.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Shortcut and press the Enter key.

CMS displays the Shortcut window.


	Add
Shortcut name:	Сору
Description:	Delete
	Find one
User ID: <u>cms</u>	Get contents
	List all
	Modify
	Next
	Previous
L	

- 3. In the **Shortcut name** field, enter the name of the shortcut in which a task will be copied.
- 4. Press the Enter key.

CMS shifts focus to the action list.

5. Highlight Get contents and press the Enter key.

CMS displays the Shortcut: Get Contents window.



6. In the Task(s) field, enter the number of the task to copy and press the Enter key.

CMS shifts focus to the action list.

7. Highlight Copy and press the Enter key.

CMS displays the Shortcut: Get Contents: Copy window.

Shortcut: Get Contents: Copy	G3V6_eas
Specify where to put copied tasks (Select one):	Copy
<x> Add following task 2_</x>	
< > Add each task after the task from which it	
was copied	
*	

- 8. Place an x in one of the following options:
  - Add following task This option will create the task after the task number specified in the field to the right.
  - Add each task after the task from which it was copied This option will create the task and place it immediately following the original task. If you specified to make a copy of task #1, the copy will be created as task #2. Any other tasks are shifted to a higher number to accommodate this action.
- 9. Press the Enter key.

CMS shifts focus to the action list.

10. Press the Enter key again.

CMS copies the original task, creates the new task, closes the Shortcut: Get Contents: Copy window, and displays a Successful message in the status line.

If any sort of error occurs, the status line will display Failed and CMS displays an error message describing the nature of the error.

11. Select the **Exit** SLK to close the Shortcut: Get Contents window.

### Modifying shortcut tasks

#### About this task

This topic provides the procedure for editing tasks within a shortcut.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Shortcut and press the Enter key.

CMS displays the Shortcut window.


Shortcut	test 1
Shortcut name: Description: User ID: <u>cms</u>	Add Copy Delete Find one Get contents List all Modify Next Previous

- 3. In the **Shortcut name** field, enter the name of the shortcut where tasks will be modified.
- 4. Press the Enter key.

CMS shifts focus to the action list.

5. Highlight Get contents and press the Enter key.

CMS displays the Shortcut: Get Contents window.



In the Task(s) field, enter the number of the task to modify and press the Enter key.
 CMS shifts focus to the action list.

7. Highlight Modify and press the Enter key.

CMS displays the input window of the specified task.

8. Change the input parameters of the window as necessary.

For example, this might include changing the split, agent, or another entity on which a report is based. This can also include making changes to the size and position of the task window.

9. When the appropriate information has been entered, press the Enter key.

CMS shifts focus to the action list.

10. Highlight Modify and press the Enter key.

CMS displays a confirmation asking if the changes should be saved.

11. Press the Y key and then the Enter key.

CMS saves the changes to the task, closes the task window, and displays a Successful message in the status line.

12. Select the Exit SLK to close the Shortcut: Get Contents window.

### **Deleting shortcut tasks**

#### About this task

This topic provides the procedure for deleting a task from a shortcut.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Shortcut and press the Enter key.

CMS displays the Shortcut window.

Shortcut	test 1
Shortcut name: Description:	Add Copy Delete
	Find one
User ID: <u>cms</u>	Get contents
	List all
	Modify
	Next
	Previous

- 3. In the **Shortcut name** field, enter the name of the shortcut containing the task to delete.
- 4. Press the Enter key.

CMS shifts focus to the action list.

5. Highlight Get contents and press the Enter key.

CMS displays the Shortcut: Get Contents window.

Shortcut: Get Contents Task(s):		G3V6_eas Add tasks
Shortcut: Shortcut8 Number of tasks: 2 Task Action Window Title 1 Run Rpts: Real: Split/Skill: Skill Top Agent Report In 2 Run Rpts: Hist: Agent: AUX: Interval Input	a a c	Copy Delete Modify
Successful		5x132 >

- 6. In the **Task(s)** field, enter the number of the task to delete.
- 7. Press the Enter key.

CMS shifts focus to the action list.

8. Highlight **Delete** and press the Enter key.

CMS displays a confirmation window asking if the changes to the shortcut should be saved.

9. Press the Y key and then the Enter key.

CMS deletes the specified tasks and displays the Shortcut: Get Contents window.

10. Select the Exit SLK to close the Shortcut: Get Contents window.

### **Deleting a shortcut**

#### About this task

This topic provides the procedure for deleting a shortcut from the CMS server.

#### Procedure

- 1. From the CMS Main Menu, select the Keep Screen-Labeled Key (SLK).
- 2. Select Shortcut and press the Enter key.

CMS displays the Shortcut window.

Shortcut	_ test1
Shortcut name: Description: User ID: <u>cms</u>	Add Copy Delete Find one Get contents List all Modify Next Previous

3. In the **Shortcut name** field, enter the name of the shortcut to delete.

Shortcuts owned by other users cannot be deleted.

4. Press the Enter key.

CMS shifts focus to the action list.

5. Highlight Find one and press the Enter key.

CMS retrieves the information for the specified shortcut. If the shortcut with the name specified cannot be found, this will be indicated on the status line.

6. Verify that this is the shortcut to be deleted and press the Enter key.

CMS shifts focus to the action list.

7. Highlight Delete and press the Enter key.

CMS displays a confirmation window.

8. Press the Y key and then the Enter key.

CMS deletes the specified shortcut and displays a <code>Successful</code> message in the status line.

# **Chapter 16: Resources**

# **Documentation**

#### **CMS and CMS Supervisor Documents**

Title	Description	Audience	
Overview			
Avaya Call Management System Overview and Specification	Describes tested product characteristics and product capabilities including feature descriptions, interoperability, performance specifications, security, and licensing requirements.	Sales engineers, Administrators	
Product Privacy Statement for Avaya Call Management System	Describes how personal data is stored and processed by CMS.	Administrators	
Design			
Avaya Customer Experience Virtualized Environment Solution Description	Describes the AvayaCustomer Experience Virtualized Environment market solution from a holistic perspective that focuses on the functional view of the solution architecture.	Sales engineers	
Installation, upgrades, maintenar	ce, and troubleshooting		
Deploying Avaya Call Management System	Describes how to plan, deploy, and configure CMS on new VMware-based installations.	Avaya support personnel	
Deploying Avaya Call Management System on Amazon Web Services	Describes how to plan, deploy, and configure CMS on new Amazon Web Services installations.	Avaya support personnel	
Avaya Call Management System Dell <sup>®</sup> PowerEdge <sup>™</sup> R630 and R730 Hardware Installation, Maintenance and Troubleshooting	Describes how to install, maintain, and troubleshoot Dell <sup>®</sup> servers used with CMS.	Avaya support personnel	
Avaya Call Management System HPE DL20 G9 and DL380 G9 Hardware Installation, Maintenance, and Troubleshooting	Describes how to install, maintain, and troubleshoot HPE servers used with CMS.	Avaya support personnel	

Table continues...

Title	Description	Audience
Planning for Avaya Call Management System Upgrades	Describes the procedures customers must plan for before and after upgrading to a new CMS release.	Administrators
Upgrading Avaya Call Management System	Describes the procedures required to upgrade to a new CMS release.	Avaya support personnel
Maintaining and Troubleshooting Avaya Call Management System	Describes how to configure, maintain, and troubleshoot CMS.	Avaya support personnel, Administrators
Avaya Call Management System and Communication Manager Connections, Administration, and Troubleshooting	Describes how to connect and administer the Communication Manager systems used by CMS.	Avaya support personnel, Administrators
Avaya Call Management System Base Load Upgrade	Describes the procedures to upgrade from one base load (for example, 19.1.0.0) to another base load (for example, 19.1.0.1). Not all releases support base load upgrades.	Administrators
Using Avaya Call Management System High Availability	Describes how to install and maintain a CMS HA system.	Avaya support personnel, Administrators
Using Avaya Call Management System LAN Backup	Describes how to back up your CMS data using a LAN connection to a remote server.	Administrators
Avaya Call Management System High Availability Connectivity, Upgrade and Administration	Describes how to connect to HA servers and upgrade to HA.	Avaya support personnel, Administrators
Using Avaya Call Management System High Availability	Describes how to install and maintain your CMS High Availability (HA) system.	Avaya support personnel, Administrators
Administration		
Administering Avaya Call Management System	Provides instructions on administering a call center using CMS Supervisor.	Avaya support personnel, Administrators
Avaya Call Management System Call History Interface	Describes the format of the Call History data files and how to transfer these files to another computer.	Administrators
Using ODBC and JDBC with Avaya Call Management System	Describes how to use Open Database Connectivity (ODBC) and Java Database Connectivity (JDBC) with CMS.	Administrators
Avaya Call Management System Database Items and Calculations	Describes each database item and calculation that CMS tracks and how CMS calculates the values displayed on CMS reports and CMS Supervisor reports.	Administrators, Report designers

Table continues...

Title	Description	Audience		
Avaya Call Management System Custom Reports	Describes how to design and create custom reports in CMS.	Administrators, Operations personnel, Report designers		
Avaya Call Management System Security	Describes how to implement security features in CMS.	Avaya support personnel, Administrators		
CMS Supervisor	CMS Supervisor			
Avaya CMS Supervisor Clients Installation and Getting Started	Describes how to install and configure CMS Supervisor.	Avaya support personnel, Administrators		
Avaya CMS Supervisor Reports	Describes how to use CMS Supervisor reports.	Administrators, Operations personnel		
Avaya CMS Supervisor Report Designer	Describes how to create new reports and to edit existing reports through Report Designer and Report Wizard.	Administrators, Operations personnel, Report designers		

### Avaya Solutions Platform Documents

Title	Description	Audience
Avaya Solutions Platform Overview and Specification	Describes the key features of Avaya Solutions Platform server	IT Management, sales and deployment engineers, solution architects, support personnel
Installing the Avaya Solutions Platform 130 Appliance	Describes how to install Avaya Solutions Platform 130 Series servers.	Sales and deployment engineers, solution architects, support personnel
Maintaining and Troubleshooting Avaya Solutions Platform 130 Appliance	Describes procedures to maintain and troubleshoot Avaya Solutions Platform 130 Series servers.	Sales and deployment engineers, solution architects, support personnel
Avaya Solutions Platform 130 Series iDRAC9 Best Practices	Describes procedures to use the iDRAC9 tools on the Avaya Solutions Platform 130 Series servers.	Sales and deployment engineers, solution architects, support personnel

#### WebLM Documents

Title	Description	Audience
Deploying standalone Avaya WebLM in Virtual Appliance	Deploy the application in virtual appliance environment by using Solution Deployment Manager	Implementation personnel

Table continues...

Title	Description	Audience
Deploying standalone Avaya WebLM in Virtualized Environment	Deploy the application in virtualized environment.	Implementation personnel
Deploying standalone Avaya WebLM in Infrastructure as a Service Environment	Deploy the application on cloud services.	Implementation personnel
Deploying standalone Avaya WebLM in Software-Only Environment	Deploy the application in software-only environment.	Implementation personnel
Upgrading standalone Avaya WebLM	Upgrade the application.	Implementation personnel
Administering standalone Avaya WebLM	Do administration tasks	System administrators

#### **VMware Documents**

VMware component or operation	Document description	Document URL
vSphere Virtual Machine Administration	<ul> <li>Provides information on managing virtual machines in the VMware vSphere Web Client for vSphere 6.0 or later. This document also provides information of the following:</li> <li>Deploying OVF templates</li> <li>Configuring virtual machine hardware and options</li> <li>Managing Virtual Machines</li> </ul>	https://docs.vmware.com/en/ VMware-vSphere/6.5/ com.vmware.vsphere.vm_admin. doc/GUID-55238059-912E-411F- A0E9-A7A536972A91.html
vSphere Web Client	Provides information on how through a browser vSphere Web Client connects to a vCenter server or directly to an ESXi host if a vCenter Server is not used.	https://docs.vmware.com/en/ VMware-vSphere/6.5/ com.vmware.vsphere.vcenterhost .doc/GUID- A618EF76-638A-49DA-991D- B93C5AC0E2B1.html

#### Note:

If the document description (link) are no longer active, consult VMware for documents associated with the component or operation.

#### **Related links**

<u>Finding documents on the Avaya Support website</u> on page 539 <u>Accessing the port matrix document</u> on page 539 <u>Avaya Documentation Center navigation</u> on page 540

### Finding documents on the Avaya Support website

#### Procedure

- 1. Go to https://support.avaya.com.
- 2. At the top of the screen, type your username and password and click Login.
- 3. Click Support by Product > Documents.
- 4. In **Enter your Product Here**, type the product name and then select the product from the list.
- 5. In **Choose Release**, select the appropriate release number.

The **Choose Release** field is not available if there is only one release for the product.

6. In the **Content Type** filter, click a document type, or click **Select All** to see a list of all available documents.

For example, for user guides, click **User Guides** in the **Content Type** filter. The list only displays the documents for the selected category.

7. Click Enter.

### Accessing the port matrix document

#### Procedure

- 1. Go to https://support.avaya.com.
- 2. Log on to the Avaya website with a valid Avaya user ID and password.
- 3. On the Avaya Support page, click **Support by Product > Documents**.
- 4. In **Enter Your Product Here**, type the product name, and then select the product from the list of suggested product names.
- 5. In Choose Release, select the required release number.
- 6. In the Content Type filter, select one or both the following categories:
  - Application & Technical Notes
  - Design, Development & System Mgt

The list displays the product-specific Port Matrix document.

7. Click Enter.

### **Avaya Documentation Center navigation**

The latest customer documentation for some programs is now available on the Avaya Documentation Center website at <u>https://documentation.avaya.com</u>.

#### Important:

For documents that are not available on Avaya Documentation Center, click **More Sites** > **Support** on the top menu to open <u>https://support.avaya.com</u>.

Using the Avaya Documentation Center, you can:

- · Search for content by doing one of the following:
  - Click Filters to select a product and then type key words in Search.
  - From **Products & Solutions**, select a solution category and product, and then select the appropriate document from the list.
- Sort documents on the search results page.
- Click Languages ( ) to change the display language and view localized documents.
- Publish a PDF of the current section in a document, the section and its subsections, or the entire document.
- Add content to your collection by using **My Docs** ( $\bigtriangleup$ ).

Navigate to the **Manage Content > My Docs** menu, and do any of the following:

- Create, rename, and delete a collection.
- Add topics from various documents to a collection.
- Save a PDF of selected content in a collection and download it to your computer.
- Share content in a collection with others through email.
- Receive collection that others have shared with you.
- Add yourself as a watcher using the Watch icon (

Navigate to the Manage Content > Watchlist menu, and do the following:

- Enable Include in email notification to receive email alerts.
- Unwatch selected content, all content in a document, or all content on the Watch list page.

As a watcher, you are notified when content is updated or deleted from a document, or the document is removed from the website.

- Share a section on social media platforms, such as Facebook, LinkedIn, and Twitter.
- Send feedback on a section and rate the content.

#### 😵 Note:

Some functionality is only available when you log on to the website. The available functionality depends on the role with which you are logged in.

# Viewing Avaya Mentor videos

Avaya Mentor videos provide technical content on how to install, configure, and troubleshoot Avaya products.

#### About this task

Videos are available on the Avaya Support website, listed under the video document type, and on the Avaya-run channel on YouTube.

- To find videos on the Avaya Support website, go to <u>https://support.avaya.com/</u> and do one of the following:
  - In Search, type Avaya Mentor Videos, click Clear All and select Video in the Content Type.
  - In **Search**, type the product name. On the Search Results page, click **Clear All** and select **Video** in the **Content Type**.

The Video content type is displayed only when videos are available for that product.

In the right pane, the page displays a list of available videos.

- To find the Avaya Mentor videos on YouTube, go to <u>www.youtube.com/AvayaMentor</u> and do one of the following:
  - Enter a key word or key words in the **Search Channel** to search for a specific product or topic.
  - Scroll down Playlists, and click a topic name to see the list of videos available for the topic. For example, Contact Centers.

😵 Note:

Videos are not available for all products.

## Support

Go to the Avaya Support website at <u>https://support.avaya.com</u> for the most up-to-date documentation, product notices, and knowledge articles. You can also search for release notes, downloads, and resolutions to issues. Use the online service request system to create a service request. Chat with live agents to get answers to questions, or request an agent to connect you to a support team if an issue requires additional expertise.

#### **Related links**

Using the Avaya InSite Knowledge Base on page 542

## Using the Avaya InSite Knowledge Base

The Avaya InSite Knowledge Base is a web-based search engine that provides:

- Up-to-date troubleshooting procedures and technical tips
- · Information about service packs
- Access to customer and technical documentation
- · Information about training and certification programs
- Links to other pertinent information

If you are an authorized Avaya Partner or a current Avaya customer with a support contract, you can access the Knowledge Base without extra cost. You must have a login account and a valid Sold-To number.

Use the Avaya InSite Knowledge Base for any potential solutions to problems.

- 1. Go to http://www.avaya.com/support.
- 2. Log on to the Avaya website with a valid Avaya user ID and password.

The system displays the Avaya Support page.

- 3. Click Support by Product > Product-specific Support.
- 4. In Enter Product Name, enter the product, and press Enter.
- 5. Select the product from the list, and select a release.
- 6. Click the Technical Solutions tab to see articles.
- 7. Select relevant articles.

# **Appendix A: Updating time zones**

# Updating time zones displayed to users

#### About this task

A time zone list stored on the CMS server is used by the CMS Supervisor PC client and Web client for display of available time zones in any report input screens as well as on the System Setup Data Summarization Time Zone administration screen.



For daily, weekly, and monthly archived data reports, you must administer time zones specific to each ACD and tenant (If the Multi-Tenancy feature is installed) using System Setup Data Summarization Time Zone. Your available choices for this administration screen is based on the <code>TimeZoneList.dat</code> file.

If a CMS Supervisor client on the current release is connecting to a CMS server on an older release, follow the setting time zones for interval reports instructions in *Avaya CMS Supervisor Clients Installation and Getting Started*.

#### Procedure

1. Enter the following commands to display the time zone DAT files. The TimeZoneList.dat file is a subset of full time zone list file, TimeZoneFullList.dat.

cd /cms/db/config

ls

The system displays the list of DAT files:

TimeZoneFullList.dat TimeZoneList.dat TimeZoneShortList.dat

2. Save the time zone list file copying it to a temporary file.

#### cp TimeZoneList.dat TimeZoneListSaved.dat

3. If you only want to add new time zones to the TimeZoneList.dat file, skip this step. Otherwise, edit the file to remove any time zones you do not wish to use. Each time zone is on a separate line. Remove only those lines that you do not need.

#### vi TimeZoneList.dat

4. When finished editing, save and close the file.

:wq!

5. To add new time zones, make a temporary copy of the TimeZoneFullList.dat file for editing. Edit your temporary file to contain only the new time zones you wish to add to your TimeZoneList.dat file. Each time zone is on a separate line. Remove only those time zones you do not need.

```
cp TimeZoneFullList.dat TimeZoneEditList.dat
```

```
vi TimeZoneEditList.dat
```

6. When finished editing, save and close the file.

:wq!

7. Create one new TimeZoneList.dat file with your changes and delete your temporary files.

```
cat TimeZoneList.dat TimeZoneEditList.dat > MyTimeZoneList.dat
```

```
mv MyTimeZoneList.dat TimeZoneList.dat
```

```
rm MyTimeZoneList.dat TimeZoneEditList.dat TimeZoneListSaved.dat
```

The CMS server will automatically update the CMS Supervisor PC and Web clients with the new time zone choices.

abandoned call	A call on which a caller hangs up before an agent answers.
abandoned call search	An ACD capability that enables the system to verify that the caller is still on the line before passing the call to an agent.
acceptable service level	1) A target value for the acceptable amount of time before an agent answers a call.
	2) A percentage of calls answered within a set amount of time (for example, 80% of calls answered within 20 seconds).
access permissions	Permissions assigned to a CMS user so that the user can access different CMS capabilities or administer specific elements such as splits/skills, trunks, or vectors. Access permissions can be read, write, or exceptions. See also <u>read permission</u> on page 555, <u>write permission</u> on page 558.
ACD	See Automatic Call Distribution (ACD) on page 547
ACD call	1) A call that queues to a split/skill and is answered by an agent in that split/skill.
	2) A call that queues as a direct agent call and is answered by the agent for whom it was queued.
Action List	A menu in the upper right-hand corner of most CMS ASCII screens. The menu lists the actions available for that particular window.
active VDN calls	A Call Vectoring feature on Communication Manager systems that provides conditional branching to a different step in the same vector or to a different vector, based on the number of incoming trunk calls a VDN is processing in a vector or at an agent position. Also called counted calls to VDN.
ACW	See after call work (ACW) on page 545
Adjunct/Switch Applications Interface (ASAI)	A recommendation for interfacing adjuncts and communications systems that is based on the CCITT Q.932 specification for layer 3. ASAI supports activities such as event notification and call control.
after call work (ACW)	An agent state consisting of work related to the preceding ACD call. If an agent hangs up after an ACD call, the agent is in ACW. ACW is also

	accessible by a button on the agent's set and does not have to be related
	to an ACD call.
agent	A person or VRU port that answers calls to an ACD split/skill. The agent is represented to CMS by a login identification keyed into a voice terminal.
agent login ID	A 1- to 9-digit number keyed by an ACD agent from a voice terminal to activate the agent position. Agent logins are needed for all CMS-measured ACD agents.
agent occupancy	The percentage of time that you expect or target for each split/skill agent to spend on ACD calls and in ACD while logged in.
agent position (EAS)	The combination of the agent login ID and the skills the agent is assigned. Data is collected for the agent by skill so that the total work for the agent is the sum of all skills in which the agent worked.
agent position (non- EAS)	The combination of the agent login ID and the split the agent logged into. Agents logged into multiple splits are associated with multiple positions. Call data is collected separately for each agent/split combination.
agent role	A description of the kind of service an agent in multiple skills give for one of these skills. Agent role is a combination of call-handling preference and skill/reserve levels.
agent skill	An attribute that is associated with an ACD agent and that qualifies the agent to handle calls requiring the attribute. An agent can be assigned up to 60 skills; for example, the ability to speak a particular language or the expertise to handle a certain product.
	See also <u>primary skill</u> on page 554 , <u>secondary skill</u> on page 556 , and <u>skill level</u> on page 556
agent state	A feature of agent call handling that allows agents to change their availability to the switch; for example, ACW, AVAIL, AUX.
agent terminal	The voice terminal used by a call center agent.
agent trace	A CMS capability that allows you to trace agent activities such as state changes which can then be shown in a report.
AI	See <u>Auto-in (AI)</u> on page 547.
ANI	See Automatic Number Identification (ANI) on page 547.
announcement	A recorded voice message that typically identifies the call's destination, asks the caller to stay on the line, and describes the product or service offered. With the Call Vectoring feature, announcements can be part of a vector's call processing.

ASA	See Average Speed of Answer (ASA) on page 548.
ASAI	See Adjunct/Switch Applications Interface (ASAI) on page 545.
auto-available split	An ACD capability that enables VRUs such as the CONVERSANT <sup>®</sup> Voice Information System to be brought online again immediately after a power failure or system restart without time-consuming reprogramming.
Auto-in (Al)	An ACD work mode that makes the agent available to receive calls and allows the agent to receive a new ACD call immediately after disconnecting from the previous call.
Automatic Call Distribution (ACD)	1) A switch feature that channels high-volume incoming and outgoing call traffic to agent groups (splits or skills).
	2) An agent state in which the extension is engaged on an ACD call.
Automatic Number Identification (ANI)	An industry term for notification of the calling party number (CPN). When the calling party is connected through a switch, the CPN can be either a billing number for the switch or the station identification (SID) number.
AUX	See <u>auxiliary work (AUX)</u> on page 547.
AUX reason codes	Codes that enable a call center to track an agent's time more precisely when the agent is in the AUX state. Agents can specify why they are in the AUX state - for example, on break or in a meeting.
auxiliary work (AUX)	An agent state in which the agent is doing non-ACD work, is on break, or is in a meeting. Agent enter AUX work by pressing the AUX WORK button or dialing the access code from their voice terminal. Agents can also enter AUX work by going off-hook to make or answer an extension call while in AVAIL mode or with a call on hold.
AVAIL	See <u>available (AVAIL)</u> on page 547.
available (AVAIL)	An agent work mode in which the extension can accept an ACD call. The agent enters this state by selecting the AI (auto-in) or MI (manual-in) work mode.
Avaya Business Advocate	A set of features designed to enhance call and agent selection in a contact center.
Avaya Interactive Response	A powerful voice-response system that may include automated call routing, announcement storage, message retrieval, and callback. Used to be called CONVERSANT.
average agent service time	The average time you are expecting or targeting each agent to spend on an ACD call including talk time and ACW time.

Average Speed of Answer (ASA)	The average time a caller waits in queue before connecting to an agent. The ASA for a split/skill includes the time spent in queue and the time ringing an agent. The ASA for a VDN includes the time spent in vector processing including the time spent in queue and the time ringing for the VDN that the call was answered in.
backup	The process of protecting data by writing the contents of the disk to an archive, such as tape, that can be removed from the computer environment and stored safely.
calculation	A formula for representing call center entities in the Dictionary. Calculations generate the date for fields in a report.
Call Management System (CMS)	A software product used to connect to a switch that monitors and records data for large volumes of telephone calls that are processed through the ACD feature of the switch.
Call Prompting	A switch feature that routes incoming calls based on information supplied by the caller such as an account number. The caller hears an announcement and is prompted to select an option from those listed in the announcement.
Call Vectoring	A switch feature that provides a highly flexible method for processing ACD calls using VDNs and vectors as processing points between trunk groups and splits. Call Vectoring permits a treatment of calls that is independent of splits.
Call Work Code (CWC)	An ACD capability that allows the agent to enter a string of digits during or after the call and send them to CMS for management reporting.
call-based items	The category of database items in CMS that are entered in the database after a call completes. If a call starts and ends in different intrahour intervals, the call-based data is recorded for the interval in which the call completed. Most database items are call-based.
call-handling performance	A parameter of agent administration in an EAS environment that specifies how calls are selected for the agent.
call-handling profile	A set of objectives describing how a split/skill handles calls. Call-handling profiles are part of the Avaya CMS Forecast product.
calls carried	The number of inbound/outbound calls carried by a trunk.
change agent skills	A CMS capability that allows you to change a single agent's skill assignment or apply an agent template to multiple agents.
CMSADM backup	A backup that saves all the file systems on the CMS server including the Solaris operating system, CMS programs, and CMS administration data.

CONN	See <u>connected (CONN)</u> on page 549.
connected (CONN)	A trunk state in which a caller and an agent are connected on an ACD call.
connected call	A non-ACD call connected to an agent through a VDN and for which CMS receives an indication that the call rang or was answered.
CONVERSANT	See Avaya Interactive Response on page 547.
current	A CMS operation that displays data from the current interval.
current interval	The current intrahour period of time (15, 30, or 60 minutes) which is archived to the historical database when the period expires. The current interval is part of the real-time database.
current wait time	The time a call has waited for service in a call queue adjusted for queue priority.
custom report	A real-time or historical report that has been customized from standard reports or created by the user through the Custom Reports subsystem of CMS.
CWC	See <u>Call Work Code (CWC)</u> on page 548.
DABN	See <u>dequeued and abandoned (DABN)</u> on page 550.
DACD	See direct agent ACD (DACD) on page 550.
DACW	See direct agent ACW (DACW) on page 550.
daily data	Interval data that has been converted to a 1-day summary.
data collection	This CMS feature can be used to determine if call activity and the associated ACD data is recorded. In many maintenance operations, it is necessary to disable data collection. If data collection is turned off, CMS does not void data on current call activity.
database	The CMS databases are used to store ACD data according to a specific time period. This can be current and previous intrahour real-time data or intrahour, daily, weekly, and monthly historical data.
database item	A name for a specific type of data stored in one of the CMS databases. A database item can store ACD identifiers such as split numbers or names, login IDs, and VDNs or statistical data on ACD performance such as number of ACD calls, wait time for calls in queue, current states of individual agents, and so forth.
database tables	Each CMS database can consist of several database tables which are used to logically separate data based on different criteria. For example, historical reports can be used to display data on a daily, weekly, or

	monthly basis; each of these different time measurements are stored in separate database tables.
DDC	See direct department calling (DDC) on page 550.
dequeued and abandoned (DABN)	A trunk state in which the trunk quickly goes idle after the caller abandons the call.
designer reports	Customized reports that you create and run through Avaya CMS Supervisor Report Designer. See the Avaya CMS Supervisor Report Designer User Guide for more information.
Dictionary	A CMS capability used to assign easily-interpreted names to call center entities such as login IDs, splits/skills, trunk groups, VDNs, and vectors.
DID	See <u>direct inward dialing (DID)</u> on page 550.
Digital Subscriber Line (DSL)	A public switched telephone network (PSTN) line that provides high bandwidth for short distances using copper cable. This type of line operates at the Basic Rate Interface (BRI) with two 64-kilobit per second circuit-switched channels and one 16-kilobit packet-switched channel. DSL can carry both data and voice signals at the same time.
direct agent ACD (DACD)	An agent state in which the agent is on a direct agent ACD call.
direct agent ACW (DACW)	An agent state in which the agent is in the after call work (ACW) state for a direct agent ACD call.
direct agent calling	An EAS capability that allows a caller to reach the same agent every time and allows the call center to include the call as an ACD call in management tracking. This is ideal for claims processing in which a client needs to speak with the agent handling the claim. It also ensures a high level of customer service without reducing management control.
direct department calling (DDC)	A non-EAS option to select an agent when more than one agent is available. The call goes to the agent closest to the top of an ordered list.
direct inward dialing (DID)	The use of an incoming trunk used for dialing directly from the public network into a communications system without help from the attendant.
DSL	See <u>Digital Subscriber Line (DSL)</u> on page 550.
EAS	See Expert Agent Selection (EAS) on page 551.
entity	A generic term for an agent, split/skill, trunk, trunk group, VDN, or vector.
EWT	See expected wait time (EWT) on page 551.
exception	Activity in an ACD which falls outside the limits you have defined and usually indicates abnormal or unacceptable performance of the ACD,

	agents, splits/skills, VDNs, vectors, trunks, or trunk groups. The parameters used to determine the occurrence of an exception are defined in the Exceptions subsystem of CMS.
exception permissions	The rights that a user has in being notified or viewing the instances where calls, call center entities, or subsystems operated above or below specified thresholds.
expected wait time (EWT)	An estimate of how long a caller will have to wait to be served by a contact center while in queue. EWT is based on current and past traffic, handling time, and staffing conditions. Time spent in vector processing before being queued and time spent ringing an agent with manual answering is not included in the EWT. This is switch-based calculation.
Expert Agent Selection (EAS)	An optional Communication Manager feature that routes incoming calls to an agent who is a member of the specific skill required to handle the problems of the caller.
extension call	A call originated by an agent or a non-ACD call received by an agent. Extension calls include calls an agent makes to set up a conference or transfer.
FBUSY	See <u>forced busy (FBUSY)</u> on page 551.
FDISC	See forced disconnect (FDISC) on page 551.
flex agents	Agents who have the role of roving, backup, or allocated. Top and reserve agents are not flex agents. See the Avaya Business Advocate User Guide for more information.
flexible routing	An ACD capability that allows you to choose how incoming calls should be routed to agents in a split. Calls can be routed to the first available agent or to the most-idle agent.
forced busy (FBUSY)	A trunk state in which the caller receives a forced busy signal.
forced disconnect (FDISC)	A trunk state in which the caller receives a forced disconnect.
Forced Multiple Call Handling (FMCH)	A feature available for Communication Manager system which, when activated for a split/skill, allows calls to be automatically delivered to an idle line appearance if the agent is in the AI (auto-in) or MI (manual-in) work mode and if an unrestricted line appearance is available on the voice terminal.
Forecast, Avaya CMS	An Avaya product used to generate reports displaying expected call traffic and agent/trunk group requirements for the call center for a particular day or period in the future.

historical database	A CMS database consisting of intrahour records for up to 370 days, daily records for up to 5 years, and weekly/monthly records for up to 10 years for each CMS-measured agent, split/skill, trunk, trunk group, VDN, and vector.
historical reports	Reports of past ACD data for various agent, split/skill, trunk, trunk group, VDN, or vector activities. Historical reports summarize call data into daily, weekly, or monthly totals.
HOLD	A trunk state in which an agent has put a call on this trunk on hold.
IDLE	A trunk state in which this trunk is not in use and is waiting for a call.
II	See Information Indicator (II) on page 552.
Inbound Call Management (ICM)	A set of switch and adjunct features using ASAI to enable the adjunct to provide automatic screen delivery and call routing.
Information Indicator (II)	A 2-digit code that identifies the type of originating line for incoming ISDN PRI calls, such as hotel or pay phone.
INFORMIX	A relational database management system used to store and retrieve CMS data.
INFORMIX SQL	An interactive interface typically used to view the INFORMIX database.
Integrated Services Digital Network (ISDN)	A digital standard for telephony that enables analog and digital signals on the same line.
interval ASA	The average time a call waits in queue before connecting to an agent, calculated on reporting interval boundaries. Interval ASA is cleared to zero at the start of each reporting interval. See also <u>Average Speed of Answer (ASA)</u> on page 548 and <u>rolling ASA</u> on page 555.
interval-based items	A category of database items that represent the amount of time during a collection interval spent on a particular activity. Interval-based items are updated throughout the collection interval and timing is restarted at the end of the interval.
intrahour interval	A 15-, 30-, or 60-minute segment of time starting on the hour. An intrahour interval is the basic unit of CMS report time.
ISDN	See Integrated Services Digital Network (ISDN) on page 552.
LAN	See <u>local area network (LAN)</u> on page 552.
local area network (LAN)	A private interactive communication network that allows computers and compatible devices to communicate over short distances, usually less than one mile, at high data transfer rates.

Logical Agent	An EAS feature that associates an agent's login ID with a physical extension when the agent logs in. Properties such as the assigned skills, class of restriction, and coverage path are associated with the login ID rather than the physical extension. This allows agents to log in at any available set.
LOGOFF	An agent trace work mode in which an agent is logged out and not available to take ACD calls.
LOGON	An agent trace work mode in which an agent is logged in and available to take ACD calls.
logout reason codes	Codes that enable an agent to specify the reason for logging out such as the end of a shift or for training.
Look Ahead Interflow (LAI)	A switch feature that can be used to balance the call load among multiple call centers. LAI works with Call Vectoring and ISDN PRI trunks to intelligently route calls between call centers. This allows multiple call centers to share workloads, expand hours of coverage, and allows calls to be transparently handled by call centers in different time zones.
maintenance	A CMS subsystem that is used for routine maintenance of CMS, such as backing up data, checking on the status of the connection to the switch, and scanning the error log.
maintenance busy (MBUSY)	A trunk state in which the trunk is out of service for maintenance purposes.
Manual-In (MI)	An ACD work mode in which an agent is available to receive an ACD call and is automatically placed into the ACW state upon release from the call.
MBUSY	See <u>maintenance busy (MBUSY)</u> on page 553.
МСН	See Multiple Call Handling (MCH) on page 554.
measured	A term meaning that an ACD element such as agent, split/skill, trunk, trunk group, VDN, or vector that is identified to CMS for data collection. If the ACD element is not measured, no data is collected.
МІ	See <u>Manual-In (MI)</u> on page 553.
MIA	See Most Idle Agent (MIA) on page 553.
monthly data	Daily data that has been converted to a monthly summary.
Most Idle Agent (MIA)	An ACD distribution method that maintains a queue of idle agents. An agent is put at the end of the list for a particular split when the agent completes an ACD call for that split. The agent continues to advance on

	the list as long as he or she remains staffed and in ACW, AVAIL, or on AUXIN/OUT extension calls from the AVAIL mode.
multi-user mode	A CMS state in which any administered user can log into CMS and data continues to be collected if the data collection feature is enabled.
Multiple Call Handling (MCH)	A process in which an agent receives an ACD call while other calls are active on the agent's station. The agent must put the current call on hold and press Auto-In/Manual-In to receive another ACD call.
multiple split queuing	A Call Vectoring capability that directs a call to up to three splits at the same time, with the first agent who is free receiving the call.
name (synonym) fields	A field in which you can input a name (synonym) that you have entered in the Dictionary. For example, you can input names of agents, splits/skills, agent groups, trunk groups, VDNs, or vectors.
night service	A switch capability that enables calls that arrive after business hours or on weekends to be automatically re-routed to a split, an announcement, or an alternate destination set up for after-hours coverage.
nonprimary split/skill	The second and third splits/skills to which a call queued to multiple splits/ skills queues in a VDN. Also called secondary and tertiary split/skill, respectively.
OTHER	An agent work mode in which the agent is on a direct agent call, on a call for another split or skill, or has put a call on hold and has not chosen another work mode.
Outbound Call Management (OCM)	A set of switch and adjunct features using ASAI that distributes outbound calls initiated by an adjunct to internal extensions (usually ACD agents).
percent within service level	The percentage of calls that you are expecting or targeting to be answered by an agent within a specific number of seconds.
phantom abandon call timer	A CMS capability that tracks information about abandoned calls. When the phantom abandon call timer is enabled, calls with a duration shorter than the administered value (0 to 10 seconds) are counted as phantom abandon calls. Setting the timer to 0 disables this capability.
previous interval	An intrahour interval that is part of the real-time database. At the end of each intrahour interval, the contents of the current intrahour interval are copied to the previous intrahour interval portion of the real-time database.
primary skill	A skill assigned to an agent as that agent's strongest skill. Primary skills are the areas in which the agent has the most expertise.

pseudo-ACD	An area created on CMS to place previously backed-up ACD data. A pseudo-ACD is not a live (real) ACD and does not communicate with any switch.
queue	A holding area for calls waiting to be answered in the order in which they were received. Calls in a queue may have different priority levels, in which case, calls with a higher priority are answered first.
QUEUED	A trunk state in which an ACD call has seized the trunk and is queued to a split/skill, waiting for an agent to answer.
read permission	A permission with which a CMS user can access and view data; for example, running reports or viewing the Dictionary subsystem.
real-time database	A CMS database consisting of the current intrahour data on each CMS- measured agent, split, trunk, trunk group, VDN, and vector.
real-time reports	A report that shows ACD call activity on agents, split/skills, trunks, trunk groups, VDNs, and vectors for the current or previous intrahour interval.
Redirect On No Answer	An ACD capability that assist the user if a call is not answered in a specified number of rings. The terminal extension, including ports with VRUs, is busied out and the call goes back into the queue at top priority.
refresh rate	The number of seconds that CMS should wait for each update of real- time report data.
reserve agent	An agent whose skills are set so that they do not have a top skill, but are used to handle calls when all other agents of that skill are unavailable. Reserve agents are used for high-priority skills where customers must not wait for long periods of time.
RINGING	1) An agent state consisting of the time a call rings at an agent's voice terminal after leaving the queue and before the agent answers the call.
	2) A trunk state in which a call is ringing at the agent's voice terminal.
rolling ASA	A running, weighted, average calculation made without using interval boundaries. Rolling ASA is used for vector routing; it is calculated on the Communication Manager system and set to CMS.
screen-labeled key (SLK)	The first eight function keys at the top of the keyboard that correspond to the screen labels at the bottom of the CMS ASCII terminal screen. The screen labels indicate each key's function.
scripting	A CMS Supervisor capability that allows you to automate operations such as changing an agent's skills, running a report, and exporting report data.

secondary skill	A skill assigned to an agent in a subject that is not that agent's strongest area of expertise. Secondary skills are used in Communication Manager systems with Expert Agent Selection (EAS).
SEIZED	A trunk state in which an incoming or outgoing call is using the trunk.
service level	A time, in seconds, within which all calls should be answered. Also called acceptable service level.
Service Observing - Remote	A feature that allows a user to dial into the switch and monitor a call.
Service Observing - VDNs	A feature available with Communication Manager systems that give a user the ability to monitor the treatment that a call receives as it is processed by a VDN.
shortcut	A series of tasks which, when run, are performed on the CMS server. Shortcuts are a fast, easy way to view windows every day for the same ACD entities.
single-user mode	A CMS mode in which only one administrator can log in to the CMS server. Data continues to be collected if the data collection feature is enabled.
skill	See <u>agent skill</u> on page 546.
skill level	A rating from 1 (highest) to 16 (lowest) that indicates an agent's level of expertise in handling calls for which that expertise is needed.
split	A group of extensions that receive calls.
staffed agent	An agent who is currently logged in to the switch.
standard reports	The set of reports that are supplied with CMS or CMS Supervisor.
station	1) An unmeasured extension
	<ol> <li>An extension that is not currently staffed by an agent or that is a member of an unmeasured split/skill.</li> </ol>
switch	A system providing voice or voice/data communication services for a group of terminals.
timetable	A CMS feature that allows you to schedule one or more activities to run unattended. Timetables can be set to run once or at multiple times.
trunk	A telephone circuit that carries calls between two switches, between a central office and a switch, or between a central office and a telephone.

trunk group	A group of trunks that are assigned the same dialing digits: either a phone number or a direct inward dialed (DID) prefix.
uniform call distribution (UCD)	A method of call distribution in which the most idle agent for a skill receives the call (if the agent is available).
universal call identifier (UCID)	A number that uniquely identifies a call in a network of nodes that support UCID.
UNKNOWN	1) An agent state in which CMS does not recognize the state of the agent.
	2) A trunk state in which CMS does not recognize the state of the trunk.
UNSTAF	An agent state in which the agent is not logged in and, therefore, is not tracked by CMS.
VDN	See <u>Vector Directory Number (VDN)</u> on page 557.
VDN calls-counted	See <u>active VDN calls</u> on page 545.
VDN of Origin Announcement (VOA)	A short announcement that is assigned to a VDN through switch administration. The VOA identifies the origin or purpose of a call for the call center agent who answers the call.
VDN skill preference	A prioritized list of agent skills administered for a VDN that are needed or preferred for the answering agent. VDN skill preferences require a call to be routed to an ACD agent with a particular attribute or set of attributes.
vector	A list of steps that process calls according to a user definition. The steps in a vector can send calls to splits, play announcements and music, disconnect calls, give calls a busy signal, or route calls to other destinations based on specific criteria.
vector command	A step in a vector that describes the action to be executed for a call.
Vector Directory Number (VDN)	An extension number that enables calls to connect to a vector for processing. A VDN can connect calls to a vector when the calls arrive over an assigned automatic-in trunk group or when the calls arrive over a DID trunk group and the final digits match the VDN. The VDN by itself may be dialed to access the vector from any extension connected to the switch.
vector step	A single task within a vector that performs an action regarding a call. A vector step consists of a command with the possibility of one or more conditions or parameters, if necessary.
vector step condition	A condition accompanying a vector command that defines the circumstances in which the command is applied to a call.
VOA	See <u>VDN or Origin Announcement (VOA)</u> on page 557.

voice terminal	A telephone set, usually with buttons.
weekly data	Daily data that has been converted to a weekly summary.
write permission	A permission with which a CMS user can add, modify, or delete data and execute processes.

# Index

#### Α

accessing port matrix	
accessing script options	
accessing scripts	<u>484</u>
ACD	
administrative interface	
settings	
settings, viewing	
setup	<u>320</u>
user permissions	
ACD access permissions	
adding	<u>248</u>
deleting	
modifying	
viewing	
ACD administration	
ACD Administration Log field descriptions	
ACD Administration Log report	
ACD-for-migration description	
ACD from an ACD group	
deleting	152 157
ACD group benefits	
	<u>140</u>
ACD group contents	150 154
viewing	<u>150</u> , <u>154</u>
ACD group name	450
modifying	
renaming	
ACD groups	
adding	<u>150</u> , <u>155</u>
Call Center Administration	
deleting	
listing	
ACD groups feature interfaces	<u>149</u>
ACD groups in the Dictionary	
before using	
permissions	
ACD Groups in the Dictionary	
List all	
view contents	<u>51</u>
ACD name	
deleting	<u>47</u> , <u>49</u>
ACD names	<u>45</u>
permissions	<u>46</u>
ACD status	
field descriptions	<u>421</u>
viewing	<u>420, 421</u>
ACD to an ACD group	
adding	<u>151, 15</u> 5
ACD user permissions	
adding	<u>25</u> 0
listing all	
viewing	
5	

adding	100	106
	. <u>123</u> ,	120
ACD access permissions		
ACD groups		
ACD to an ACD group		
ACD user permissions		
agent exceptions	. <u>277</u> ,	<u>278</u>
agent group	<u>53</u> ,	<u>216</u>
agents to agent group	<u>55</u>	5, <u>58</u>
AUX reason code name	68	3, 71
backup/restore devices	405.	407
call work code names		
call work codes		
constants		
custom database items		
custom menu		
custom menu access permissions		
location ID		
login ID name		
logout reason code name		
printer	. <u>410</u> ,	<u>412</u>
pseudo-ACD		
split/skill user permissions		
split or skill call profiles	. <u>167</u> ,	<u>171</u>
split or skill exceptions		
split or skill name		
split or skill user permissions		
tenant data user permissions		267
trunk group data user permissions		
trunk group name		
trunk group user permissions		
users		
VDN call profile	.180.	183
VDN data user permissions	260	263
VDN name		
vector data user permissions		
vector name		
adding a Full Maintenance Backup Timetable for an	ACD	396
adding an ACD name		
adding an agent group		
administering		
call center features		
custom menu items and access		
split or skill exceptions		
splits		
tenant features		
tenants		
trunk group exceptions		
user permissions		
users		
VDN assignments		
VDN exceptions		
VDN skill preferences		
vector exceptions		<u>302</u>

	<u>409</u>
administration	
reports	<u>428</u>
Advanced Debugging window	<u>427</u>
agent	
changing skills	193
exceptions	
exceptions, definitions	
exceptions, report	
templates, changing skills for	
tenant	
	<u>515</u>
agent exceptions	077 070
adding	
deleting	
modifying	
agent group	
adding	
deleting	<u>54, 57</u>
listing agents	<u>54</u> , <u>57</u>
agent group members	
running a report	<u>431</u>
agent groups	52
tenant	
agents	
adding to an agent group	55 58
administering	
deleting from an agent group	
multiple, adding to another skill	
multiple, moving from skill to skill	
agent skills	
	100
adding	
adding changing	<u>191</u>
adding changing deleting	<u>191</u> <u>192</u>
adding changing deleting agent string value field descriptions	<u>191</u> <u>192</u> <u>60</u>
adding changing deleting agent string value field descriptions agent string values	<u>191</u> <u>192</u> <u>60</u> <u>59</u>
adding changing deleting agent string value field descriptions agent string values permissions	<u>191</u> <u>192</u> <u>60</u> <u>59</u> . <u>59</u>
adding changing deleting agent string value field descriptions agent string values	<u>191</u> <u>192</u> <u>60</u> <u>59</u> . <u>59</u>
adding changing deleting agent string value field descriptions agent string values permissions	<u>191</u> <u>192</u> <u>60</u> <u>59</u> . <u>59</u>
adding changing deleting agent string value field descriptions agent string values permissions agent trace	
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space	<u>191</u> <u>192</u> <u>60</u> <u>59</u> <u>59</u> <u>203</u> – <u>205</u> <u>338</u>
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating	<u>191</u> <u>192</u> <u>60</u> <u>59</u> <u>59</u> <u>203</u> – <u>205</u> <u>338</u>
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID see automatic number identification/station num	<u>191</u> <u>192</u> <u>60</u> <u>59</u> <u>203–205</u> <u>338</u> <u>34</u> nber
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID see automatic number identification/station num	<u>191</u> <u>192</u> <u>60</u> <u>59</u> <u>203–205</u> <u>338</u> <u>34</u> nber
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID	<u>191</u> <u>192</u> <u>60</u> <u>59</u> <u>203–205</u> <u>338</u> <u>34</u> nber
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID see automatic number identification/station num identification announcement name	
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID see automatic number identification/station num identification announcement name adding	
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID see automatic number identification/station nun identification announcement name adding deleting	
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID see automatic number identification/station nun identification announcement name adding deleting listing	
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID see automatic number identification/station nun identification announcement name adding deleting listing modifying	
adding changing deleting agent string value field descriptions agent string values permissions agent trace allocating disk space Already exists status message ANI/SID see automatic number identification/station nun identification announcement name adding deleting listing modifying viewing	
adding	
adding	<u>191</u> <u>192</u> <u>60</u> <u>59</u> <u>203–205</u> <u>203–205</u> <u>338</u> <u>338</u> <u>434, 442</u> <u>62, 65</u> <u>64, 66</u> <u>65, 64</u> <u>62</u> , 64 <u>62</u>
adding	<u>191</u> <u>192</u> <u>60</u> <u>59</u> <u>203–205</u> <u>203–205</u> <u>338</u> <u>34</u> nber <u>434, 442</u> <u>62, 65</u> <u>64, 66</u> <u>65, 64</u> <u>62, 64</u> <u>62</u> <u>62</u> <u>359</u>
adding	
adding	
adding	
adding	

assigning <i>(continued)</i> custom menu access permissions	<u>231</u>
automatic number identification/station number id	dentification
	<u>434</u> , <u>442</u>
AUX reason code name	
deleting	<u>69</u> , <u>72</u>
AUX reason code names	<u>67</u>
adding	<u>68</u> , 71
before administering	
listing	
modifying	
viewing	
Avaya support website	
,	

#### В

backing up
pseudo-ACDs <u>330</u>
backing up data scenario
pseudo-ACD <u>329</u>
backing up real ACD data to load on a pseudo-ACD <u>328</u>
backup
adding a full maintenance backup timetable for an ACD
before adding a full maintenance backup timetable for an
ACD
binary database backup
CMSADM <u>375</u> , <u>381</u>
data <u>374</u>
duration of standard full Maintenance Backup to tape
<u>379</u>
maintenance <u>375</u> , <u>385</u>
maintenance backup <u>387</u> , <u>389</u>
performing a CMSADM backup
recovery kit
USB/network backup restore devices <u>376</u>
backup/restore device
viewing <u>404,</u> <u>406</u>
backup/restore devices
adding <u>405, 407</u>
deleting <u>406, 408</u>
listing all <u>407</u>
modifying
backup and restore
alternative methods <u>378</u>
considerations
factors <u>377</u>
reducing times <u>377</u>
backup check
Backup Data window
backup error messages <u>391</u>
backup information
how to interpret <u>391</u>
backup volume
labeling
before adding a Full Maintenance Backup Timetable for an
ACD
<u></u>

before administering access to ACDs
before administering access to trunk group data239
before administering a printer
before administering call center features <u>147</u>
before administering passwords
before administering report properties <u>415</u>
before administering split or skill access
before administering storage intervals <u>344</u>
before backing up data for a pseudo-ACD <u>328</u>
before changing agent skills <u>189</u>
before changing extension split assignments
before changing skills for multiple agents <u>198</u>
before changing the intrahour interval
before configuring CMS system settings
Before deleting CMS users
before listing agents traced <u>206</u>
before loading pseudo-ACD data
before migrating data <u>367</u>
before modifying data storage allocation <u>339</u>
before modifying data summarizing settings
before modifying switch time zone <u>347</u>
before moving extensions between splits <u>210</u>
before performing a CMSADM backup <u>381</u>
before performing a maintenance backup
before restoring data <u>398</u>
before using
ACD groups in the dictionary <u>50</u>
before using ACD Administration Log report
before using ACD groups <u>147</u>
before using agent exceptions
before using calculations
before using call work codes
before using CMS state
before using custom database items
before using Data Storage Allocation
before using exceptions <u>274</u>
before using External Application Status
before using Free Space Allocation <u>342</u>
before using login ID names <u>101</u>
before using logout reason code names <u>106</u>
before using Maintenance Error Log 456
before using pseudo-ACDs <u>323</u>
before using shortcuts
before using split or skill exceptions
before using split or skill names <u>112</u>
before using split or skill string values <u>117</u>
before using Switch Setup
before using tenant access
before using the Maintenance window
before using the operating system
before using the User Permissions subsystem
before using trunk group exceptions
before using trunk group members report
before using trunk group names
before using VDN access
before using VDN assignments 177
before using VDN call profiles <u>179</u>

before using VDN exceptions	<u>295</u>
before using VDN names	136
before using VDN skill preferences	
before using vector access	
before using vector configuration report	
before using vector exceptions	
before using vector names	
before viewing ACD status	
-	
before viewing CMS users	<u>214</u>
before viewing trunk group assignments	<u>174</u>
before you begin scripting CMS operations	<u>483</u>
binary backup	
to a network device	<u>395</u>
to a USB storage device	
binary database backup	
, , , , , , , , , , , , , , , , , , , ,	

#### С

calculating data space
CMSADM backup <u>381</u>
for CMS full maintenance backup
calculation names
adding <u>74</u>
viewing <u>74</u>
calculations
adding <u>77</u>
deleting <u>76</u> , <u>79</u>
listing all <u>77</u>
modifying <u>75</u> , <u>78</u>
viewing
Call Center Administration
ACD groups <u>147</u>
call center features
administering <u>147</u>
call handling preference
changing
call profiles
split or skill <u>166</u>
Call Vectoring
capabilities of <u>24</u>
Call Work Code
tenant <u>315</u>
call work code 0 <u>159</u>
call work code names
adding <u>80</u> , <u>83</u>
deleting <u>82</u> , <u>84</u>
listing all <u>83</u>
modifying
viewing
call work codes
adding <u>160,</u> <u>162</u>
configuring <u>158</u>
deleting
listing all
unassigned
viewing <u>159</u> , <u>161</u>
Cancelled status message <u>34</u>

change agent skills	
web client	<u>190</u>
changing	
agent skills	
CMS state	
exception notification	
master ACD	
passwords	
VDN skill preferences	
changing agent string value descriptions	
changing skills for multiple agents	
chunks	<u>29</u>
CMSADM backup	. 375, 381
CMS database items	
standard	120
CMS state	
changing	
CMS Tenancy feature	<u>309</u>
collection	
delete	<u>540</u>
edit name	
generating PDF	<u>540</u>
sharing content	
colors, reports	
colors threshold	
common features	····· <u>vv</u>
Web Client	30
Communications Tab	<u>37</u> , <u>40</u>
contiguiring	
configuring	
system settings	
system settings Configuring LDAP	<u>426</u>
system settings Configuring LDAP connection status	
system settings Configuring LDAP	
system settings Configuring LDAP connection status field descriptions	<u>426</u> <u>416</u> <u>418</u>
system settings Configuring LDAP connection status field descriptions viewing	<u>426</u> <u>416</u> <u>418</u> <u>417</u>
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring	<u>426</u> <u>416</u> <u>418</u> <u>417</u> <u>376</u>
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g	426 416 418 417 <u>417</u> <u>376</u> groups . <u>52</u>
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent of constants	426 416 418 417 376 groups . <u>52</u> <u>85</u> 85, 87
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent of constants adding deleting listing	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent of constants adding deleting listing modifying	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent of constants adding deleting listing wodifying viewing	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent of constants adding deleting listing modifying	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent of constants adding deleting listing wodifying viewing content	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing wodifying viewing content publishing PDF output	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying agent group	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying agent group creating	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying agent group creating new report color scheme	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying agent group creating	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying agent group creating new report color scheme	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying agent group creating new report color scheme custom database items adding	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying agent group creating new report color scheme custom database items adding deleting deleting	
system settings Configuring LDAP connection status field descriptions viewing considerations when backing up or restoring considerations when sizing and reporting on agent g constants adding deleting listing modifying viewing content publishing PDF output searching sharing sort by last updated watching for updates copying agent group creating new report color scheme custom database items adding	

custom database items (continued)	
viewing	<u>89</u> , <u>91</u>
custom menu	
adding	<u>352</u>
deleting	<u>353</u>
modifying	<u>353</u>
viewing	
custom menu access permissions	
adding	<u>229</u>
assigning	
listing all	
modifying	
viewing	
custom menu items	
custom menu items and access	
administering	
0	

## D

data
historical, migrating <u>368</u> , <u>369</u>
migrating
storage, allocating
data archiving
data backup
Database constants
database items
custom <u>89</u>
data collection
disabling
enabling <u>358</u>
report
turning on and off <u>357</u> , <u>358</u>
data restore <u>456</u>
Data Storage Allocation
field definitions <u>339</u>
modifying <u>339</u>
data summarization time zone <u>186</u> , <u>361</u> , <u>362</u>
Data summarization time zone fields <u>187</u>
data summarizing <u>26, 344, 359–361</u>
settings, modifying <u>348</u>
data summarizing time settings
modifying <u>349</u> , <u>350</u>
date and time on status indicator
dbspace
dbspaces
contents, viewing
Default ACD
defining entity formats <u>40</u> definitions
split or skill exceptions
deleting ACD access permissions249, 251
ACD access permissions
ACD groups
agent exceptions
agent group
ugoni group

deleting (continued)	
agents from an agent group <u>55</u> , <u>58</u>	
announcement name	
AUX reason code name	
backup/restore devices	
calculations	
call work code names84	
call work code names, deleting	
call work codes	
constant	
custom database items <u>91</u> , <u>93</u>	
custom menu <u>353</u>	
location ID <u>98, 100</u>	
login ID name <u>103, 105</u>	
logout reason code name <u>108</u> , <u>111</u>	
printer	
pseudo-ACDs	
skill name	
split or skill call profile <u>169, 173, 235</u>	
split or skill exceptions	
split or skill name	
tenant data user permissions	
tenant name	
trunk group data user permissions	
trunk group data user permissions	
Users	
VDN call profile	
VDN data user permissions	
VDN name	
vector data user permissions	
vector name <u>143</u> , <u>146</u>	
devices	
backup/restore <u>404</u>	
dictionary	
before using <u>43</u>	
global search results <u>45</u>	
searching	
Dictionary	
ACD Groups	
ACD Groups in the Dictionary51	
ACD name, deleting	
agent group members report, running	
announcement name, adding62, 65	
announcement name, viewing	
calculation names <u>74</u>	
calculations	
call work code names, listing all	
call work codes	
constants	
custom database items	
location ID, listing all	
location IDs	
login ID names	
logout reason code names	
reports, printing	
searching	
split/skill names	

Dictionary (continued)	
split/skill string values	<u>117</u>
standard CMS database items	<u>120</u>
trunk group names	<u>127</u>
trunk string values	<u>132</u>
trunk string values, field descriptions	
VDN names	<u>135</u>
vector names	<u>141</u>
dictionary, overview	<u>42</u>
Dictionary ACDs Report	
Dictionary Login Identifications Report	<u>429</u>
Dictionary rules	<u>43</u>
Dictionary Standard CMS Items Report	<u>429</u>
Dictionary tenant report	<u>429</u>
Dictionary Trunk Groups Report	<u>430</u>
Dictionary VDNs Report	<u>430</u>
Dictionary Vectors Report	<u>430</u>
direct agent calls	
changing skills	<u>195</u>
disabling	
data collection	<u>358</u>
disk space	
allocating	
documentation	
documentation center	
finding content	
navigation	
documentation portal	
finding content	<u>540</u>
navigation	
Does not exist status message	
duration of standard full maintenance backup to tape	<u>379</u>

## Ε

EAS (see Expert Agent Selection), Expert Agent Selection  $\underline{24}$  EAS (See Expert Agent Selection), Expert Agent Selection

EAG (Gee Expert Agent Gelection), Expert Agent Gelection	on
	<u>189</u>
enabling	
data collection	
entity formats, defining	<u>40</u>
error and warning messages	<u>492</u>
error log messages	
maintenance	<u>458</u>
Error status message	<u>34</u>
events that start or stop data collection	<u>31</u>
exception capacities	<u>273</u>
exception counter	
exception notification	
changing	<u>275</u>
exception reports	431
exceptions	
agent	
agent, definitions	
agent, report	2, 439
data collection433	
definition	

exceptions (continued)	
malicious call trace report <u>434</u> ,	<u>442</u>
notification	
real-time exceptions log	
split/skill, report	
split or skill	
trunk group	<u>290</u>
trunk group, adding	<u>292</u>
trunk group, deleting	
trunk group, modifying	
trunk group, report	<u>445</u>
VDN, adding	<u>297</u>
VDN, deleting	<u>299</u>
VDN, modifying	<u>298</u>
VDN, report	<u>446</u>
vector	<u>301</u>
vector, adding	<u>303</u>
vector, deleting	<u>305</u>
vector, modifying	<u>304</u>
vector, report	<u>448</u>
export	
report output	<u>488</u>
Export All Data window	<u>488</u>
Export Chart Data window	<u>488</u>
extensions	
split assignments, changing	<u>208</u>
splits, moving between	
external applications	
starting or stopping	<u>366</u>
states, viewing	<u>365</u>
External Application Status feature	<u>364</u>
disabling	<u>365</u>
enabling	<u>365</u>

### F

Failed status message	<u>34</u>
Feature Access	
user permissions, listing all	<u>227</u>
user permissions, modifying	<u>228</u>
feature access permissions	<u>225</u>
modifying	<u>226</u>
viewing	<u>226</u>
field definitions	
Data Storage Allocation	<u>339</u>
user	<u>217</u>
field descriptions	
split or skill string value	
finding content on documentation center	<u>540</u>
finding port matrix	<u>539</u>
firewall status	
viewing	<u>424</u>
First Day of Week	<u>35</u>
Free Space Allocation	<u>341</u>
contents, viewing	<u>343</u>
viewing <u>3</u>	<u>42, 343</u>

### G

generic string values	
modifying	<u>94, 95</u>
viewing	<u>94</u> , <u>95</u>
generic string value synonyms	<u>94</u>
getting started with CMS Supervisor	<u>32</u>
global search results	

#### Η

historical data	
archiving	<u>360, 361</u>
historical databases	<u>25</u>
how CMS tracks ACD data	<u>30</u>

#### I

Informix Dynamic Server (IDS) Informix Software, Inc. INFORMIX	<u>341</u>
interface to historical database	<u>24</u>
input window	
scripting	<u>489</u>
InSite Knowledge Base	<u>542</u>
interactive and automatic scripts	<u>484</u>
interactive report script	
creating	<u>487</u>
interrupt type associated with the skill	
changing	<u>196</u>
interval	
intrahour	344
intervals	
storage	
intrahour interval	
modifying	

## L

LDAP integration	<u>425</u>
license status	
viewing	<u>424</u>
listing	
ACD groups	<u>149, 153</u>
announcement name	
AUX reason code names	
constants	
custom database items	
custom menu access permissions	
login ID name	
logout reason code name	
split or skill name	
trunk group names	
VDN name	
vector name	
listing agents in an agent group	
listing agents traced	
5 5	

listing all
ACD user permissions
backup/restore devices407
call work codes <u>161</u>
printers
trunk group user permissions
VDN data user permissions
VDN skill preferences
vector data user permissions <u>256</u>
loading data
pseudo-ACDs
location ID
deleting <u>98, 100</u>
modifying <u>97, 99</u>
viewing
location IDs
adding <u>96,</u> <u>99</u>
logging in to CMS
login ID name
adding <u>102, 104</u>
deleting <u>103, 105</u>
listing
modifying
viewing
login ID names <u>100</u>
login status <u>34</u>
logout reason code name
adding <u>107, 110</u>
deleting <u>108, 111</u>
listing all <u>109</u>
modifying <u>108, 110</u>
viewing <u>107, 109</u>
logout reason code names <u>106</u>

#### Μ

Main Menu Addition	<u>352</u>
Main Menu Addition access	<u>229</u>
maintenance	
reports	
maintenance backup	
	<u>979</u> , <u>909</u>
maintenance error log	457
report	
Maintenance Error Log	
running	<u>456</u>
Maintenance Error Log messages	<u>458</u>
maintenance reports	
making changes	
finishing	<u>198</u>
malicious call trace	
report	434, 442
master ACD	
changing	<u>356</u>
methods for backup and restore, alternative	378
Migrate Data field descriptions	
migrating	<u></u>
from a non-tape device	379
	<u>070</u>

migrating data	<u>367</u> – <u>369</u>
modifying	
ACD access permissions	<u>248, 251</u>
ACD group name	<u>156</u>
agent exceptions	
agent string value descriptions	
announcement name	
AUX reason code name	
backup/restore devices	
call work code names, modifying	
constants	
custom calculation	75 78
custom database items	<u>75,70</u>
custom menu	
custom menu access permissions	<u>229, 231</u>
Data Storage Allocation	
data summarizing time settings	
feature access permissions	
generic string values	
intrahour interval	
location ID	
login ID name	
logout reason code name	<u>108, 110</u>
printer options	<u>411, 413</u>
report properties	<u>415, 416</u>
skill name, modifying	<u>113</u>
skill string values	<u>118</u>
split/skill user permissions	<u>237</u>
split or skill call profile <u>16</u>	
split or skill exceptions	
split or skill name, modifying	
split or skill string values	
switch time zone	
tenant data user permissions	
tenant name	
trunk group data user permissions	
trunk group name	
trunk string value	
users	
VDN call profile	
VDN data user permissions	
•	
VDN name	
vector data user permissions	
vector name	
modifying an ACD name	
mounted volume contains CMS data	
Mounted volume is bad	
multi-agent skill change	<u>199</u>
multiple agents	
applying changes	<u>197</u>
multi-user mode	
setting	
My Docs	<u>540</u>
Ν	
Name Format Tab	<u>40</u>

new percent allocation	
specifying	<u>196</u>
new report color scheme, creating	<u>38</u>
N matches found	34
No CMS access to specified device	<u>3</u> 91
No matches found status message	
No permission status message	
notification	

## 0

operating system, using <u>494</u> Options	<u>4</u>
Communications Tab40	n
Default ACD	
First Day of Week <u>38</u>	
general <u>38</u>	
Name Format Tab <u>40</u>	<u>0</u>
report colors <u>37</u>	7
threshold colors	9
time synchronization	5
Options	
Communications Tab	7
Options window, before using34	_

#### Ρ

password	
aging	<u>498</u>
passwords	
changing	<u>223, 224</u>
choosing	
PC Client tenant administration sub-menus	<u>313</u>
permissions	
ACD	<u>246</u>
ACD groups in the Dictionary	<u>50</u>
ACD names	<u>46</u>
ACD status	<u>420</u>
adding a CMS user	<u>216</u>
administer access to ACDs	
agent exceptions	<u>276</u>
agent groups	<u>52</u>
agent string values	<u>59</u>
announcement names	<u>62</u>
archiving status	<u>422</u>
AUX reason code names	
backing up data for a pseudo-ACD	<u>330</u>
backup or restore devices	<u>404</u>
calculation names	<u>73</u>
call work codes	<u>159</u>
CMSADM backup	
CMS State	<u>355</u>
connection status	<u>416</u>
constants	<u>85</u>
custom database items	<mark>89</mark>
custom menu access	<u>230</u> , <u>2</u> 31
custom menu items and access	229

permissions (continued)	
data collection	
Data Storage Allocation	
data summarizing	
Dictionary reports	
feature access	
for ACD Administration Log report	
for ACD groups	
for call work codes	
for changing agent skills	
for changing extension split assignments	
for changing skills for multiple agents	
for External Application Status	
for listing agents traced	
for moving extensions between splits	
for running a split members report	
for shortcuts	
for standard CMS database items	
for starting or stopping an agent trace	
for timetables	
for trunk group members report	
for vector configuration report	
Free Space Allocation	
generic string values synonyms	
loading pseudo-ACD data	
location IDs	
login IDs	
logout reason code names	
maintenance backup	
migrating data	
modifying users	
printer administration pseudo-ACDs	
report properties	
restoring data	
split/skill, deleting user	
split/skill, listing all split/skill, modifying user	
split/skill names	
split or skill access	
split or skill call profiles	
split or skill exceptions	
split or skill string values	
storage intervals	
Switch Setup	
tenant access	
tenant names	
trunk group, deleting user	
trunk group assignments	
trunk group data	
trunk group exceptions	
trunk group exceptions	
trunk string values	
user, listing all Feature Access	
user, modifying Feature Access	
VDN access	
VDN assignments	
	·····

permissions (continued)
VDN call profiles <u>179</u>
VDN exceptions <u>296</u>
VDN names
VDN skill preferences <u>163</u>
vector access
vector exceptions <u>302</u>
viewing users <u>214</u>
permitted ones displayed <u>34</u>
phantom abandon call timer <u>320</u>
port matrix
printer
adding
deleting
printer options
modifying <u>411</u> , <u>413</u>
printers
listing all <u>412</u>
viewing
pseudo-ACD
adding <u>325</u>
pseudo-ACD data
loading <u>332</u>
pseudo-ACDs
backing up
deleting <u>324,</u> <u>328</u>
loading data <u>334</u> , <u>335</u>
viewing <u>324,</u> <u>325</u>
Pseudo-ACDs <u>322</u>

### R

real-time exceptions log3	307
reboot your CMS server3	
recovery kit	
reducing tape backup and restore times	
related documentation5	<u>535</u>
report	
ACD Administration Log4	55
trunk group members	
vector configuration	
report colors	
report properties	
modifying <u>415</u> , <u>4</u>	16
reports	
Tepena	
ACD Administration Log4	54
ACD Administration Log4	
ACD Administration Log4 administration	28
ACD Administration Log	<u>28</u> <u>39</u>
ACD Administration Log	<u>28</u> <u>39</u> 41
ACD Administration Log	28 39 41 28
ACD Administration Log	28 39 41 28 30
ACD Administration Log	28 39 41 28 30 31
ACD Administration Log	28 39 41 28 30 31
ACD Administration Log	28 39 41 28 30 30 31 39
ACD Administration Log       4         administration       4         colors       4         data collection       433, 4         Dictionary       4         Dictionary, printing       4         exceptions       4         exceptions, agent       432, 4         exceptions, trunk group       436, 4	28 39 41 28 30 30 31 39 45
ACD Administration Log       4         administration       4         colors       4         data collection       433, 4         Dictionary       4         Dictionary, printing       4         exceptions       4         exceptions, agent       432, 4         exceptions, trunk group       436, 4         maintenance       4	28 39 41 28 30 30 31 39 45 45 28
ACD Administration Log       4         administration       4         colors       4         data collection       433, 4         Dictionary       4         Dictionary, printing       4         exceptions       4         exceptions, agent       432, 4         exceptions, trunk group       436, 4	128 39 141 128 130 131 139 145 128 157

reports (continued)	
members, trunk group	<u>449</u>
split/skill, exceptions	<u>435</u> , <u>443</u>
split members, running	
tenant agent group members	<u>453</u>
tenant agent groups	<u>453</u>
VDN, exceptions	<u>437</u> , <u>446</u>
vector, exceptions	<u>438</u> , <u>448</u>
reports saved as HTML	<u>488</u>
restore	
automatic	
manual	<u>400</u> , <u>402</u>
restore check	<u>333</u>
restore database from a binary backup	<u>404</u>
restore error messages	<u>391</u>
restoring	
from a non-tape device	<u>379</u>
restoring data	<u>398</u> , <u>456</u>
running	
ACD Administration Log report	<u>455</u>
running a split members report	<u>211</u>

## S

Save As HTML window
Save as Script - Action window
script
creating automatic <u>487</u>
creating to run reports <u>484</u>
exporting report output
to export report data as HTML
Script descriptions
scripting
tasks
scripting an action
scripting an input window
Scripting tab
scripts
accessing
organizing
searching for content
searching the dictionary
See status window message <u>34</u>
server <u>24</u>
service level
increment <u>167, 171</u>
increments <u>179</u>
settings
ACD
ACD, viewing
switch <u>321</u> , <u>322</u>
setting user ID and password
setting users
setup
ACD/switch <u>320</u>
severity of errors
sharing content

shortcuts	<u>499</u>
copying	<u>528</u>
copying tasks in	<u>529</u>
creating	<u>524</u>
deleting	<u>533</u>
description, modifying	<u>527</u>
overview	
running	
tasks, adding	<u>525</u>
tasks, deleting	
tasks, modifying	<u>531</u>
single-user mode	
setting	<u>355</u>
skill assigned to the agent or template	
removing	<u>196</u>
skill assignment for other agents	
changing	<u>198</u>
skill name	
deleting	
modifying	
viewing	<u>112</u>
skills	
multiple agents, changing	<u>201</u>
skills for multiple agents	
adding	
deleting	
moving	<u>200</u>
skill string values	
modifying	
viewing	
Solaris	
changing user passwords	
local login	
printer commands	
remote login	
sort documents by last updated	<u>540</u>
split	000
extension assignments, changing	
extensions, moving	
members report, running	<u>211</u>
split/skill exceptions, report	112
user permissions, deleting	<u>443</u>
user permissions, deleting user permissions, listing all	230
	230
split/skill exceptions adding	286
split/skill names	
split/skill user permissions	112
adding	227
viewing	
split or skill	233
call profiles	166
exceptions	
string values	
split or skill access	
split or skill call profile	202
deleting	225
<u>100</u> , <u>110</u> ,	

split or skill call profile <i>(continued)</i>
modifying <u>168</u> , <u>172</u> , <u>234</u>
viewing <u>167</u> , <u>170</u>
split or skill call profiles
adding <u>167, 171</u>
split or skill exceptions
administering
definitions <u>288</u>
deleting
modifying
split or skill name
adding <u>113, 115</u>
deleting
modifying
viewing
split or skill names
listing all
split or skill string value
field descriptions
split or skill string values
modifying
viewing
split or skill user permissions
adding
viewing
standard CMS database item
viewing
standard CMS database items
standard database items
viewing alphabetically
status indicators on controller window
status messages on Controller window
storage intervals
viewing
storeing ACD data
Successful status message
summarizing
data, modifying
support
switch settings
settings, viewing
setup <u>320</u>
switch time zone
modifying
synchronize
time zone
system settings
configuring <u>320</u>

### Т

table cannot be backed up	391
tape drives and cartridges	
tasks	
timetable, adding49	9, 504
timetable, modifying	

tasks scripts can automate <u>483</u>
tenant
agent <u>313</u>
agent groups
Call Work Code
trunk group
VDN <u>318</u>
vector <u>318</u>
tenant access <u>266, 269</u>
operations <u>270</u>
tenant administration reports
tenant agent group members
report
tenant agent groups
tenant agent groups
report
tenant data user permissions
adding <u>267</u>
deleting
modifying
viewing
tenant features
administering
tenant name
adding <u>123</u> , <u>126</u>
deleting <u>125, 127</u>
modifying <u>124</u> , <u>126</u>
viewing <u>123, 125</u>
tenant name permissions <u>123</u>
Tenant names
Before using
Listing all
tenants
Tenant split/skill assignment
tenant user access restrictions <u>310</u>
the agent or template
adding skill <u>196</u>
threshold colors <u>39</u>
time synchronization <u>35</u>
master ACD <u>356</u>
timetable
deleting
tasks, adding
timetables
backups
changing
copying
creating <u>499,</u> <u>501</u>
global edits <u>514</u>
listing all <u>506</u>
overview
prerequisites
scheduling
tasks, adding
tasks, copying <u>509</u>
tasks, modifying
timezone
adjustment, ACD

time zone	
offset, ACD	347
time zones	
updating	543
top skill for the agent	
assigning	197
trace	101
	206
agent, listing all records	
tracking CMS calls	<u>30</u>
trunk group	
assignments	
exceptions	
exceptions, adding	
exceptions, deleting	<u>294</u>
exceptions, modifying	293
exceptions, report	
members report	
tenant	
user permissions, deleting	
trunk group assignment	240
	175
viewing a single	
viewing by VDN or split	170
trunk group assignments	
viewing	
viewing all	
trunk group data access	<u>239</u>
trunk group data user permissions	
adding	241
deleting	
modifying	
viewing	
Trunk group exception definitions	
trunk group exceptions	
administering	290
trunk group members	200
report	450
	430
trunk group name	404
adding	
deleting <u>130</u> ,	
listing all	
modifying <u>129</u> ,	<u>131</u>
viewing	
trunk group names	<u>127</u>
listing	<u>131</u>
trunk group user permissions	
adding	244
listing all	
viewing	
trunk string values	
field descriptions	
modifying	
viewing	
turning data collection on and off	351
type associated with the skill	
changing	
types of exceptions	272

### U

USB/network backup restore devices3 user	<u>376</u>
field definitions2	217
user data2	
user permissions	
administering2	<u>213</u>
viewing2	
user permissions example2	<u>213</u>
users	
ACD permissions2	<u>246</u>
adding2	217
administering	
custom menu access permissions	
deleting2	<u>222</u>
modifying	<u>221</u>
permissions2	
permissions, deleting split/skill	
permissions, deleting trunk group	
permissions, list all split/skill2	
permissions, listing all Feature Access2	
permissions, modifying Feature Access2	
viewing2	
using split or skill call profiles1	166

#### V

VDN		
call profiles		179
exceptions, adding		<u>297</u>
exceptions, deleting		<u>299</u>
exceptions, modifying		298
exceptions, report4	<u>37</u> ,	446
tenant		
VDN access		259
VDN assignments		
administering		
modifying		
viewing		
viewing by vector		
VDN call profile		
adding1	<u>80</u> ,	<u>183</u>
deleting1	<u>82</u> ,	<u>185</u>
modifying1	<u>81</u> ,	<u>184</u>
viewing1	<u>80</u> ,	<u>182</u>
VDN data user permissions		
adding2	<u>'60</u> ,	<u>263</u>
deleting2	<u>'62</u> ,	<u>265</u>
listing all		<u>263</u>
modifying2	<u>'61</u> ,	<u>264</u>
viewing2	<u>'60</u> ,	<u>262</u>
VDN exceptions		<u>295</u>
administering		<u>296</u>
VDN name		
adding <u>1</u>	<u>37</u> ,	<u>139</u>
deleting1		

VDN name <i>(continued)</i>	
listing	139
modifying	
viewing	
VDN names	
VDN skill preferences	<u></u>
administering	163
changing	
listing all	
viewing	
vector	<u>104</u> , <u>105</u>
configuration report	451
exceptions	
exceptions, adding	
exceptions, deleting	
exceptions, modifying	
exceptions, report	
tenant	
vector access	<u>252</u>
vector configuration	
report	<u>451</u> , <u>452</u>
vector data user permissions	
adding	<u>254</u> , <u>256</u>
deleting	
listing all	<u>256</u>
modifying	<u>254</u> , <u>257</u>
viewing	<u>253</u> , <u>255</u>
vector exception definitions	<u>306</u>
vector exceptions	
administering	<u>302</u>
	<u>302</u>
administering vector name	
administering vector name adding	<u>142</u> , <u>145</u>
administering vector name adding deleting	<u>142</u> , <u>145</u> <u>143</u> , <u>146</u>
administering vector name adding deleting listing	<u>142,</u> <u>145</u> <u>143, 146</u> <u>144</u>
administering vector name adding deleting listing modifying	<u>142</u> , <u>145</u> <u>143</u> , <u>146</u> <u>144</u> <u>143</u> , <u>145</u>
administering vector name adding deleting listing modifying viewing	<u>142</u> , <u>145</u> <u>143</u> , <u>146</u> <u>144</u> <u>143</u> , <u>145</u> <u>142</u> , <u>144</u>
administering vector name adding deleting listing modifying viewing vector names	<u>142</u> , <u>145</u> <u>143</u> , <u>146</u> <u>143</u> , <u>144</u> <u>143</u> , <u>145</u> <u>142</u> , <u>144</u> <u>141</u>
administering vector name adding deleting listing modifying viewing vector names videos	<u>142</u> , <u>145</u> <u>143</u> , <u>146</u> <u>143</u> , <u>144</u> <u>143</u> , <u>145</u> <u>142</u> , <u>144</u> <u>141</u>
administering vector name adding deleting listing modifying viewing viewing videos viewing	<u>142</u> , <u>145</u> <u>143</u> , <u>146</u> <u>143</u> , <u>145</u> <u>142</u> , <u>144</u> <u>141</u> <u>541</u>
administering vector name adding deleting listing wodifying viewing videos videos viewing ACD access permissions	<u>142</u> , <u>145</u> <u>143</u> , <u>146</u> <u>143</u> , <u>145</u> <u>142</u> , <u>144</u> <u>141</u> . <u>541</u>
administering vector name adding deleting listing wodifying viewing videos videos viewing ACD access permissions ACD group contents	
administering vector name adding deleting listing wodifying viewing viewing videos videos viewing ACD access permissions ACD group contents ACD status	<u>142</u> , <u>145</u> <u>143</u> , <u>146</u> <u>143</u> , <u>145</u> <u>142</u> , <u>144</u> <u>142</u> , <u>144</u> <u>141</u> <u>541</u> <u>247</u> <u>150</u> , <u>154</u> <u>420</u> , <u>421</u>
administering vector name adding deleting listing wodifying viewing videos videos videos videos ACD access permissions ACD group contents ACD status ACD user permissions	
administering vector name adding deleting listing modifying viewing vector names videos videos videos videos ACD access permissions ACD group contents ACD group contents ACD status ACD user permissions announcement name	142, 145 143, 146 143, 145 142, 144 142, 144 
administering vector name adding deleting listing modifying viewing vector names videos videos videos videos ACD access permissions ACD group contents ACD group contents ACD status ACD user permissions announcement name archiving status	142, 145 143, 146 143, 145 142, 144 142, 144 
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\141\\541\\541\\247\\150, 154\\249\\249\\62, 64\\242\\62, 68, 70\\ \end{array}$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\541\\541\\541\\247\\150, 154\\247\\249\\249\\62, 64\\249\\62, 64\\242\\68, 70\\404, 406\end{array}$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\541\\541\\541\\247\\541\\247\\$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\541\\541\\541\\541\\$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\141\\541\\541\\$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\541\\541\\541\\541\\$
administering vector name adding deleting listing wodifying viewing vector names videos videos viewing ACD access permissions ACD group contents ACD group contents ACD status ACD status ACD status ACD user permissions announcement name archiving status AUX reason code name backup/restore device call work codes connection status constants custom database item	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\141\\541\\541\\$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\541\\541\\541\\$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\541\\541\\541\\$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\141\\541\\541\\$
administering vector name adding	$\begin{array}{c}142, 145\\143, 146\\143, 145\\142, 144\\142, 144\\141\\541\\$

viewing (continued)
generic string values
license status
location ID
login ID name
logout reason code name <u>107</u> , <u>109</u>
printers
pseudo-ACDs
real-time exceptions log <u>308</u>
skill name, viewing
skill string values
split/skill user permissions $\frac{235}{235}$
split or skill call profile <u>167</u> , <u>170</u>
split or skill name, viewing <u>114</u>
split or skill string values
split or skill user permissions
standard CMS database item <u>121</u>
standard database items <u>122</u>
storage intervals <u>345</u>
tenant data user permissions <u>267</u>
tenant name <u>123, 125</u>
trunk group assignments <u>174</u>
trunk group data user permissions
trunk group name <u>128, 130</u>
trunk group user permissions <u>242</u>
trunk string value <u>133</u>
user permissions <u>227</u>
users
VDN assignments <u>178</u>
VDN call profile <u>180</u> , <u>182</u>
VDN data user permissions <u>260</u> , <u>262</u>
VDN name <u>136, 138</u>
VDN skill preferences <u>164</u> , <u>165</u>
vector data user permissions <u>253, 255</u>
vector name <u>142, 144</u>
viewing all
trunk group assignments <u>175</u>
viewing a single
trunk group assignment <u>175</u>
viewing by VDN or split
trunk group assignment
volume mounted has errors
volume mounted is the last backup volume
Volume tape not mounted <u>391</u>

#### W

watch list	<u>540</u>
Web Client	
common features	<u>32</u>
week	
beginning of	<u>348</u>
end of	
work day	
start time	<u>348</u>
stop time	<u>348</u>